stonebranch workload Automation Simplified.


Universal Controller 6.3.x

Resources

© 2016 by Stonebranch, Inc. All Rights Reserved.

1. Resources	3
1.1 Resources Overview	4
1.2 Agents	5
1.2.1 Linux Unix Agent	12
1.2.2 Windows Agent	16
1.2.3 zOS Agent	20
1.3 Agent Clusters	24
1.4 OMS Servers	
1.5 Cluster Nodes	37
1.6 Virtual Resources	42
1.7 Scripts	48
1.8 Email Templates	53
1.9 Email Connections	
1.10 Database Connections	
1.11 SAP Connections	
1.12 SNMP Managers	66

Resources





The information on these pages also is located in the Universal Controller 6.3.x Resources.pdf.

Resources Overview

Universal Controller resources are records that both define your Universal Automation Center system and that you set up to help facilitate operations:

Agents	Universal Agents, running programs on one or more remote machines, connected to the Controller via Universal Message Service (OMS): Linux/Unix Windows z/OS
Agent Clusters	Groups of Agents from which the Controller uses pre-defined parameters to select the most appropriate agent for a task.
OMS Servers	Network communication provider between Universal Controller 6.3.x and Universal Agent.
Cluster Nodes	Controller instances.
Virtual Resources	Allow you to create throttling schemes for tasks.
Scripts	Allow you to execute scripts stored in the Controller database.
Email Templates	Allow you to construct information that can be copied to create Email tasks.
Email Connections	Provide email server information required for the Controller to send an email.
Database Connections	Provide database server information required for running SQL tasks and Stored Procedure tasks.
SAP Connections	Provide SAP server information required for running SAP tasks.
SNMP Managers	Allow you to generate SNMP notifications.
Application Resources	Define the names of applications being monitored.

Agents

- Agents
- Displaying Agent Details
- Starting and Stopping Agents
- Suspending Agents, Agent Clusters, and Agent Cluster Memberships
 - Suspending an Agent
 - Suspending an Agent Cluster
 - Suspending an Agent Cluster Membership
- Resetting the Current Task Count
- Sending Notifications on Status of an Agent
 - Email Notification Details
 - Email Notification Details Field Descriptions
 - SNMP Notification Details
 - SNMP Notification Details Field Descriptions

Agents

Agent resources refer to Universal Agents, running programs on one or more remote machines, connected to the Controller via Universal Message Service (OMS).

OMS must be running in order for you to run tasks on an Agent.

There are three types of Agents:

- Linux/Unix Agent
- Windows Agent
- z/OS Agent

Displaying Agent Details

When you start an Agent for the first time, the Controller automatically creates a database record for that Agent. You can view these records for details and status information.

(You also can view status information about Agents from the Command Line Interface (CLI).)

✓ 9 Linux/Unix Agents		Custom Filter Unsaved 1			~	👻 🦁 Filter 🔯 Go To 🍣		
Agent Name A	Host Name	Agent Id	Version	Last Heartbeat	Current Task Count	Suspended	Status	Started Date
aix61.stone.branch - AIX61	aix61.stone.branch	AIX61	6.3.0.1	2016-04-28 09:33:09 -0400			Active	
centerpoint.stone.branch - centerpoint	centerpoint.stone.branch	centerpoint	6.2.0.0	2016-04-28 09:33:52 -0400			Active	
db2.stone.branch - QADB2	db2.stone.branch	QADB2	6.2.0.0	2016-04-28 09:34:58 -0400			Active	
db3.stone.branch - QADB3	db3.stone.branch	QADB3	6.2.0.0	2016-04-28 09:33:04 -0400			Active	
db5.stone.branch - QADB5	db5.stone.branch	QADB5	6.2.0.0				Offine	
in26rh4-x64.stone.branch - LXRH4X64	lin26rh4-x64.stone.branch	LXRH4X64	5.2.0.11	2016-04-28 09:33:14 -0400			Active	
k3ora7-x64.stone.branch - LX30RA7X64	bx3ora7-x64.stone.branch	LX30RA7X64	5.2.0.11	2016-04-28 09:33:40 -0400			Active	
k3rh7-x64.stone.branch - LX3RH7X64	bx3rh7-x64.stone.branch	LX3RH7X64	6.3.0.1	2016-04-28 09:34:41 -0400			Active	
k3rh7c-x64.stone.branch - LX3RH7CX64	bx3rh7c-x64.stone.branch	LX3RH7CX64	6.3.0.0	2016-04-28 09:34:57 -0400			Active	

	(mm)		
		Update 📵 Suspend Agent 🎲 Delete 📑 Refres	sh 💥 Clo
Linux/Unix Agent			
Configuration Details			
Agent Name : stonebranch-linuxunixagent-01	Agent Id :	: agent1	
Status : Offline	Suspended	:	
Log Level : Informational 🗸	Member of Business Services	i	~
Heartbeat Interval : 120	Credentials	:	× 13
Task Execution Limit:	Limit Amount :	: 5	
Installation Details			
Host Name : Linux1		: 5.2.0.2	
IP Address :	Build Id		
Operating System : Linux		20140318194235	
Operating System x86_64 2.6.18-274.7.1.el5 (#1 SMP Thu Oct 20 16:21:01 EDT Release :	CPU	: AuthenticAMD AMD Phenom(tm) II X6 1055T Process	or (6 CPU)
System Details			
Started Date : 2014-04-23 17:28:55 -0400	PID	: 5915	
Last Heartbeat: 2014-04-28 17:50:46 -0400	Jobs Run		
CPU Load : 0	Current Task Count		
OMS Server : localhost 7878	Ξ		
📙 Update 🔘 Suspend Agent 🎯 Delete 🔄 Refresh 🛛 💥	Close		
lost fields are display-only; however, you can make the follo	owing changes	S:	
 Add a Member of Business Services. Assign Credentials. 			

You also can choose to:

• Temporarily suspend the agent's ability to run tasks.

Agents List Column Descriptions

The following table describes the default display columns on an Agents list.

Column	Description
Agent Name	User-defined during installation; name used within the Controller to identify this Agent.
Host Name	User-provided during installation; IP address or domain/name of the host machine where the resource resides.
Туре	Agent's platform: Linux/Unix, Windows, or z/OS.
Agent ID	Unique ID for this Agent, created during installation.
Version	System-supplied; version number of the Agent program.

Last Heartbeat	System-supplied; date and time the most recent heartbeat was received from the resource.
Current Task Count	System supplied; current number of tasks currently being run by this Agent.
Suspended	Specification (true or false) for whether or not this Agent has been suspended from the ability to run tasks.
Status	 System-supplied; status of the Agent. Active: the Agent is running. Offline: the Agent is not running.
Updated By	User that last updated this record.
Updated	Date when this record was last updated.

Agent Details Field Descriptions

Detailed descriptions of the fields in the Agent Details are provided for each type of Agent.

Starting and Stopping Agents

For instructions on starting and stopping Agents, see Starting and Stopping Agent Components.

Suspending Agents, Agent Clusters, and Agent Cluster Memberships

If an Agent or Agent Cluster reaches its Task Execution Limit, all new work queued against that Agent or Agent Cluster will transition into the Execution Wait status until the Current Task Count falls below the Limit Amount.

You also can manually suspend (and resume) Agents and Agent Clusters, as well as Agent memberships in Agent Clusters.

🔥 Note

The following roles and permissions are required to suspend/resume Agents, Agent Clusters, and Agent Cluster Memberships:

- Agent Suspend/Resume requires the ops_admin role and the appropriate Agent permissions for Agent Suspend/Resume commands.
- Agent Cluster Suspend/Resume and Agent Cluster Membership Suspend/Resume require the ops_agent_cluster_admin role.

Suspending an Agent

You can temporarily suspend the ability of an Agent to run tasks from the Agent list or the Agent Details for that Agent. Any tasks queued against a suspended Agent will transition into Execution Wait status until the Agent has been resumed.

- To suspend an Agent from the Agents list, either:
 - Right-click the Agent Name of the Agent to be suspended and, on the Action menu, click Suspend Agent.
 - Click the box to the left of the Agent Name and, from the Action on selected rows... drop-down list at the bottom of the page, click Suspend Agent.
- To suspend an Agent from the Agent Details, click the Suspend Agent button. A Resume Agent button replaces the Suspend Agent button.

Resuming an Agent

(To end the suspension, and resume the ability of an Agent to run tasks, either:

- · Click Resume Agent on the Action menu or from the Action on selected rows... drop-down list.
- Click the **Resume Agent** button.

Suspending an Agent Cluster

You can temporarily suspend the ability of a cluster of Agents to run tasks from the Agent Clusters list or an Agent Cluster Details. Any tasks

queued against a suspended agent cluster will transition into Execution Wait status until the agent cluster has been resumed.

- To suspend an Agent Cluster from the Agent Clusters list, either:
 - Right-click the Cluster Name of the agent cluster to be suspended and, on the Action menu, click Suspend Agent Cluster.
 - Click the box to the left of the agent cluster. From the Action on selected rows... drop-down list at the bottom of the page, click Suspend Agent.
- To suspend an Agent Cluster from an Agent Cluster Details, click the **Suspend Cluster** button. A **Resume Cluster** button replaces the *Suspend Cluster * button.

Resuming an Agent Cluster

To end the suspension, and resume the ability of a cluster of Agents to run tasks, either:

- Click Resume Agent Cluster on the Action menu or from the Action on selected rows... drop-down list.
- Click the **Resume Cluster** button.

Suspending an Agent Cluster Membership

You can temporarily suspend the membership of an Agent in an agent cluster from an Agent Cluster Details. Suspending the membership of an Agent in an agent cluster is equivalent to removing the Agent from the agent cluster, except it is meant to be temporary. The Agent will not be available as a selection from the agent cluster when a task is queued against the agent cluster until the membership of the Agent has been resumed.

Note

If a task specifies both an Agent and an agent cluster in which that Agent is a member, and the specified Agent has been suspended from the agent cluster, the Agent still has the ability to run the task. Directly specifying an Agent overrides its suspension from an agent cluster.

To suspend the membership of an Agent from an Agent Cluster Details, click the Agents in Cluster tab and then either:

- Right-click an Agent on the list and, on the Action menu, click Suspend Cluster Membership.
- Click the box to the left of an Agent and then, from the Action on selected rows... drop-down list at the bottom of the page, click Suspend Cluster Membership.

Resuming an Agent Cluster Membership

To end the suspension, and resume the membership of an Agent in an agent cluster:

• Click Resume Cluster Membership on the Action menu or from the Action on selected rows... drop-down list.

Resetting the Current Task Count

The Current Task Count field in Agent Details and Agent Cluster Details identifies the current number of tasks currently being run by, respectively, that Agent or Agent Cluster.

If there is a limit to the number of tasks that an Agent or Agent Cluster can run concurrently (as specified by the **Task Execution Limit** and **Limit Amount** fields), you can reset the current task count to 0. This can help avoid a situation where the Controller believes the Agent to be running more tasks than it actually is running, and therefore might impose the task limit on the Agent unnecessarily.

To reset the Current Task Count field, hover your cursor over the down arrow on the Agent Details or the Agent Cluster Details title bar, or right-click the title bar, and then click, respectively, **Reset Agent Task Count** or **Reset Cluster Task Count**.



- Reset Agent Task Count requires the ops_admin role and the Update Agent permission.
- Reset Cluster Task Count requires the ops_agent_cluster_admin role.

Sending Notifications on Status of an Agent

You can configure an Agent to send a notification via email or SNMP if the Agent goes down (Offline) or then when it comes back up (Active).

Step 1	Fron	From the Agents & Connections navigation pane, select Agents > All Agents or Agents > <type agent="" of="">. An Agents list displays.</type>						
Step 2	Click	Click the icon next to the Agent Name of an Agent, or click anywhere in the Agent row, to display Details about the Agent.						
Step 3	Click	the N	lotifications tab to display a list of any Email and SNMP notifications configured for the Agent.					
Step 4			type of notification you want the Agent to send, and then click New . Notification Details for a new Notification displays (Sec fication Details and SNMP Notification Details, below.					
Step 5	Com belo		the fields as needed (see Email Notification Details Field Descriptions and SNMP Notification Details Field Descriptions,					
			Noto					
		۸	Note Agent built-in variables are available to pass data about the Agent into the notification. (User-defined variables, including Global variables, are not available for use in Agent email notifications).					

Email Notification Details

mail Notification Details		-	
Email Notification		Save	💥 Close
Criteria			
Status Options :			~
- Details			
Email Template :	🗸 🔄 Email Connection :		× 13
Reply-To :			
To :			
Cc:			
Bcc :			
Subject :			
Body :			
Save	X Close		

Email Notification Details Field Descriptions

The following table describes the fields and buttons on Email Notification Details.

Field Name	Description
Criteria	This section contains criteria for sending the notification.
Status Options	 Offline = Trigger the notification when the resource goes offline. Active = Trigger the notification when the resource comes up.

Details	This section contains assorted detailed information about the notification.
Email Template	Name of an Email template defined in an Email Template Details. An Email template allows you to specify standard recipients and text for outgoing emails. Enter the name of an existing Email template, select an Email template from the drop-down list, or click the Details icon to create a new Email template. Every Email template specifies an Email connection. If you do not specify an Email template in this field, you must specify an Email connection in the Email Connection field. If you specify both an Email template (in this field) and an Email Connection, the Email server specified in the Email Connection field. (Any information specified in an Email task overrides what is specified in an Email template.)
Email Connection	Required if an Email Template is not specified in the Email Template field; name of an Email Connection. An Email Connection specifies information about an email server. Enter the name of an existing Email Connection, or click the magnifying glass to browse for an existing Email Connection or create a new Email Connection. If you specify both an Email Template and an Email Connection (in this field), the Email Connection specified in this field overrides the Email Connection specified in the Email Template field.
Reply-To	Email address of the sender. Use commas to separate multiple recipients. Variables and functions supported.
То	Email address of the recipient. Use commas to separate multiple recipients. Variables and functions supported.
СС	Email address of the party being sent a copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
BCC	Email address of the party being sent a blind (hidden) copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
Subject	Subject line of the email. Variables and functions supported.
Body	Text of the email message. Variables and functions supported. If both the email template and the email task contain text in the body, the text is appended.
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.
Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this notification.

SNMP Notification Details

SNMP Notification Details				_)[])×
			📳 Save	💢 Close
SNMP Notification				
Criteria Status Options :				*
SNMP Manager :	× 📰	Notification Severity : Normal		~
🕅 Save 🗱 Close				

SNMP Notification Details Field Descriptions

The following table describes the fields and buttons on SNMP Notification Details.

Field Name	Description
Criteria	This section contains criteria for sending the notification.
Status Options	 Offline = Trigger the notification when the resource goes offline. Active = Trigger the notification when the resource comes up.
Details	This section contains assorted detailed information about the notification.
SNMP Manager	The SNMP Manager that will receive the SNMP notification.
Notification Severity	Severity of this notification. Options: • Normal (1) • Warning (2) • Minor (3) • Major (4) • Critical (5)
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.
Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this notification.

Linux Unix Agent

- Overview
- Linux/Unix Agent Details
- Linux/Unix Agent Details Field Descriptions


Overview

The Linux/Unix Agent resource provides information about Universal Agent for UNIX running on a Linux/Unix platform. To run a Linux/Unix task, you need a UNIX Agent installed and running on the target machine.

Linux/Unix Agent Details

Linux/Unix Agent Details provide the information necessary for the scheduler to locate and communicate with the machine where the Agent resides. Universal Controller creates this record automatically when the Agent connects with the Controller.

To view Linux/Unix Agent Details:



in a contract of the contract	stonebranch-linuxunixagent-01		
			Update 🕕 Suspend Agent 🎲 Delete 📑 Refresh 渊 Clo
Linux/Unix Agent 🛛 🔍	Agent Clusters Notifications Task Instances		
Configuration Detail	s		
Agent Name :	stonebranch-linuxunixagent-01	Agent Id :	agent1
Status :	Offline	Suspended :	
Log Level :	Informational	Member of Business Services :	×
Heartbeat Interval :	120	Credentials :	× =
Task Execution		Limit Amount :	
Limit :	Limited	Limit Amount .	5
- Installation Details			
Host Name :	Linux1	Version :	5.2.0.2
IP Address :		Build Id :	110
Operating System :	Linux	Build Date :	20140318194235
Operating System	x86_64 2.6.18-274.7.1.el5 (#1 SMP Thu Oct 20 16:21:01 EDT .		AuthenticAMD AMD Phenom(tm) II X6 1055T Processor (6 CPU)
Release :			· · · · · · · · · · · · · · · · · · ·
System Details			
Started Date :	2014-04-23 17:28:55 -0400	PID :	5915
Last Heartbeat :	2014-04-28 17:50:46 -0400	Jobs Run :	0
CPU Load :	0	Current Task Count	0
OMS Server :	localhost7878		
🔛 Update 🕕) Suspend Agent 👔 Delete 🕞 Refresh 🔰 🎽	Close	

You also can choose to temporarily suspend the agent's ability to run tasks.

See the field descriptions, below, for details about all fields in the Linux/Unix Agent Details.

Linux/Unix Agent Details Field Descriptions

The following table describes the fields, buttons, and tabs in the Linux/Unix Agent Details.

Field Name	Description
Configuration Details	This section contains detailed information about the configuration of the Agent.
Agent Name	User-defined during installation; name used within the Controller to identify this Agent.
Agent ID	Unique ID for this Agent, created during installation.
Status	System-supplied; status of the Agent.
Suspended	Indication that the Agent's ability to run tasks has been suspended.

Log Level	
	User-modifiable; level of logging that the Agent should perform.
	Options:
	Severe Error Errors
	Warning Informational
	 Debug Trace
Member of Business Service	User-defined at installation; specifies one or more Business Services that this resource belongs to.
Heartbeat Interval	User-modifiable; heartbeat interval (in seconds). The heartbeat is a status message sent from the Agent to the Controller.
	If you change the heartbeat interval, it only affects new Agents that are registered after the change. It does not affect the
	heartbeat interval of existing Agents.
Credentials	
	Credentials under which this Agent runs tasks. These credentials are overridden by any credentials provided in the task definition for any tasks being run by this Agent.
Task Execution	Specification for whether a Limited or Unlimited number of task instances can be run concurrently on the Agent. (Default
Linin	is Unlimited.)
	For purposes of imposing this task execution limit, running task instances are those in any of these statuses: Cancel
	Pending, Queued, Received, Running, Submitted, and Started.
Limit Amount	
	If Task Execution Limit = Limited; Number of tasks that can be running at the same time by the Agent.
Installation	This section contains detailed information about the installation of the Agent.
Details	
Host Name	User-provided during installation; IP address or domain/name of the host machine where the resource resides.
IP Address	User-provided during installation; TCP/IP address of the machine where the Agent is running.
Operating System	System-supplied; operating system on which the Agent is running.
Operating System Release	System-supplied; release information for the operating system on which the Agent is running.
Keledde	
Version	System-supplied: version number of the Agent program
	System-supplied; version number of the Agent program.
Build ID	System symplical provided by the Arent build ID of the Arent latered use a stu
	System-supplied, provided by the Agent; build ID of the Agent. Internal use only.
Build Date	
	System-supplied, provided by the Agent; date the Agent program was last built.
CPU	
	System-supplied; information about the CPU on the Agent machine.

System Details	This section contains detailed information about the Agent system.	
Started Date	System-supplied; date/timestamp when the Agent was last started.	
Last Heartbeat	System-supplied; date and time the most recent heartbeat was received from the resource.	
CPU Load	System-supplied; current CPU load on the Agent machine, expressed as a percentage. For example, 1 means 1% currently utilized.	
OMS Server	Host name of the OMS Server.	
PID	System-supplied, provided by the Agent; process ID of the Agent.	
Jobs Run	Total number of jobs that have been run through the Controller to this Agent.	
Current Task Count	If Task Execution Limit = Limited; Current number of tasks currently being run by this Agent. (See Resetting the Current Task Count for information on resetting the current task count.)	
Buttons	This section identifies the buttons displayed above and below the Agent Details that let you perform various actions.	
Save	Saves a new task record in the Controller database.	
Update	Saves updates to the record.	
Suspend Agent	Suspends the Agent's ability to run tasks.	
Resume Agent	Resumes the suspended Agent's ability to run tasks.	
Delete	Deletes the current record.	
Refresh	Refreshes any dynamic data displayed in the Details.	
Close	For pop-up view only; closes the pop-up view of this task.	
Tabs	This section identifies the tabs across the top of the Agent Details that provide access to additional information about the Agent.	
Agent Clusters	Lists all agent clusters that this Agent belongs to.	
Notifications	Lists all notifications that have been defined for this Agent.	
Task Instances	System-supplied; lists all task instances that have run or are ready to run on this Agent since it last started.	

Windows Agent

```
    Overview
```

- Windows Agent Details
- Windows Agent Details Field Descriptions

Overview

The Windows Agent resource provides information about Universal Agent for Windows running on a Windows platform. To run a Windows task, you need a Windows Agent installed and running on the target machine.

Windows Agent Details

Windows Agent Details provides the information necessary for the scheduler to locate and communicate with the machine where the Agent resides. Universal Controller creates this record automatically when the Agent connects with the Controller.

To view Windows Agent Details:

	From the Agents & connected Window		on pane, select Age	nts > Window	vs Agents . The Windows Agents list displays a list of
		lso can select Agents s: Linux/Unix, Window		ne Agents & C	Connections navigation pane to display a list of all
2	Click the Details in	con next to an Agent N	ame or click anywhe	re in the Agen	t row to display Details for that agent.
	Windows Agent Details:	stonebranch-windowsagent-01			
					Jpdate 🐽 Suspend Agent 🎲 Delete 📑 Refresh 💥 Close 🗌
	Windows Agent 🧧 🖌	Agent Clusters Notifications	Task Instances		
	Configuration Detai	Is			
	Agent Name :	stonebranch-windowsagent-01		Agent Id :	WX64
	Status :	Offline		Suspended :	
	Log Level :	Informational	~	Member of Business Services :	QA Department
	Heartbeat Interval :	120		Credentials :	× 🖂
	Task Execution Limit :		v	Limit Amount :	
	- Installation Details				
	Host Name :	w2-x64		Version :	5.2.0.2
	IP Address :			Build Id :	109
	Operating System :	Microsoft Windows		Build Date :	20140317155851
	Operating System Release :	Server 4.0 (Build 9200)		CPU :	AMD64 (1 CPU(s))
	- System Details				
		2014-03-18 15:49:03 -0400		PID :	244
	Last Heartbeat :	2014-03-24 15:17:17 -0400		Jobs Run :	1
	CPU Load :	6		Current Task	0
	OMS Server :	localhost:7878	E-		
	🔛 Update 🕕	Suspend Agent 👔 Delete	😫 Refresh 🛛 💥	Close	

Step 3 Most fields are display-only; however, you can make the following changes:

- 1. Add a Member of Business Services.
- 2. Assign Credentials.
- 3. Change the heartbeat interval. The heartbeat is a status message sent from the Agent to the Controller.
- 4. Change the Log Level (default is Informational).
- 5. Select whether or not to apply a Task Execution Limit (and Limit Amount) on the Agent.

You also can choose to temporarily suspend the agent's ability to run tasks.

See the field descriptions, below, for details about all fields in the Windows Details.

Windows Agent Details Field Descriptions

The following table describes the fields, buttons, and tabs in the Windows Agent Details.

Field Name	Description	
Configuration Details	This section contains detailed information about the configuration of the Agent.	
Agent Name	User-defined during installation; name used within the Controller to identify this Agent.	
Agent ID	Unique ID for this Agent, created during installation.	
Status	System-supplied; status of the Agent.	
Suspended	Indication that the Agent's ability to run tasks has been suspended.	
Log Level	User-modifiable; level of logging that the Agent should perform. Options: • Severe Error • Errors • Warning • Informational • Debug • Trace	
Member of Business Service	User-defined at installation; specifies one or more Business Services that this resource belongs to.	
Heartbeat Interval	User-modifiable; heartbeat interval (in seconds). The heartbeat is a status message sent from the Agent to the Controller. If you change the heartbeat interval, it only affects new Agents that are registered after the change. It does not affect the heartbeat interval of existing Agents.	
Credentials	Credentials under which this Agent runs tasks. These credentials are overridden by any credentials provided in the task definition for any tasks being run by this Agent.	

Task Execution Limit	Specification for whether a Limited or Unlimited number of task instances can be run concurrently on the Agent. (Default is Unlimited .)
	For purposes of imposing this task execution limit, running task instances are those in any of these statuses: Cancel Pending, Queued, Received, Running, Submitted, and Started.
Limit Amount	If Task Execution Limit = Limited; Number of tasks that can be running at the same time by the Agent.
Installation Details	This section contains detailed information about the installation of the Agent.
Host Name	User-provided during installation; IP address or domain/name of the host machine where the resource resides.
IP Address	User-provided during installation; TCP/IP address of the machine where the Agent is running.
Operating System	System-supplied; operating system on which the Agent is running.
Operating System Release	System-supplied; release information for the operating system on which the Agent is running.
Version	System-supplied; version number of the Agent program.
Build ID	System-supplied, provided by the Agent; build ID of the Agent. Internal use only.
Build Date	System-supplied, provided by the Agent; date the Agent program was last built.
CPU	System-supplied; information about the CPU on the Agent machine.
System Details	This section contains detailed information about the Agent system.
Started Date	System-supplied; date/timestamp when the Agent was last started.
Last Heartbeat	System-supplied; date and time the most recent heartbeat was received from the resource.
CPU Load	System-supplied; current CPU load on the Agent machine, expressed as a percentage. For example, 1 means 1% currently utilized.
OMS Server	Host name of the OMS Server.
PID	System-supplied, provided by the Agent; process ID of the Agent.
Jobs Run	Total number of jobs that have been run through the Controller to this Agent.
Current Task Count	If Task Execution Limit = Limited; Current number of tasks currently being run by this Agent. (See Resetting the Current Task Count for information on resetting the current task count.)

Buttons	This section identifies the buttons displayed above and below the Agent Details that let you perform various actions.
Save	Saves a new task record in the Controller database.
Update	Saves updates to the record.
Suspend Agent	Suspends the Agent's ability to run tasks.
Resume Agent	Resumes the suspended Agent's ability to run tasks.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this task.
Tabs	This section identifies the tabs across the top of the Agent Details that provide access to additional information about the Agent.
Agent Clusters	Lists all agent clusters that this Agent belongs to.
Notifications	Lists all notifications that have been defined for this Agent.
Task Instances	System-supplied; lists all task instances that have run or are ready to run on this Agent since it last started.

zOS Agent

```
    Overview
```

- z/OS Agent Details
- z/OS Agent Details Field Descriptions

Overview

The z/OS Agent resource provides information about a Universal Agent for z/OS running on a z/OS platform.

To run a z/OS task, you need a z/OS Agent installed and running on the target machine.

z/OS Agent Details

z/OS Agent Details provide the information necessary for the scheduler to locate and communicate with the machine where the Agent resides. Universal Controller creates this record automatically when the Agent connects with the Controller.

To view z/OS Agent Details:



2/05 Agent Details: stone	branch-zOSagent-01			
		; u	Update 🔳 Suspend Agent 🎲 Delete 📑 Refresh 🗧	🔀 Clos
z/OS Agent 😐 Notif	cations Task Instances			
- Configuration Detail	s			
Agent Name :	stonebranch-zOSagent-01	Agent Id :	ZOS52	
Status :	Offline	Suspended :		
Log Level :	Debug	Member of Business Services :	f	~
Heartbeat Interval :	120	Credentials :		× 13
Task Execution			5	
Limit :	Limited	Limit Amount :		
- Installation Details				
Host Name :	ZOS11	Version :	5.2.0.3	
IP Address :		Build Id :	111	
Operating System :	ZOS	Build Date :	20140430105205	
Operating System Release :	011100	CPU :	2098	
- System Details				
	2014-04-30 10:53:36 -0400	PID :	126058520	
Last Heartbeat :	2014-04-30 11:19:48 -0400	Jobs Run :		
CPU Load :	0	Current Task Count :		
OMS Server :	localhost.7878			
🔛 Update 间	Suspend Agent 👔 Delete 🕞 Refresh 🔀 🛠	Close		

You also can choose to temporarily suspend the agent's ability to run tasks.

See the field descriptions, below, for details about all fields in the z/OS Agent Details.

z/OS Agent Details Field Descriptions

The following table describes the fields, buttons, and tabs in the z/OS Agent Details.

Field Name	Description
Configuration Details	This section contains detailed information about the configuration of the Agent.
Agent Name	User-defined during installation; name used within the Controller to identify this Agent.
Agent ID	Unique ID for this Agent, created during installation.
Status	System-supplied; status of the Agent.
Suspended	Indication that the Agent's ability to run tasks has been suspended.

Log Level	User-modifiable; level of logging that the Agent should perform.
	Options:
	 Severe Error Errors Warning Informational Debug Trace
Member of Business Service	User-defined at installation; specifies one or more Business Services that this resource belongs to.
Heartbeat Interval	User-modifiable; heartbeat interval (in seconds). The heartbeat is a status message sent from the Agent to the Controller.
	If you change the heartbeat interval, it only affects new Agents that are registered after the change. It does not affect the heartbeat interval of existing Agents.
Credentials	Credentials under which this Agent runs tasks. These credentials are overridden by any credentials provided in the task definition for any tasks being run by this Agent.
Task Execution Limit	Specification for whether a Limited or Unlimited number of task instances can be run concurrently on the Agent. (Default is Unlimited .)
	For purposes of imposing this task execution limit, running task instances are those in any of these statuses: Cancel Pending, Queued, Received, Running, Submitted, and Started.
Limit Amount	If Task Execution Limit = Limited; Number of tasks that can be running at the same time by the Agent.
Installation Details	This section contains detailed information about the installation of the Agent.
Host Name	User-provided during installation; IP address or domain/name of the host machine where the resource resides.
IP Address	User-provided during installation; TCP/IP address of the machine where the Agent is running.
Operating System	System-supplied; operating system on which the Agent is running.
Operating System Release	System-supplied; release information for the operating system on which the Agent is running.
Version	System-supplied; version number of the Agent program.
Build ID	System-supplied, provided by the Agent; build ID of the Agent. Internal use only.
Build Date	System-supplied, provided by the Agent; date the Agent program was last built.
CPU	System-supplied; information about the CPU on the Agent machine.

System Details	This section contains detailed information about the Agent system.		
Started Date	System-supplied; date/timestamp when the Agent was last started.		
Last Heartbeat	System-supplied; date and time the most recent heartbeat was received from the resource.		
CPU Load	System-supplied; current CPU load on the Agent machine, expressed as a percentage. For example, 1 means 1% currently utilized.		
OMS Server	Host name of the OMS Server.		
PID	System-supplied, provided by the Agent; process ID of the Agent.		
Jobs Run	Total number of jobs that have been run through the Controller to this Agent.		
Current Task Count	If Task Execution Limit = Limited; Current number of tasks currently being run by this Agent. (See Resetting the Current Task Count for information on resetting the current task count.)		
Buttons	This section identifies the buttons displayed above and below the Agent Details that let you perform various actions.		
Save	Saves a new task record in the Controller database.		
Update	Saves updates to the record.		
Suspend Agent	Suspends the Agent's ability to run tasks.		
Resume Agent	Resumes the suspended Agent's ability to run tasks.		
Delete	Deletes the current record.		
Refresh	Refreshes any dynamic data displayed in the Details.		
Close	For pop-up view only; closes the pop-up view of this task.		
Tabs	This section identifies the tabs across the top of the Agent Details that provide access to additional information about the Agent.		
Agent Clusters	Lists all agent clusters that this Agent belongs to.		
Notifications	Lists all notifications that have been defined for this Agent.		
Task Instances	System-supplied; lists all task instances that have run or are ready to run on this Agent since it last started.		

Agent Clusters

- Overview
- Creating an Agent Cluster
 - Agent Cluster Details
 - Agent Cluster Details Field Descriptions
- Assigning Agents to the Cluster
- Suspending Agent Clusters and Agent Cluster Memberships

Overview

For Windows and Linux/Unix Agents only, Universal Controller allows you to create clusters (groups) of Agents.

If you specify an agent cluster in a task, the Controller selects an Agent from the cluster based on the selection method that you specified when you created the cluster. If you specify both an Agent and an agent cluster in a task, the Controller first attempts to run the task on the Agent; if the Agent is unavailable, the Controller selects an Agent from the agent cluster.

🔥 Note

The instructions and illustrations, below, for creating Windows agent clusters and Linux/Unix agent clusters, and assigning Agents to those clusters, are the same.

Creating an Agent Cluster

Linux/Unix Agent Clusters				
	Custom Filter None 🗸 🦁 Filter 😨 Go To 🍰 New 🦿			
✓ 5 Linux/Unix Agent Clusters Cluster Name ▲	Distribution Current Task Count Suspended Updated By Updated *			
stonebranch-linuxunixcluster-01	Any 0 No ops.admin 2014-06-13 15:23:02 -0400			
stonebranch-linuxunixcluster-02	Any 0 No ops.admin 2014-06-13 15:23:06 -0400			
stonebranch-linuxunixcluster-03	Any 0 No ops.admin 2014-06-13 15:23:11 -0400			
stonebranch-linuxunixcluster-04	Any 0 No ops.admin 2014-06-13 15:23:16 -0400			
stonebranch-linuxunixcluster-05	Any 0 No ops.admin 2014-06-13 15:23:19 -0400			
✓ Linux/Unix Agent Cluster Details	🐺 Save 🗖 New			
Linux/Unix Agent Cluster Agents I	s In Cluster S Tasks Versions			
Details				
Cluster Name :	Version : 1			
Distribution : Any	V Last Agent Used :			
Suspended :	Current Task Count : 0			
Task Execution Limit :	✓ Limit Amount : 5			
Save New				
	new agent cluster, using the field descriptions below as a guide.			
Required fields disDefault values for f				

Agent Cluster Details

The following Agent Cluster Details is for an existing Linux/Unix agent cluster. See the field descriptions, below, for a description of all fields that may display in the Agent Cluster Details.

			📳 Update	Suspend Agent Cluster	🇊 Delete 🛭 😫 Refresh	💥 Clo
nux/Unix Agent Cluster	Agents In Cluster	Versions				
Details						
Cluster Name :	stonebranch-linuxunixcluster-01		Version :	1		
Distribution :	Any	~	Last Agent Used :			57
Suspended :			Current Task Count :	0		
Task Execution Limit :	Limited	*	Limit Amount :	5		
\Bigg Update 🕕	Suspend Agent Cluster	lete	X Close			

Agent Cluster Details Field Descriptions

The following table describes the fields, buttons, and tabs in the Agent Cluster Details.

Field Name	Description
Details	This section contains detailed information about the agent cluster.
Cluster Name	Name used within the Controller to identify this agent cluster. Up to 40 alphanumerics. It is the responsibility of the user to develop a workable naming scheme for agent clusters.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Distribution.	Method used to select an Agent. Options: • Any - Select any Agent in the cluster. • Round Robin - Select the next Agent in a round robin series. • Lowest CPU Utilization - Selects the Agent whose CPU utilization is currently the lowest.
Last Agent Used	System-supplied; Agent that was selected the last time a task was sent to this agent cluster.
Suspended	Indication that the ability for this cluster of Agents to run tasks has been suspended.
Current Task Count	If Task Execution Limit = Limited; Current number of tasks currently being run by the Agents in this agent cluster. (See Resetting the Current Task Count for information on resetting the current task count.)
Task Execution Limit	Specification for whether a Limited or Unlimited number of task instances can be run concurrently by the Agents in this agent cluster. (Default is Unlimited.) For purposes of imposing this task execution limit, running task instances are those in any of these statuses: Cancel Pending, Queued, Received, Running, Submitted, and Started.
Limit Amount	If Task Execution Limit = Limited; Number of tasks that can be running at the same time by the Agents in this agent cluster.
Buttons	This section identifies the buttons displayed above and below the Agent Cluster Details that let you perform various actions.
Save	Saves a new task record in the Controller database.
Update	Saves updates to the record.

Suspends the ability for this cluster of Agents to run tasks.
Resumes the ability for this suspended cluster of Agents to run tasks.
Deletes the current record.
Refreshes any dynamic data displayed in the Details.
For pop-up view only; closes the pop-up view of this task.
This section identifies the tabs across the top of the Agent Cluster Details that provide access to additional information about the agent cluster.
List of Agents assigned to this cluster.
Lists all tasks, according to task type, that currently are being dispatched to this agent cluster.
You also can create tasks for the identified task types that will have this agent cluster pre-selected in the Agent Cluster field of its Task Details.
Stores copies of all previous versions of the current record. See Record Versioning.

Assigning Agents to the Cluster

Step 1 On the Linux/Unix Clusters list (for example), click the Cluster Name of the cluster to which you want to assign one or more existing Agents.

✓ 5 Linux/Unix Agent Clusters	Custom Filter None		~	😼 Filter [🗟 <u>G</u> o To 🏭 New ಿ
Cluster Name *	Distribution	Current Task Count		Updated By	Updated
stonebranch-linuxunixcluster-01	Any	0	No	ops.admin	2014-06-13 15:23:02 -0400
stonebranch-linuxunixcluster-02	Any	0	No	ops.admin	2014-06-13 15:23:06 -0400
stonebranch-linuxunixcluster-03	Any	0	No	ops.admin	2014-06-13 15:23:11 -0400
stonebranch-linuxunixcluster-04	Any	0	No	ops.admin	2014-06-13 15:23:16 -0400
stonebranch-linuxunixcluster-05	Any	0	No	ops.admin	2014-06-13 15:23:19 -0400
✓ Linux/Unix Agent Cluster Details Linux/Unix Agent Cluster ● Agents in Cluster ● Tasks	Versions				🗑 Save 🔳 New
	s versions				
Details					
Cluster Name :		Version : 1			
Distribution : Any	✓ Last A	gent Used :			13
Suspended:	Current T	ask Count : 0			
Task Execution Limit :	✓ Lin	it Amount : 5	5		
ick the Edit button. The Edit Members	dialog displays:				
	dialog displays:				
lick the Edit button. The Edit Members Edit Members	dialog displays:	Linu	x/linix A	nents list	
				gents List	
Edit Members Collection	\$			gents List kunixcluste	
Edit Members	9				
Edit Members Collection	Age	stonebra	nch-linu		r-01
Edit Members Collection Agent Name ^ stonebranch-linuxunixagent-04	Age	stonebra nt Name ^ ebranch-linuxunixagent-0	nch-linu: I		r-01
Edit Members Collection Agent Name *	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name ^ stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name ^ stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name ^ stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name ^ stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name A stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Edit Members Collection Agent Name A stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01
Collection Agent Name * stonebranch-linuxunixagent-04	Age stor stor •	stonebra nt Name ^ ebranch-linuxunixagent-0 ebranch-linuxunixagent-0;	nch-linu: 1		r-01

Step 4	The Agents in the Collection window are existing Agents of the current type that do not belong to this cluster. The Agents in the Linux/Unix Agents List window are Agents that belong to this cluster.
Step 5	 To add to or remove Agents from the Linux/Unix Agents List: To add an Agent, double-click the Agent Name (or click the Agent Name and then click the -> arrow) in the Collection window. To remove an Agent from the list, double-click the Agent Name (or click the Agent Name and then click the <- arrow) in the Linux/Unix Agents List window.
Step 6	When you are finished, click Save.

Suspending Agent Clusters and Agent Cluster Memberships

You can temporarily suspend the ability for an agent cluster to run tasks, and you can temporarily suspend the agent cluster membership of any Agent in an agent cluster.

For information on how to implement these suspensions, see Suspending Agents, Agent Clusters, and Agent Cluster Memberships.

OMS Servers

- Introduction
- Creating OMS Server Records
 - OMS Server Details
 - OMS Server Details Field Descriptions
- Starting and Stopping OMS
 - Sending Notifications on Status of an OMS Server
 - Email Notification Details
 - Email Notification Details Field Descriptions
 - SNMP Notification Details
 - SNMP Notification Details Field Descriptions

Introduction

OMS (Universal Message Service) Servers are the network communication providers between Universal Controller 6.3.x and Universal Agent 6.3.x.

Creating OMS Server Records

You must create a record for each OMS Server and OMS HA cluster (two or more OMS Servers in an HA / High Availability environment) that will be used as the network communications provider between the Controller and Agents.

Do not create individual records for each member (OMS Server) of an OMS HA cluster. You must define an OMS HA cluster as a single record, with the OMS Server Address containing a comma-separated list of each OMS Server in the cluster.

✓ 3 OMS Servers	Custom Filter None	-	~	🦁 Filter	🔯 Go To 🔚 New ಿ
OMS Server Address A	Status	Session Status	Authenticate OMS Serve	er Updated By	Updated 🔺
localhost:7878	Connected	Operational	No	opswise.syst	em 2014-03-05 10:07:13 -0400
in2611-x64	Disconnected	None	Yes	ops.admin	2014-08-27 16:17:41 -0400
k32-x64	Connected	Impaired	No	upswise.syst	em 2014-08-27 16:20:05 -0400
V OMS Server Details					🔚 Save 📃 New
OMS Server Agents Notification	ions				
- Details -					
OMS Server		01-1	Discourse		
Address :		Status .	Disconnected		
Network Timeout (Seconds): 30		Session Status :	None		
Authenticate OMS Server :		Last Connected Server Address :			
Save New					
Enter / select Details for a new • Required fields display			low as a guide.		
 Default values for field 		-	e the list		
Default values for field To display more of the Details	fields on the screen, you can ter	mporarily hid			

OMS Server Details

The following OMS Server Details is for an existing OMS Server. See the field descriptions, below, for a description of all fields that display in the OMS Server Details.

OMS Server Details: localhost:7878							
			🔚 Update	🇊 Delete	S Refresh	💥 Clo	se
OMS Server Agents Notifications							
Details OMS Server localhost:7878 Address :	Status :	Connected					
Network Timeout 30 (Seconds):	Session Status :						E
Authenticate OMS Server:	Last Connected Server Address :	localhost/127.0	0.0.1:7878				
🐺 Update 👔 Delete 🕼 Refresh 🗱 Close							Ŧ

OMS Server Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the OMS Server Details.

Field Name	Description
Details	This section contains detailed information about the OMS Server.
OMS Server Address	IP address or host name of an OMS Server, or a comma-separated list of OMS Servers configured as an OMS Server cluster.
Network Timeout (Seconds)	Network socket time-out value used for TCP/IP receive and connect operations.
Authenticate OMS Server	If enabled, the Controller authenticates the OMS server digital certificate.
Status	Current status of the OMS server: Connected or Disconnected.
Session Status	 Current status of the OMS server messaging sessions: heartbeat, input, and output sessions. Options: Operational - All OMS Server messaging sessions are operational. Impaired - Ability of OMS clients to produce and/or consume messages is impaired. None - OMS Server is disconnected.
Last Connected Server Address	OMS Server, in a High Availability environment of multiple cluster nodes, that is connected to the Controller or was last connected to the Controller.
Buttons	This section identifies the buttons displayed above and below the OMS Server Details that let you perform various actions.
Save	Saves a new record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new OMS Server record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this record.
Tabs	This section identifies the tabs across the top of the OMS Server Details that provide access to additional information about the OMS Server.
Agents	Lists all Agents for which this OMS Server is the network communication provider between the Controller.

Starting and Stopping OMS

For instructions on starting and stopping OMS Servers, see Starting and Stopping Agent Components.

Sending Notifications on Status of an OMS Server

You can configure OMS Servers to send a notification via email or SNMP if that OMS Server status changes from Connected to Disconnected or Disconnected to Connected.

Step 1	Fror	m the	Agents and Connections navigation pane, select System > OMS Servers. The OMS Servers list displays.			
Step 2	Open the record of an OMS Server on the list.					
Step 3	Click the Notifications tab to display a list of any Email and SNMP notifications configured for the OMS Server.					
Step 4		Select the type of notification you want the OMS Server to send, and then click New . Notification Details for a new Notification displays (See Email Notification Details and SNMP Notification Details, below.				
Step 5	Con belc		the fields as needed (see Email Notification Details Field Descriptions and SNMP Notification Details Field Descriptions,			
		۸	Note OMS built-in variables are available to pass data about the OMS Server into the notification. (User-defined variables, including Global variables, are not available for use in OMS Server email notifications.)			
Step 6	Clic	k the S	Save button to save the record.			

Email Notification Details

Email Notification Details			
		🔛 Save	💢 Close
Email Notification			
Criteria			
Status Options :			~
Details			
Email Template :	🛩 🔄 Email Connection :		*
Reply-To :			
To :			
Cc:			
Bcc :			
Subject :			
Body :			
Save	X Close		

Email Notification Details Field Descriptions

The following table describes the fields and buttons on Email Notification Details.

Field	Description
Name	

Criteria	This section contains criteria for sending the notification.
Status Options	 Disconnected = Trigger the notification when the OMS Server is connected. Connected = Trigger the notification when the OMS Server is connected.
	 Note If you select Disconnected, and the OMS Server status is Connected but the session status becomes Impaired, the notification will qualify and be sent. If you select Connected, and the OMS Server recovers from an Impaired session status, the notification will qualify and be sent.
Details	This section contains assorted detailed information about the notification.
Email Template	Name of an Email template defined in an Email Template Details. An Email template allows you to specify standard recipients and text for outgoing emails. Enter the name of an existing Email template, select an Email template from the drop-down list, or click the Details icon to create a new Email template.
	Every Email template specifies an Email connection. If you do not specify an Email template in this field, you must specify an Email connection in the Email Connection field.
	If you specify both an Email template (in this field) and an Email Connection, the Email server specified in the Email Connection field overrides the Email server specified in this field.
	(Any information specified in an Email task overrides what is specified in an Email template.)
Email Connection	Required if an Email Template is not specified in the Email Template field; name of an Email Connection. An Email Connection specifies information about an email server. Enter the name of an existing Email Connection, or click the magnifying glass to browse for an existing Email Connection or create a new Email Connection.
	If you specify both an Email Template and an Email Connection (in this field), the Email Connection specified in this field overrides the Email Connection specified in the Email Template field.
Reply-To	Email address of the sender. Use commas to separate multiple recipients. Variables and functions supported.
То	Email address of the recipient. Use commas to separate multiple recipients. Variables and functions supported.
СС	Email address of the party being sent a copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
BCC	Email address of the party being sent a blind (hidden) copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
Subject	Subject line of the email. Variables and functions supported.
Body	Text of the email message. Variables and functions supported. If both the email template and the email task contain text in the body, the text is appended.
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.

Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this notification.

SNMP Notification Details

SNMP Notification Details			
	🦷 Save 🎽	Close	
SNMP Notification			
Criteria			
Status Options :		~	
Dataila			
Details			
SNMP Manager :	Notification Severity : Normal	~	
🕎 Save 🗱 Close			
L			

SNMP Notification Details Field Descriptions

The following table describes the fields and buttons on SNMP Notification Details.

Field Name	Description	
Criteria	This section contains criteria for sending the notification.	
Status Options	 Disconnected = Trigger the notification when the OMS Server is connected. Connected = Trigger the notification when the OMS Server is connected. 	
	 Note If you select Disconnected, and the OMS Server status is Connected but the session status becomes Impaired, the notification will qualify and be sent. If you select Connected, and the OMS Server recovers from an Impaired session status, the notification will qualify and be sent. 	
Details	This section contains assorted detailed information about the notification.	
SNMP Manager	The SNMP Manager that will receive the SNMP notification.	

Notification Severity	Severity of this notification. Options: • Normal (1) • Warning (2) • Minor (3) • Major (4) • Critical (5)
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.
Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this notification.

Cluster Nodes

- Introduction
- Displaying Information About Cluster Nodes
 - Cluster Node Details
 Cluster Node Details
 - Cluster Node Details Field Descriptions
 the second secon
- Starting/Stopping Cluster Nodes
 - Sending Notifications on Status of a Cluster Node
 - Email Notification Details
 - Email Notification Details Field Descriptions
 - SNMP Notification Details
 - SNMP Notification Details Field Descriptions

Introduction

Cluster Nodes are Universal Controller instances in a Universal Automation Center system.

Universal Automation Center contains more than one cluster node only if it is operating in a High Availability environment.

Displaying Information About Cluster Nodes

When you start a cluster node for the first time, the Controller automatically creates a database record for that cluster node. You can view these records for details and status information.

1 Cluster Node				Custom Filter None			× 🤘	🖇 Filter [🟹 💁 To 🛛 🍣 🗌
Node Id 👻	Mode	Start Time	Timestamp Upt	ime	Host Name	IP Address	Release	Build Id	Build Date
opswise:88-opswise	Active	2014-06-19 10:47:19 -0400	2014-07-02 11:11:32 -0400 13	Days 0 Hour 24 Minutes 12 Seconds	opswise6	168.174.31.74	6.1.2.0	build.200	12-18-2014_0800

Cluster Node Details

ister Node Details: op	swise:8080-opswise		
			🔄 Refresh 💥 Clos
Cluster Node 🛛 🔍 Clu	ster Notifications		
Details			
Node Id :	opswise:80-opswise	Mode :	Active
Host Name :	opswise6	Release :	6.1.2.0
IP Address :	168.174.31.74	Build Id :	build.17
Start Time :	2014-10-16 15:34:07 -0400	Build Date :	12-16-2014_0130
Timestamp :	2014-10-17 09:41:10 -0400	Uptime :	18 Hours 7 Minutes 2 Seconds
Paused :			
S Refresh	X Close		
4 Reliesh	A Close		

Cluster Node Details Field Descriptions

The following table describes the fields on the Cluster Nodes Details

Field Name	Description
Details	This section contains detailed information about the cluster node.
Node ID	URL of the cluster node.
Mode	 Current mode of the cluster node: Active: Cluster node processes events and messages and interfaces with the database. It is the active node for automated operations.\\ Passive: Cluster node is running but is not connected to its OMS Server. It performs the following tasks: Accepts HTTP requests for data. It can access the database, generate reports, monitor and display data. Does not process any events or messages. Takes over as Active node if it determines that the Active node is not running. Offline: Cluster node is not running. (See Passive Cluster Node Restrictions for further information on Passive cluster node capabilities.)
Host Name	User-provided during installation; IP address or domain/name of the host machine where the resource resides.
Release	System-supplied; release number for this node. Support purposes only.
IP Address	System-supplied; IP address of this node.
Build ID	System-supplied; build ID for this node. Support purposes only.
Start Time	System-supplied; date and time this node was last started.
Build Date	System-supplied; build date for this node. Support purposes only.
Timestamp	System-supplied; date and time of this node's last heartbeat.
Uptime	System-supplied; amount of time this node has been running.
Paused	Indication that the Controller has been paused.
Buttons	This section identifies the buttons displayed above and below the Cluster Node Details that let you perform various actions.
Refresh	Refreshes any dynamic data displayed in the Details.
Tabs	This section identifies the tabs across the top of the Cluster Node Details that provide access to additional information about the cluster node.
Cluster Notifications	Lists all notifications that have been defined for this cluster node.


Starting/Stopping Cluster Nodes

For instructions on starting and stopping cluster nodes, see Starting and Stopping Universal Controller.

Sending Notifications on Status of a Cluster Node

You can configure Cluster Nodes to send a notification via email or SNMP when the resource goes Offline or becomes Active.

Step 1	From the Agents and Connections navigation pane, select System > Cluster Nodes. The Cluster Nodes list displays.
Step 2	Click the Details icon next to the Node ID of a Cluster Node, or click anywhere in the Cluster Node row, to display Details about the Cluster Node.
Step 3	Click the Cluster Notifications tab to display a list of any Email and SNMP notifications configured for the Cluster Node.
Step 4	Select the type of notification you want the Cluster Node to send, and then click New . Notification Details for a new Notification displays (see Email Notification Details and SNMP Notification Details, below).



Email Notification Details

Email Notification Details			
		🔛 Save	💢 Close
Email Notification			
Criteria			
Mode :			~
Details			
Email Template :	🛩 🔄 Email Connection :		¥ 🖂
Reply-To :			
To :			
Cc:			
Bcc :			
Subject :			
Body :			
Save	K Close		

Email Notification Details Field Descriptions

The following table describes the fields and buttons on Email Notification Details.

Field Name	Description
Criteria	This section contains criteria for sending the notification.
Mode	 Options: Offline = Trigger the notification when the cluster node goes offline. Active = Trigger the notification when the cluster node becomes active. Passive = Trigger the notification when the cluster node becomes passive.
Details	This section contains assorted detailed information about the notification.

Email Template	Name of an Email template defined in an Email Template Details. An Email template allows you to specify standard recipients and text for outgoing emails. Enter the name of an existing Email template, select an Email template from the drop-down list, or click the Details icon to create a new Email template. Every Email template specifies an Email connection. If you do not specify an Email template in this field, you must specify an Email connection in the Email Connection field. If you specify both an Email template (in this field) and an Email Connection, the Email server specified in the Email Connection field. (Any information specified in an Email task overrides what is specified in an Email template.)
Email Connection	Required if an Email Template is not specified in the Email Template field; name of an Email Connection. An Email Connection specifies information about an email server. Enter the name of an existing Email Connection, or click the magnifying glass to browse for an existing Email Connection or create a new Email Connection. If you specify both an Email Template and an Email Connection (in this field), the Email Connection specified in this field overrides the Email Connection specified in the Email Template field.
Reply-To	Email address of the sender. Use commas to separate multiple recipients. Variables and functions supported.
То	Email address of the recipient. Use commas to separate multiple recipients. Variables and functions supported.
СС	Email address of the party being sent a copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
BCC	Email address of the party being sent a blind (hidden) copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
Subject	Subject line of the email. Variables and functions supported.
Body	Text of the email message. Variables and functions supported. If both the email template and the email task contain text in the body, the text is appended.
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.
Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.

SNMP Notification Details

SNMP Notification D	tails			
		🐺 Save	💥 Clo	se
SNMP Notification				
Criteria				
Mode	:		~	
Details] =
SNMI Manager			~	
F Save	Close			- -

SNMP Notification Details Field Descriptions

The following table describes the fields and buttons on SNMP Notification Details.

Field Name	Description
Criteria	This section contains criteria for sending the notification.
Mode	 Options: Offline = Trigger the notification when the cluster node goes offline. Active = Trigger the notification when the cluster node becomes active. Passive = Trigger the notification when the cluster node becomes passive.
Details	This section contains assorted detailed information about the notification.
SNMP Manager	The SNMP Manager that will receive the SNMP notification.
Notification Severity	Severity of this notification. Options: Normal (1) Warning (2) Minor (3) Major (4) Critical (5)
Buttons	This section identifies the buttons displayed above and below the Notification Details that let you perform various actions.
Save button	Submits the new record to the database.
Update	Saves updates to the record.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this notification.

Virtual Resources

- Overview
- Using a Virtual Resource
- Creating a Virtual Resource
 - Virtual Resource Details
 - Virtual Resource Details Field Descriptions
- Assigning Tasks to a Virtual Resource
- Resetting a Renewable Virtual Resource

Overview

A virtual resource allows you to set up a throttling scheme that will manage the number of specific tasks that can run at one time.

Using a Virtual Resource

Outlined below is the basic procedure and processing flow for using a virtual resource:

Step 1	Create a virtual resource.
	There are three types of virtual resources:
	 Renewable: Resources that renew; that is, when a task has finished using them, they can be returned and made available to other tasks sharing the same resources. Boundary: Resources that are like "windows." Only those tasks defined to fit through that window (or Resource Limit) will run. For example, if you define a Boundary Resource with Resource Limit of 5, and Task A requires a window (amount) of 5, Task B requires a window (amount) of 5, and Task C requires a window (amount) of 10, both A and B will run. However, C will go into a Resource Wait state. If the Boundary Resource is updated to a Resource Limit of 10, C will run. Depletable: Resources that do not renew. Once consumed by a task, they are gone.
Step 2	Assign a resource limit to the virtual resource as appropriate for the resource type.
Step 3	Assign tasks to the virtual resource.
Step 4	Specify the number of resource units that each task will consume. For example, a task that requires a small amount of processing power might consume one unit; a task that requires a high amount of resources might consume three units. The number of units you specify for each task is relative to the maximum number that you assign to the resource.
Step 5	Save the virtual resource record.
Step 6	When a task with a virtual resource requirement launches, Universal Controller checks the virtual resource record to see if enough units are available to run the task, based on what other tasks assigned to that virtual resource are currently running.
	 If enough units are available, the task runs and the number of available units is decremented by the amount specified in the task. For example, if the resource has a maximum of ten and the task uses two, the remaining amount available on that virtual resource for use by other tasks is eight.
	 If there are not enough units available, the task is put into Resource Wait status and is listed in the Outstanding Requests tab in the virtual resource. When the required amount of resource becomes available, the task is launched. If multiple tasks are in Resource Wait status, the virtual resource priority is used to determine which task will be first to acquire the resource when it becomes available.
Step 7	Tabs on the Virtual Resource record keep track of tasks that are currently "running" on this virtual resource and tasks that are waiting to "run" on this virtual resource.

Creating a Virtual Resource

	es 🗵						
✓ 5 Virtual Re	OUTCOR		Custom Filter None	_		✓ Silter	🔽 Go To 🙅 New 🍣
Resource		Resource Type	Resource Description	Resource Limit R	esource lle		Updated
_	ch-virtualresource-01	Renewable		10	0	stonebranch-user-02	2014-06-13 15:26:49 -0400
_	ch-virtualresource-02	Renewable		10	0	stonebranch-user-01	2014-06-13 15:26:54 -0400
_	ch-virtualresource-03	Renewable		10	0	stonebranch-user-02	2014-06-13 15:26:58 -0400
stonebran	ch-virtualresource-04	Renewable		10	0	stonebranch-user-01	2014-06-13 15:27:01 -0400
stonebran	ch-virtualresource-05	Renewable		10	0	stonebranch-user-02	2014-06-13 15:27:05 -0400
Virtual Reso							🔚 Save 📄 New
Virtual Resou	rce Tasks 0 (Currently In Use By 🛛 🔍 🕻	Outstanding Requests 🛛 🔍 Ve	rsions			
Details -							
Resou	ce Name :			Version :	1		
Reso	urce Type : Renewable		~	Resource Limit :	10		
	Resource escription :						
	Member of						
Business							*
Resou	rce Used : 0						
Sa	re New						
		ew Virtual Resou May in boldface .	urce, using the field	d descriptions b	elow a	s a guide.	
• Re • De	fault values for fie	elds, if available	, display automatic screen, you can ter	-	he list.		

Virtual Resource Details

The following Virtual Resource Details is for an existing Virtual Resource. See the field descriptions, below, for a description of all fields that display in the Virtual Resource Details.

							Update	🇊 Delete	😫 Refresh	💥 Clo
rtual Resource 🛛 😐	Tasks	Currently In Use By	Outstanding Requests	Versions						
Details										
Resource Name	stonebranch	n-virtualresource-01			Version :	1				
Resource Type	Renewable		~	Reso	Irce Limit :	10				
Resource Description										
Member o Business Services										~
Resource Used	0]								

🔥 Note

This sample Virtual Resource Details shows a Resource Limit of 1. Because each task has a minimum value of 1, this virtual resource would be limited to running only one task at a time.

Virtual Resource Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the Virtual Resource Details.

Field Name	Description
Details	This section contains detailed information about the Virtual Resource.
Resource Name	Name used within the Controller to identify this resource. Up to 40 alphanumerics. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Resource Type	Type of resource. Options: • Renewable • Boundary • Depletable
Resource Limit	Maximum number of units available for this resource.
Resource Description	Description of this virtual resource.
Member of Business Services	User-defined; allows you to select one or more Business Services that this record belongs to.
Resource Used	If Resource Type = Renewable; system-supplied. Number of units currently in use, as of the time you opened the record.
Buttons	This section identifies the buttons displayed above and below the Virtual Resource Details that let you perform various actions.
Save	Saves a new record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new Virtual Resource record.

Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this record.
Tabs	This section identifies the tabs across the top of the Virtual Resource Details that provide access to additional information about the Virtual Resource.
Tasks	Lists tasks that are assigned to this virtual resource.
Currently In Use By	Lists the task instances that have acquired this virtual resource and the number of units acquired, at the time you opened this virtual resource record.
Outstanding Requests	Lists the task instances that are currently waiting to acquire this virtual resource, and the number of units required for each waiting task instance, at the time you opened this record.
Versions	Stores copies of all previous versions of the current record. See Record Versioning.

Assigning Tasks to a Virtual Resource

▲ Note You can also assign a task to a virtual resource from a task Details. Open the Virtual Resource record that you want to assign tasks to. Step 1 Step 2 Click the Tasks tab. A list of any tasks assigned to the Virtual Resource displays. Virtual Resource Details: stonebranch-virtualresource-01 Virtual Resource Tasks
 Currently In Use By
 Outstanding Requests
 Versions Edit 2 Task Å Amount Updated By Updated 2014-07-02 13:22:42 -0400 stonebranch-linuxunixtask-01 stonebranch-user-02 1 stonebranch-linuxunixtask-02 stonebranch-user-01 2014-07-02 13:22:43 -0400

	Edit Members					
		Collection			Tasks List	
	stone	Linux/Un	ix 🗸 🌱		stonebranch-virtualresource-0)1
	Task Name *	Туре		Amount	Task Name *	<u> </u>
	stonebranch-linuxunixtask-03	Linux/Un	ix	1	stonebranch-linuxunixtask-01	
	stonebranch-linuxunixtask-04	Linux/Un		1	stonebranch-linuxunixtask-01	
	stonebranch-linuxunixtask-05	Linux/Un			stonebranch-inuxunixtask-uz	
				→		
				+		
				•		
				••		
			Save	Cance		
T	The Tasks List win o filter the Tasks listed in th	dow lists tasks the collection win	hat refer to this	s virtual resou do either or b	both of the following:	unance of characters will
T	 The Tasks List wind o filter the Tasks listed in th Enter characters in the list. 	dow lists tasks the Collection win	hat refer to this ndow, you can ove the Task N	s virtual resou do either or t Name column	urce. both of the following: . Only tasks containing that seq	quence of characters will
- To	 The Tasks List wind o filter the Tasks listed in the Enter characters in the 	dow lists tasks the Collection win	hat refer to this ndow, you can ove the Task N	s virtual resou do either or t Name column	urce. both of the following: . Only tasks containing that seq	quence of characters will
	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type fr 	dow lists tasks the Collection win the text field abo	hat refer to this ndow, you can ove the Task N wn list above t	do either or t Name column he Type colu	urce. both of the following: . Only tasks containing that seq	-
	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the virtual of the virtual o	dow lists tasks the Collection win the text field abo om the drop-dow al Resource, mo	hat refer to this adow, you can ove the Task N wn list above t	do either or the Name column he Type column the Collect	urce. both of the following: . Only tasks containing that seq mn. c tion window to the Tasks List	-
	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type fr 	dow lists tasks the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click	hat refer to this adow, you can ove the Task N wn list above t ove the task fro it or click it on	do either or the Name column he Type column the Collect ce and then c	urce. both of the following: . Only tasks containing that seq mn. c tion window to the Tasks List slick the -> arrow.	-
	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the virtual of the virtual o	dow lists tasks the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the	hat refer to this adow, you can ove the Task N wn list above t ove the task fro it or click it on em and then c	do either or the Name column he Type column the Collect ce and then c	urce. both of the following: . Only tasks containing that seq mn. c tion window to the Tasks List slick the -> arrow.	-
5 To	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the select a task to the Virtuant of the virtuant of the select a single ta 2. To move a single ta 3. To move all tasks, or the virtual tasks,	dow lists tasks the Collection win the text field abor om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow	hat refer to this adow, you can ove the Task N wn list above t ove the task fro it or click it on em and then c v.	do either or the Name column he Type column the Type column from the Collec ce and then collick the > arrow	urce. both of the following: . Only tasks containing that seq mn. ction window to the Tasks List click the -> arrow. bw.	window:
5 To	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the select a task to the Virtuant of the virtuant of the select a single ta 2. To move a single ta 3. To move all tasks, or the virtual tasks,	dow lists tasks the Collection win the text field abor om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow	hat refer to this adow, you can ove the Task N wn list above t ove the task fro it or click it on em and then c v.	do either or the Name column he Type column the Type column from the Collec ce and then collick the > arrow	urce. both of the following: . Only tasks containing that seq mn. c tion window to the Tasks List slick the -> arrow.	window:
5 To	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the select a task to the Virtuant of the virtuant of the select a single ta 2. To move a single ta 3. To move all tasks, or the virtual tasks,	dow lists tasks the ne Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r	hat refer to this adow, you can ove the Task N wn list above the ove the task from it or click it on em and then co v. move the task	do either or t Name column he Type colu om the Collec ce and then o lick the > arro from the Tas	urce. both of the following: . Only tasks containing that seq mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect	window:
5 To	 The Tasks List wind o filter the Tasks listed in th Enter characters in the list. Select a task type fr o assign a task to the Virtue 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Virtue 1. To move a single ta 2. To move a single ta 3. To move a single ta 	dow lists tasks the ne Collection win the text field about om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the	hat refer to this adow, you can ove the Task N wn list above the remand then cov. move the task it or click it on- em and then cov.	do either or t Name column he Type colu om the Collect ce and then o click the > arro from the Tas ce and then o	urce. both of the following: . Only tasks containing that seq mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow.	window:
5 To	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type fr o assign a task to the Virtue 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Virtue 1. To move a single ta 	dow lists tasks the ne Collection win the text field about om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the	hat refer to this adow, you can ove the Task N wn list above the remand then cov. move the task it or click it on- em and then cov.	do either or t Name column he Type colu om the Collect ce and then o click the > arro from the Tas ce and then o	urce. both of the following: . Only tasks containing that seq mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow.	window:
5 To	 The Tasks List wind o filter the Tasks listed in th Enter characters in the list. Select a task type fr o assign a task to the Virtue 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Virtue 1. To move a single ta 2. To move a single ta 3. To move a single ta 	dow lists tasks the ne Collection win the text field about om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the	hat refer to this adow, you can ove the Task N wn list above the remand then cov. move the task it or click it on- em and then cov.	do either or t Name column he Type colu om the Collect ce and then o click the > arro from the Tas ce and then o	urce. both of the following: . Only tasks containing that seq mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow.	window:
і Та Та і Ті	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the Select a task type from the list. Select a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or the unassign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move a single ta 2. To move a single ta 2. To move a single ta 3. To	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collect ce and then co cick the > arrow from the Tas ce and then co cick the < arrow cick the < arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click th	window: ion window: ne icon next to the Task r
і Та Та і Ті	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the Select a task type from the list. Select a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or the unassign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move a single ta 2. To move a single ta 2. To move a single ta 3. To	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw.	window: ion window: ne icon next to the Task r
і Та Та і Ті	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the Select a task type from the list. Select a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or the unassign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move a single ta 2. To move a single ta 2. To move a single ta 3. To	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click th	window: ion window: ne icon next to the Task r
i Ta	 The Tasks List wind o filter the Tasks listed in the Enter characters in the list. Select a task type from the Select a task type from the list. Select a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or the unassign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move a single ta 2. To move a single ta 2. To move a single ta 3. To	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the Enter characters in a in the list. Select a task type fr o assign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Virtual 1. To move a single ta 2. To move a single ta 3. To move a single ta 2. To move a single ta 3. To move a single ta 4. To move a single ta 5. To move a single ta 6. To move a single ta 6. To move a single ta 6. To move all tasks, or 6. To move all tasks, or 	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: he icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the Enter characters in a in the list. Select a task type fr o assign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Virtual 1. To move a single ta 2. To move a single ta 3. To move a single ta 2. To move a single ta 3. To move a single ta 4. To move a single ta 5. To move a single ta 6. To move a single ta 6. To move a single ta 6. To move all tasks, or 6. To move all tasks, or 	dow lists tasks the Collection win the Collection win the text field abo om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the sks, Ctrl-click the lick the << arrow h task assigned	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in th Enter characters in the list. Select a task type fr o assign a task to the Virtual 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Viri 1. To move a single ta 2. To move a single ta 3. To move all tasks, or o unassign a task to the Viri 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or o unassign a task to the Viri 1. To move a single ta 2. To move multiple ta 3. To move all tasks, or 	dow lists tasks the Collection win the Collection win the text field abor om the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the lick the >> arrow rtual Resource, r sk, double-click sks, Ctrl-click the lick the << arrow h task assigned click anywhere in	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the list. Enter characters in the list. Select a task type fr o assign a task to the Virtual To move a single ta To move all tasks, c o unassign a task to the Vir To move a single ta To move all tasks, c 	dow lists tasks the Collection winthe text field abort on the drop-dow on the drop-dow al Resource, mosk, double-click the sks, Ctrl-click the sks	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the list. Enter characters in the list. Select a task type fr o assign a task to the Virtual To move a single ta To move a single ta To move all tasks, or o unassign a task to the Virtual ass, or o unassign a task to the Virtual ass, or To move a single ta To move all tasks, or 	dow lists tasks the Collection winthe text field abort on the drop-dow on the drop-dow al Resource, mosk, double-click the sks, Ctrl-click the sks	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the list. Enter characters in the list. Select a task type fr o assign a task to the Virtual To move a single ta To move all tasks, c o unassign a task to the Vir To move a single ta To move all tasks, c 	dow lists tasks the Collection winthe text field abort on the drop-dow on the drop-dow al Resource, mosk, double-click the sks, Ctrl-click the sks	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays
i Ta	 The Tasks List wind o filter the Tasks listed in the list. Enter characters in the list. Select a task type fr o assign a task to the Virtual To move a single ta To move a single ta To move all tasks, or o unassign a task to the Virtual ass, or o unassign a task to the Virtual ass, or To move a single ta To move all tasks, or 	dow lists tasks the Collection winthe text field abort on the drop-dow al Resource, mo sk, double-click sks, Ctrl-click the sk	hat refer to this adow, you can ove the Task N wn list above t it or click it on em and then c w. move the task it or click it on em and then c v. to a Virtual Re	s virtual resound do either or the Name column he Type column the Type column or the Collec ce and then co ce and then co ce and then co cick the - arrow	urce. both of the following: . Only tasks containing that see mn. ction window to the Tasks List click the -> arrow. bw. ks List windows to the Collect click the <- arrow. bw. To change the Amount, click the al Resource Details pop-up disp	window: ion window: ne icon next to the Task r plays

Step 7 Click Save.

Resetting a Renewable Virtual Resource

You can reset the Resource Used amount of a Renewable virtual resource to accurately reflect the actual number of resources currently in use.

Resetting a **Renewable** virtual resource requires the ops_admin role.

(For **Boundary** and **Depletable** virtual resources, the Resource Used amount is always reset to 0, as it does not apply to these types of virtual resources.)

v Custom Filter - None v V Filter © O To New Resource Name ^ Resource Type Resource Link Resource	~							
stonebranch-virtualresource-01 Renewable 10 0 stonebranch-virtualreso 2014-06-13 15:26:49-040 stonebranch-virtualreso Open 10 0 stonebranch-virtualreso 2014-06-13 15:26:58-040 stonebranch-virtualreso Wew Bundles 10 0 stonebranch-user-02 2014-06-13 15:26:58-040 stonebranch-virtualreso Wew Bundles 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 stonebranch-virtualreso Wew Bundles 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 stonebranch-virtualreso Wew Bundles 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 stonebranch-virtualresource Promote Image: Control of the stonebranch-user-02 2014-06-13 15:27:05-040 stonebranch-user-02 2014-06-13 15:27:05-040 Image: Control of the stonebranch-user-02 2014-06-13 15:27:05-040 Image: Control of the stonebranch-user-02 Image: Control of the stonebranch-user-02 2014-06-13 15:27:05-040 Image: Control of the stonebranch-user-02 Image: Control of the stonebranch-user-01				Custom Filter No	ine		✓ V Filter	🔁 Go To 🛛 🙅 New
Stonebranch-virtualreso Open 0 stonebranch-user-01 2014-06-13 15-26:58-040 Stonebranch-virtualreso View Bundles 10 0 stonebranch-user-02 2014-06-13 15-26:58-040 Stonebranch-virtualreso View Bundles 10 0 stonebranch-user-02 2014-06-13 15-26:58-040 Stonebranch-virtualreso View Bundles 10 0 stonebranch-user-01 2014-06-13 15-27:01-040 Stonebranch-virtualreso Add To Bundle 10 0 stonebranch-user-02 2014-06-13 15-27:05-040 Promote Promote Promote Promote Promote Promote Reset Virtual Resource Promote Promote Promote Promote Promote Reset Virtual Resource Promote Promote Promote Promote Promote Reset Virtual Resource Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote Promote				Resource Description			Updated By	
Stonebranch-virtualres Open 10 0 stonebranch-virtualres 2014-06-13 15:26:58-040 Stonebranch-virtualres Wew Bundles 10 0 stonebranch-user-01 2014-06-13 15:27:01-040 Stonebranch-virtualres Add To Bundle Promote 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-virtualres Image: Stonebranch-virtualres Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-virtualres Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-virtualres Promote Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-virtualres Image: Stonebranch-user-02 Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-user-02 Image: Stonebranch-user-02 Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-			Renewable					
Stonebranch-virtualreso Wew Bundles 10 0 stonebranch-user-01 2014-06-13 15:27:01-040 Stonebranch-virtualreso Add To Bundle 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 Image: Reset Virtual Resource Image: Reset Virt		Den Open						
Image: Stonebranch-virtualess Image: Wew Bundles 10 0 stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-virtualess Image: Stonebranch-user-02 Image: Stonebranch-user-02 2014-06-13 15:27:05-040 Image: Stonebranch-user-0<			_					
Vrtual Resource Details V Vrtual Resource Details V Vrtual Resource Details V Vrtual Resource Details Refresh Selection V Vrtual Resource Details Refresh Selection V Vrtual Resource Details Resource Name: Resource Type: Renewable Resource Limit: 10 Resource Services:		👘 View Bundle						
Vrtual Resource Details Vrtual Resource Type: Renewable Resource Limit: 10 Resource Limit: 10 Resource Limit: 10 New Second Se		Min Add To Bund	le					
Virtual Resource Details Virtual Resource Details Image: Currently In Use By Outstanding Requests Versions Version : 1 Resource Type : Renewable Resource Limit : 10 Resource Type : Renewable Image: Currently in Use By Image: Currently in Use By Details Image: Currently in Use By Details Image: Currently in Use By Details Image: Currently in Use By Details Image: Currently in Use By Resource Image: Currently in Use By Resource Image: Currently in Use By Resource Image: Currently in Use By Image: Currently in Use By Image: Currently in Use By Imag		Promote						
Virtual Resource Details Virtual Resource Details Image: Currently in Use By Outstanding Requests Versions Virtual Resource Name : Version : 1 Resource Type : Renewable Resource Limit : 10 Resource Type : Member of Business Services : Image: Currently in Use By Image: Currently in Use By			Recource					
Virtual Resource Details Virtual Resource Details Virtual Resource Details Virtual Resource Details Virtual Resource Name : Version : Resource Name : Version : Resource Type : Resource Type : Resource Limit : 10 Business Services :		Teset viitua						
Virtual Resource Details Virtual Resource Details Image: Update New Image:		Delete						
Virtual Resource Details Virtual Resource Details Virtual Resource Type: Resource Name: Version: 1 Resource Type: Renewable Resource Limit: 10 Resource Type: Renewable Resource Limit: 10 Resource Services:								
Virtual Resource Details Virtual Resource Details Update New @ Delete Second Details Outstanding Requests Versions Resource Name: Version : 1 Resource Type: Renewable Resource Limit : 10 Resource Description : Member of Business Services : Version : 1		 Details 	•					
Virtual Resource Tasks Currently in Use By Outstanding Requests Versions Details Resource Name : Version : 1 Resource Type : Renewable Resource Limit : 10 Resource Type : Renewable Resource Limit : 10 Member of Business Services : Version : Version : 10		👍 Refresh Sel	ection					
Virtual Resource Tasks Currently in Use By Outstanding Requests Versions Details Resource Name : Version : 1 Resource Type : Renewable Resource Limit : 10 Resource Type : Member of Business Services : Version : 10								• ~
Details Resource Name : Version : 1 Resource Type : Renewable Resource Limit : 10 Resource Description :	 Virtual Resource Details 						🔚 Update 📃 I	New 🏢 Delete 📑 Ref
Resource Name : Version : 1 Resource Type : Renewable Resource Limit : 10 Member of Business Services : Image: Service serv	Virtual Resource	Tasks © Curre	ntly In Use By 🛛 🔍	Outstanding Requests 😐	Versions			
Resource Type : Renewable w Resource Limit : 10 Resource Description :	Details							
Resource Description : Member of Business Services :	Resource Name :				Version :	1		
Description : Member of Business Services :	Resource Type :	Renewable		~	Resource Limit :	10		
Member of Business Services :								
Business Services :								
Resource Used: 0								*
	Resource Used :	0						
		New	🕼 Delete	S Refresh				
🚼 Update 📃 New 🕼 Delete 🔄 🔄 Refresh	Update							

Scripts

- Overview
 Creating a
 - Creating a Script
 - Script Details
 - Script Details Field Descriptions
- Uploading a Script

Overview

Scripts allows you to store scripts in the Universal Controller database.

There are three types of scripts:

- Scripts
- UDM scripts
- SAP definition files

When a task that specifies a script is executed, the script is transmitted to the remote machine for execution.

🔥 Note

There is a 1MB limit on the content size of scripts, whether the content is defined in the Script Details or a uploaded from a local file system (see Uploading a Script, below).

You can use scripts with the following task types: Windows, Linux/Unix, SAP, and File Transfer (UDM scripts for UDM File Transfer tasks).

You cannot import compiled executables into Scripts. The content of scripts must be text that can be processed by some shell, script host, or command interpreter.

You can embed Universal Controller variables in the script content. Embedded variables are resolved at trigger/run time before the script is sent to an Agent.

Controller variables can be passed as parameters, but the script still has to be written to parse the variables. However, you cannot pass variables as parameters that contain data longer than the parameter field (for example, SQL results).

For example, the following script shows how a Controller variable could be used.

```
#!/bin/bash
echo Task Name: ${ops_task_name}
echo Task Instance: ${ops_task_id}
```

View the Scripts video to learn more about this feature.

Creating a Script

Script	s 🗵					
¥ 5 S	cripts		Custom Filter - Nor	ne	v 😽 I	Filter 🔯 Go To 🚭 New ಿ
s	icript Name 🔷	Script Type	Description	Resolve UAC Variables	Updated By	Updated
in st	tonebranch-script-01	Script		No	ops.admin	2014-06-13 15:27:44 -0400
🖂 st	tonebranch-script-02	Script		No	ops.admin	2014-06-13 15:27:55 -0400
🖂 st	tonebranch-script-03	Script		No	ops.admin	2014-06-13 15:27:58 -0400
🖂 st	tonebranch-script-04	Script		No	ops.admin	2014-06-13 15:28:01 -0400
st	onebranch-script-05	Script		No	ops.admin	2014-06-13 15:28:06 -0400
✓ Scr	ipt Details				E	🖥 Save 💼 New 🎜 Upload Script
	Script © Tasks © Not	es 🛛 🖉 Versions				
	etails					A
	Script Name :			Versi	on : 1	
	Description :					
	Script Type :	Porint	v.	Resolve UAC Variabl	es · 🕅	
	Content :					E
	Member of Business Services :					~
Enter /	select Details for a ne	ew script, us	ing the field description	ons below as a guide	Э.	
	 Required fields disp Default values for fields 	lay in boldf a elds, if availa	ace. able, display automat	ically.		
o dis	play more of the Detai	ls fields on t	he screen, you can te	emporarily hide the li	st.	
	Note	t Details for	an existing script by	clicking a script in th	e list, and ther	want to create a new scr

Script Details

The following Script Details is for an existing script. See the field descriptions, below, for a description of all fields that display in the Script Details.

pt Details: stonebranch-script-01		
	🗒 Update 🎜 Upload Script 🎲 Delete 🕼 Refresh 🎇	Close
Script © Tasks © No	tes Versions	
Details		_
Script Name :	stonebranch-script-01 Version : 1	
Description :		
Script Type :	Script Resolve UAC Variables :	
Content :		
Content.		
Member of Business Services :		*
🗑 Update 🛛 🛃 Upload Script	🗊 Delete 🛛 🛱 Refresh 🛛 💥 Close	

Script Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the Script Details.

Field Name	Description
Details	This section contains detailed information about the Script.
Script Name	Name of the script. This name can be the same as the name of the script file. You also can specify a file extension; the default file extension for Windows is .bat.
	If the name has the extension .ps1, Windows will run the script as a powershell script. You may have to create the appropriate file association and security for this to work.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Description	User-defined; description of this record. (Maximum = 200 characters.)
Script Type	Type of script. Options: • Script (for use in Windows or Linux/Unix tasks) • SAP Definition (for use in SAP tasks) • UDM Script (for use in UDM File Transfer tasks)

Resolve UAC Variables	Controls whether or not the Script will be parsed in pursuit of Universal Controller variables. It allows the Controller to avoid the overhead of parsing a Script that does not contain variables.
	Note Variables <i>could</i> be embedded with this field disabled; likewise, you could have a Script with no variables but have this field enabled. However, enabling this field for a Script that does not contain Controller variables will impose an unnecessary burden (however small) on the Controller.
Content	Content of the script or SAP definition file.
	You can enter content manually or upload content from the local file system by using the Upload Script button.
	For UDM Scripts, Source and Destination credentials are available for use. The credentials can be coded into the UDM script using the following File Transfer variables:
	 ops_src_cred_user ops_src_cred_pwd ops_dst_cred_user ops_dst_cred_pwd
	The variables will be resolved by UDM internally. The following example illustrates the correct way to code them:
	<pre>open src=srcserver user=\$(ops_src_cred_user) pwd=\$(ops_src_cred_pwd) dst=dstserver user=\$(ops_dst_cred_user) pwd=\$(ops_dst_cred_pwd)</pre>
Buttons	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in
	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line.
Save	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions.
Save Update	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database.
Save Update New Upload	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record.
Save Update New Upload Script	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script.
Save Jpdate New Jpload Script Delete	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script. Allows you to upload a script from the local file system and place it in the Content field (see Uploading a Script, below).
Save Jpdate New Jpload Script Delete Refresh	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script. Allows you to upload a script from the local file system and place it in the Content field (see Uploading a Script, below). Deletes the current record.
Save Update New Upload Script Delete Refresh Close	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script. Allows you to upload a script from the local file system and place it in the Content field (see Uploading a Script, below). Deletes the current record. Refreshes any dynamic data displayed in the Details.
Save Update New Upload Script Delete Refresh Close Tabs	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script. Allows you to upload a script from the local file system and place it in the Content field (see Uploading a Script, below). Deletes the current record. Refreshes any dynamic data displayed in the Details. For pop-up view only; closes the pop-up view of this task.
Buttons Save Update New Upload Script Delete Refresh Close Tabs Tasks Notes	The values for these variables are sent to UDM via stdin. This provides a secure channel where the credentials never show up in the script or on the command line. This section identifies the buttons displayed above and below the Script Details that let you perform various actions. Saves a new script record in the Controller database. Saves updates to the record. Displays empty (except for default values) Details for creating a new script. Allows you to upload a script from the local file system and place it in the Content field (see Uploading a Script, below). Deletes the current record. Refreshes any dynamic data displayed in the Details. For pop-up view only; closes the pop-up view of this task. This section identifies the tabs across the top of the Script Details that provide access to additional information about the script.

Uploading a Script

To upload a script into the Content field in the Script Details:

Step 1	Click the Upload Script button. The Script File Uploader pop-up displays.
	Script File Uploader
	Select a file Browse_ No file selected.
	Select file encoding ISO-8859-1
	Submit Cancel
Step 2	Click the Browse button and select a script from the local file system.
Step 3	From the Select file encoding drop-down list, select the character set of the script: ISO-8859-1, US-ASCII, UTF-8, UTF-16, UTF-16BE, or UTF-16LE.
Step 4	Click the Submit button to add the script to the Content field.

Email Templates

- Overview
- Creating an Email Template
 - Email Template Details
 - Email Template Details Field Descriptions

Overview

Email templates allow you to construct commonly-used information that can be copied to create Email tasks.

If an Email task specifies a template, Universal Controller uses the information in the template to construct and execute the Email task. Any information specified in the task overrides what is specified in the template.

Creating an Email Template

 5 Email Templates Template Name * stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 	2 stonebranch@stonebranch 3 stonebranch@stonebranch 4 stonebranch@stonebranch	ch.com ch.com ch.com	None Subject	Updated By stonebranch-user- stonebranch-user- stonebranch-user- stonebranch-user-	Updated user-01 2014-06 user-02 2014-06 user-03 2014-06 user-04 2014-06	Qo To O New Updated 2014-06-13 15:31:14 -0400 2014-06-13 15:31:25 -0400 2014-06-13 15:31:23 -0400 2014-06-13 15:31:43 -0400 2014-06-13 15:31:43 -0400
stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0	stonebranch@stonebranct stonebranch@stonebranct stonebranch@stonebranct stonebranch@stonebranct stonebranch@stonebranct	ch.com ch.com ch.com ch.com	Subject	stonebranch-user- stonebranch-user- stonebranch-user- stonebranch-user-	user-01 2014-06- user-02 2014-06- user-03 2014-06 user-04 2014-06	2014-06-13 15:31:14 -0400 2014-06-13 15:31:25 -0400 2014-06-13 15:31:32 -0400 2014-06-13 15:31:32 -0400 2014-06-13 15:31:43 -0400
stonebranch-emailtemplate-0 stonebranch-emailtemplate-0 stonebranch-emailtemplate-0	2 stonebranch@stonebranch 3 stonebranch@stonebranch 4 stonebranch@stonebranch	ch.com ch.com ch.com		stonebranch-user- stonebranch-user- stonebranch-user-	user-02 2014-06 user-03 2014-06 user-04 2014-06	2014-06-13 15:31:25 -0400 2014-06-13 15:31:32 -0400 2014-06-13 15:31:43 -0400
stonebranch-emailtemplate-0 stonebranch-emailtemplate-0	3 stonebranch@stonebranch 4 stonebranch@stonebranch	ch.com ch.com		stonebranch-user- stonebranch-user-	user-03 2014-06- user-04 2014-06-	2014-06-13 15:31:32 -0400 2014-06-13 15:31:43 -0400
stonebranch-emailtemplate-0	4 stonebranch@stonebranch	ch.com		stonebranch-user-	user-04 2014-06-	2014-06-13 15:31:43 -0400
stonebranch-emailtemplate-0	5 stonebranch@stonebranch	sh.com		stonebranch-user-	iser-05 2014-06-	2014-06-13 15:31:49 -0400
4			III			
t ✓ Email Template Details Email Template ● Versions			111,			识 Save 🗖 Nev
Email Template Details			11			
Email Template Details Email Template Versions			" Version	n: 1		
Email Template Details Email Template Otails Details				n :1		
Email Template Details Email Template Versions Details Template Name : Email Connection :				n : 1		Save Nev
Email Template Details Email Template Oetails Template Name :				n : 1		Save Nev
Email Template Details Email Template Versions Details Template Name : Email Connection :				n : 1		Save Nev
Email Template Details Email Template Versions Details Template Name : Email Connection : Reply-To :				n : 1		Save Nev
Email Template Details Email Template Versions Details Template Name : Email Connection : Reply-To :				n :1		Save Nev
Email Template Details Email Template Versions Details Template Name : Email Connection : Reply-To :				n :1		Save Nev
Email Template Details Email Template Oversions Details Template Name : Email Connection : Reply-To : To : To :				n : 1		Save Nev

Step 2	• R • D	ect Details for a new Email Template, using the field descriptions below as a guide. equired fields display in boldface . efault values for fields, if available, display automatically. more of the Details fields on the screen, you can temporarily hide the list.
	۸	Note If you view Email Template Details for an existing Email Template by clicking an Email Template in the list, and then want to create a new Email Template, you must click the New button that displays above and below the Details.
Step 3	k the S bled.	Save button. The Email Template is added to the database, and all buttons and tabs in the Email Template Details are

Email Template Details

The following Email Template Details is for an existing Email Template. See the field descriptions, below, for a description of all fields that display in the Email Template Details.

mail Template Details:	stonebranch-emailtemplate-01					_	
			🔚 Update	🕼 Delete	S Refresh	X Clos	e
Email Template 🛛 Ve	rsions						
- Details							1
Template Name :	stonebranch-emailtemplate-01 Version :	1					
Email Connection :	stonebranch-emailconnection-01					♥ 13	
Reply-To :							
To :	stonebranch@stonebranch.com						
Cc:							
Bcc :							
Subject :							
Body :							
\Bigg Update	🗊 Delete 🛛 🕒 Refresh 🛛 🗱 Close						

Email Template Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the Email Template Details.

Field Name	Description
Details	This section contains detailed information about the Email Template.
Template Name	Name used within the Controller to identify this resource. Up to 40 alphanumerics. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Email Connection	Required; name of an Email connection defined via the Email Connection Details. An email connection specifies information about an email server. Enter the name of an existing Email connection, select an Email Connection from the drop-down list of all existing Email Connections, or click the Details icon to create an Email Connection.

Reply-To	Email address of the sender. Use commas to separate multiple recipients. Variables and functions supported.
То	Email address of the recipient. Use commas to separate multiple recipients. Variables and functions supported.
СС	Email address of the party being sent a copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
BCC	Email address of the party being sent a blind (hidden) copy of the email, if any. Use commas to separate multiple recipients. Variables and functions supported.
Subject	Subject line of the email. Variables and functions supported.
Body	Text of the email message. Variables and functions supported. If both the email template and the email task contain text in the body, the text is appended.
Buttons	This section identifies the buttons displayed above and below the Email Template Details that let you perform various actions.
Save	Saves a new Email Template record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new Email Template.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this Email Template.
Tabs	This section identifies the tabs across the top of the Email Template Details that provide access to additional information about the Email Template.
Versions tab	Stores copies of all previous versions of the current record. See Record Versioning.

Email Connections

- Overview
- Creating an Email Connection
 - Email Connection Details
 - Email Connection Details Field Descriptions

Overview

Email connections provide all of the email server information necessary for Universal Controller to send emails.

Email connections are used these ways within the Controller:

- An Email Task uses the Email connection to generate emails independent of tasks.
- An Email Notification uses the Email connection to generate notifications related to tasks.
- Agents, OMS Servers, and Cluster Nodes use the Email connection to generate email notifications.
- System Operations use Email connections to generate system notifications.

Creating an Email Connection

Dashboards 🛛 Email Connections 🖾	Custom Filter	None				
Connection Name A				v 🜄	Filter 🛛 🗔 G	o To 🖄 New 🔔
	Outgoing Mail Server (SMTP)		Email Address	User Name	Updated By	Updated
stonebranch-emailconnection-01	server 1	25	stonebranch@stonebranch.com	1	ops.admin	2014-06-13 15:30:39 -040
stonebranch-emailconnection-02	server 1	25	stonebranch@stonebranch.com	1	ops.admin	2014-06-13 15:30:45 -040
stonebranch-emailconnection-03	server 1	25	stonebranch@stonebranch.com	l.	ops.admin	2014-06-13 15:30:48 -040
stonebranch-emailconnection-04	server 1	25	stonebranch@stonebranch.com	l.	ops.admin	2014-06-13 15:30:54 -040
stonebranch-emailconnection-05	server 1	25	stonebranch@stonebranch.com		ops.admin	2014-06-13 15:30:59 -040
4		m				
↓ ✓ Email Connection Details		111			Save 🥅 N	ew 📷 Test Connection
	ns	m		Ē	Save 📃 N	
Email Connection Details	ns	111) Save 🚍 N	
Email Connection Details Email Connection Email Tasks Version	ns			T.	Save 📃 N	
Email Connection Details Email Connection Email Tasks	ns	III			Save 📩 N	
	ns	III		T.	Save 📑 N	
Email Connection Details Email Connection Details Connection Name : Outgoing Mail Server (SMTP) :	ns	III] Save 📃 N	

Step 2	• R • D	ect Details for a new Email Connection, using the field descriptions below as a guide. equired fields display in boldface . efault values for fields, if available, display automatically. more of the Details fields on the screen, you can temporarily hide the list.
	۸	Note If you view Email Connection Details for an existing Email Connection by clicking an Email Connection in the list, and then want to create a new Email Connection, you must click the New button that displays above and below the Details.
Step 3	k the S bled.	Save button. The Email Connection is added to the database, and all buttons and tabs in the Email Connection Details are

Email Connection Details

The following Email Connection Details is for an existing Email Connection. See the field descriptions, below, for a description of all fields that display in the Email Connection Details.

Email Connection Details	s: stonebranch-emailconnection-01	
	📳 Update 🛛 🙀 Test Connection 🍿 Delete 🕞 Refresh	X Close
Email Connection	Email Tasks Versions	
Details		
Connection Name :	stonebranch-emailconnection-01 Version : 1	
Outgoing Mail Server (SMTP) :	server 1	
SMTP Port :		
Enable SSL :		
Enable STARTTLS :		
Email Address :	stonebranch@stonebranch.com	
Authentication Required :		
Use for System Notifications :		
🔚 Update	Test Connection 🕼 Delete 🕼 Refresh 🗱 Close	

Email Connection Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the Email Connection Details.

Field Name	Description
Details	This section contains detailed information about the Email Connection.
Connection Name	Name (maximum 40 alphanumeric characters) used within the Controller to identify this resource. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller very time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Outgoing Mail Server (SMTP)	Name or IP address of the outgoing email server.
SMTP Port	Port on the machine where the email server resides.

Enable SSL	Enables SSL connectivity for your SMTP server.	
Enable STARTTLS	Enables the use of the STARTTLS command (if supported by the server) to switch the connection to a TLS-protected connection before issuing any login commands. (An appropriate trust store must be configured so that the client will trust the server's certificate.)	
Email Address	Email address of the sender.	
	Warning If the selected sender email address is invalid, or becomes invalid at any time after you create an Email Connection, all Email Notifications that specify that Email Connection will fail, but no warning will be issued. You must click the Test Connection button to test the Email Connection, which will generate an error message in the Controller Console.	
Authentication Req'd	If enabled, User Name and Password are required.	
User Name	If Authentication Req'd is enabled; user name that the Controller will use to connect to the server.	
Password	If Authentication Req'd is enabled; password that the Controller will use to connect to the server.	
Use for System Notifications	Indicates whether or not this Email Connection is to be used for system notifications.	
	Note Only one Email Connection can be used for system notifications. If this field is checked in an Email Connection Details, it will appear unchecked on all other Email Connection Details. If you then check this field in another Email Connection Details, it automatically will be unchecked from the Details in which it had been checked.	
Buttons	This section identifies the buttons displayed above and below the Email Connection Details that let you perform various actions.	
Save	Saves a new Email Connection record in the Controller database.	
Update	Saves updates to the record.	
New	Displays empty (except for default values) Details for creating a new Email Connection.	
Test Connection	After saving the record to the database, click Test Connection to run a connection test.	
Delete	Deletes the current record.	
Refresh	Refreshes any dynamic data displayed in the Details.	
Close	For pop-up view only; closes the pop-up view of this Email Connection.	
Tabs	This section identifies the tabs across the top of the Email Connection Details that provide access to additional information about the Email Connection.	
Email Tasks	Provides a list of tasks that use this email server.	
Versions	Stores copies of all previous versions of the current record. See Record Versioning.	

Database Connections

- Overview
- Creating a Database Connection
- Database Connection Details
- Database Connection Details Field Descriptions

Overview

Database Connections provide all database server information required for Universal Controller to execute an SQL task or a Stored Procedure Task.

Creating a Database Connection

	Connections 🖾							
5 Datab	base Connections			Custom	Filter None		👻 🦁 Filter	🔂 Go To 😼 New 🍣
Conn	ection Name 🔷	Database Type	Description	Connection URL	Driver	Credentials	Updated By	Updated A
stone	branch-databaseconnection-01	MySQL		jdbc:mysql:// <server>:<port330< td=""><td>06>/<database> com.mysql.jdbc.Dr</database></td><td>iver</td><td>stonebranch-user-01</td><td>2014-06-13 15:32:24 -0400</td></port330<></server>	06>/ <database> com.mysql.jdbc.Dr</database>	iver	stonebranch-user-01	2014-06-13 15:32:24 -0400
stone	branch-databaseconnection-02	MySQL		jdbc:mysql:// <server>:<port330< td=""><td>06>/<database> com.mysqLjdbc.Dr</database></td><td>iver</td><td>stonebranch-user-02</td><td>2014-06-13 15:32:32 -0400</td></port330<></server>	06>/ <database> com.mysqLjdbc.Dr</database>	iver	stonebranch-user-02	2014-06-13 15:32:32 -0400
stone	branch-databaseconnection-03	MySQL		jdbc:mysql:// <server>:<port330< td=""><td>06>/<database> com.mysql.jdbc.Dr</database></td><td>iver</td><td>stonebranch-user-03</td><td>2014-06-13 15:32:36 -0400</td></port330<></server>	06>/ <database> com.mysql.jdbc.Dr</database>	iver	stonebranch-user-03	2014-06-13 15:32:36 -0400
	branch-databaseconnection-04	MySQL		jdbc:mysql:// <server>:<port330< td=""><td>06>/<database> com.mysql.jdbc.Dr</database></td><td>iver</td><td>stonebranch-user-04</td><td>2014-06-13 15:32:39 -0400</td></port330<></server>	06>/ <database> com.mysql.jdbc.Dr</database>	iver	stonebranch-user-04	2014-06-13 15:32:39 -0400
stone	branch-databaseconnection-05	MySQL		jdbc:mysql:// <server>:<port33< td=""><td>06>/<database> com.mysql.jdbc.Dr</database></td><td>iver</td><td>stonebranch-user-05</td><td>2014-06-13 15:32:43 -0400</td></port33<></server>	06>/ <database> com.mysql.jdbc.Dr</database>	iver	stonebranch-user-05	2014-06-13 15:32:43 -0400
✓ Databa	se Connection Defails						Fi Save	New Grest Connection
		 Stored Procedure 	Tasks 0 Versions				R Save	Test Connection
Databas	e Connection SQL Tasks	Stored Procedure	Tasks 🛛 @ Versions				R Save	Test Connection
Databas — Detai	e Connection SQL Tasks	 Stored Procedure 	Taska 0 Versions		Version :	1	R Save	Test Connection
Databas — Detai	e Connection SQL Tasks ils Connection Name : Description :	 Stored Procedure 				1	E Save	
Databas	e Connection SQL Tasks Connection Name : Description : Database Type : MySQL				Version :	1	Save	New Jest Connection
Databas	e Connection SQL Tasks ils Connection Name : Description :					1	T Save	
Databas	e Connection SQL Tasks Connection Name : Description : Database Type : MySQL	/ <server>:<port330< td=""><td></td><td></td><td></td><td>1</td><td>F Save</td><td></td></port330<></server>				1	F Save	
Databas	e Connection e SQL Tasks ils Description : Database Type : MySQL Connection URL : jdbc:mysql/J	/ <server>:<port330 <br="">dbc.Driver</port330></server>				1	Save	
Databas Detai	e Connection e SQL Tasks ils Description : Database Type : MySQL Connection URL : jdbc:mysql/J Driver : com.mysql j Maximum Rows : 100	/ <server>:<port330 <br="">dbc.Driver</port330></server>	6>/ <database></database>			1	Save	

Step 2	• R • D	ect Details for a new Database Connection, using the field descriptions below as a guide. equired fields display in boldface . efault values for fields, if available, display automatically. more of the Details fields on the screen, you can temporarily hide the list.
	۸	Note If you view Database Connection Details for an existing Database Connection by clicking a Database Connection in the list, and then want to create a new Database Connection, you must click the New button that displays above and below the Details.
Step 3		Save button. The Database Connection is added to the database, and all buttons and tabs in the Database Connection e enabled.

Database Connection Details

The following Database Connection Details is for an existing Database Connection. See the field descriptions, below, for a description of all fields that display in the Database Connection Details.

abase Connection De	stails: stonebranch-databaseconnection-01	_)[□
	🔚 Update 😽 Test Connection 🎲 Delete 🔄 Refresh 💥	Clos
atabase Connection	SQL Tasks Stored Procedure Tasks Versions	
Details		
Connection Name :	stonebranch-databaseconnection-01 Version : 1	
Description :		
Database Type :	MySQL Credentials :	
Connection URL :	jdbc:mysqt:// <server>:<port3306>/<database></database></port3306></server>	
Driver :	com.mysql.jdbc.Driver	
Maximum Rows :	100	
🗐 Update	Test Connection 🕼 Delete 🕞 Refresh 🗱 Close	
🔚 Update 🔓	Test Connection	

Database Connection Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the Database Connection Details.

Field Name	Description
Details	This section contains detailed information about the Database Connection.
Connection Name	Name (maximum 40 alphanumeric characters) used within the Controller to identify this resource. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Description	Optional. Description of the database.

Database Type	Type of database.
	Options:
	 MySQL MS SQL Server Oracle DB2 Sybase SQL Anywhere Other
	Note When using the database type Other , you will need to source the JDBC driver from your database vendor. Simply place the JDBC driver .jar file into the \$TOMCAT_HOME/webapps/opswise/WEB-INF/lib directory and restart Tomcat. Format the Connection URL and Driver fields per the database vendor's documentation.
Credentials	Credentials under which an Agent runs this task. These credentials override any credentials provided in the Agent resource definition for any Agent running this task.
Connection URL	URL of the database.
	If you are using a MySQL database and want the ability to issue multiple SQL commands from a single task, you need to enable this by appending the following string to the end of the connection string:
	?allowMultiQueries=true
	For example:
	jdbc:mysql://localhost:3306/opswise?allowMultiQueries=true
Driver	Name of the JDBC driver.
Maximum Rows	If necessary, specifies a limit to the number of rows you want returned by the SQL statement.
Buttons	This section identifies the buttons displayed above and below the Database Connection Details that let you perform various actions.
Save	Saves a new Database Connection record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new Database Connection.
Test Connection	After saving the record to the database, click Test Connection to run a connection test.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this Database Connection.
Tabs	This section identifies the tabs across the top of the Database Connection Details that provide access to additional information about the Database Connection.

SQL Tasks	Lists all SQL tasks that are using this Database Connection.
Stored Procedure Tasks	Lists all Stored Procedure tasks that are using this Database Connection.
Versions	Stores copies of all previous versions of the current record. See Record Versioning.

SAP Connections

- Overview
- Creating an SAP Connection
 - SAP Connection Details
 - SAP Connection Details Field Descriptions

Overview

SAP Connections provide all the SAP server information necessary for Universal Controller to execute an SAP Task on an SAP system. These instructions assume the user is familiar with SAP.

Creating an SAP Connection

¥ 5	Connections 🖾					_					
	SAP Connections					Custom Filt	er None			🖌 🦁 Filter 🗔 G	o To 🎇 New ಿ
	Connection Name A	Connection Type	SAP ASHOST		SAP GWHOST	SAP GWSERV	SAP Instance Number	Message Server	System ID	Updated By	Updated A
_	stonebranch-sapconnection-01			client 1			instance 1			stonebranch-user-01	2014-06-13 15:34:05 -0400
_	stonebranch-sapconnection-02			client 1			instance 1			stonebranch-user-02	2014-06-13 15:34:12 -0400
	stonebranch-sapconnection-03			client 1			instance 1			stonebranch-user-03	2014-06-13 15:34:15 -0400
_	stonebranch-sapconnection-04 stonebranch-sapconnection-05			client 1			instance 1 instance 1			stonebranch-user-04 stonebranch-user-05	2014-06-13 15:34:45 -0400 2014-06-13 15:34:49 -0400
V S	AP Connection Details										🐺 Save 📃 New
	AP Connection SAP Tasks	s Ø Versions									
S/	AP Connection SAP Tasks Details	Versions									
S/		Versions					Version :	1			
S/	Details			~			Version :	1			
S/	Details Connection Name : Connection Type : Spe			~			Version :	1			
S/	Details Connection Name : Connection Type : Spe SAP ASHOST :			~		SAD I		1			
S/	Details Connection Name : Connection Type : Spe SAP ASHOST : SAP Client :			×		SAP II	istance Number :	1			
S/	Details Connection Name : Connection Type : Spe SAP ASHOST :			v		SAP II		1			
S/	Details Connection Name : Connection Type : Spe SAP ASHOST : SAP GWHOST :	ecific Application Server		×		SAP II	istance Number :	1			
S/	Details Connection Name : Connection Type : Spe SAP ASHOST : SAP Client :	ecific Application Server		×		SAP II	istance Number :	1			

	 Enter / select Details for a new SAP Connection, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. 						
		۸	Note If you view SAP Connection Details for an existing SAP Connection by clicking an SAP Connection in the list, and then want to create a new SAP Connection, you must click the New button that displays above and below the Details.				
Step 3		k the S bled.	Save button. The SAP Connection is added to the database, and all buttons and tabs in the SAP Connection Details are				

SAP Connection Details

The following SAP Connection Details is for an existing SAP Connection. See the field descriptions, below, for a description of all fields that display in the SAP Connection Details.

AP Connection Details:	stonebranch-sapconnection-01						
			📳 Update	🅼 Delete	S Refresh	洋 Clos	e
SAP Connection 8	SAP Tasks Versions						_
Details							^
Connection Name :	stonebranch-sapconnection-01	Version : 1					
Connection Type :	Specific Application Server						
SAP ASHOST :	host 1						=
SAP Client :	client 1	SAP Instance Number : instance 1					
SAP GWHOST :		SAP GWSERV :					
🔛 Update	🕼 Delete 🛛 🕞 Refresh 🛛 💥 Close						-

SAP Connection Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the SAP Connection Details.

Field Name	Description
Details	This section contains detailed information about the SAP Connection.
Connection Name	Name (maximum 40 alphanumeric characters) used within the Controller to identify this resource. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Connection Type	Type of SAP connection. Options:
	 Specific Application Server Connection to a specific SAP application server (type A RFC connection). Load Balancing Connection to an SAP system where the application server is determined by load balancing (type B RFC connection).
SAP ASHOST	If Connection Type = Specific Application Server; host name of an SAP application server. If the path to the server goes through SAP routers, prefix the host name with the SAP router string.

SAP Client	If Connection Type = Specific Application Server; SAP Client number.
SAP Instance Number	If Connection Type = Specific Application Server; SAP instance number.
SAP GWHOST	If Connection Type = Specific Application Server; host name of the SAP gateway.
SAP GWSERV	If Connection Type = Specific Application Server; service name of the SAP gateway.
System ID	If Connection Type = Load Balancing; system ID of the SAP system to which you want to connect.
Message Server	If Connection Type = Load Balancing; host name of the message server.
Group	If Connection Type = Load Balancing; application servers group name.
Buttons	This section identifies the buttons displayed above and below the SAP Connection Details that let you perform various actions.
Save	Saves a new SAP Connection record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new SAP Connection.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this SAP Connection.
Tabs	This section identifies the tabs across the top of the SAP Connection Details that provide access to additional information about the SAP Connection.
SAP Tasks tab	Lists all SAP tasks that use this SAP connection.
Versions tab	Stores copies of all previous versions of the current record. See Record Versioning.

SNMP Managers

```
    Overview

    Creating an SNMP Manager

        • SNMP Manager Details

    SNMP Manager Details Field Descriptions

• MIB File
        • MIB and SNMP Protocol

    MIB File Location
```

Overview

SNMP Managers are the network managers to which Universal Controller sends SNMP notifications.

SNMP Managers can receive SNMP notifications when:

- An Agent or OMS Server goes down or comes back up.
 A Cluster Node goes Offline or becomes Active.
- An SNMP Notification is associated with a task.

A Note

SNMP Notifications on Cluster Nodes cannot be exported; therefore, they cannot be imported. You must set up new SNMP Notifications for Cluster Nodes whenever an export / import has been run.

Creating an SNMP Manager

then want to create a new SNMP Manager, you must click the New button that displays above and below the	Menager Hune Menager Address Menager Fort Updated by Updated by If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5321.400 If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5321.400 If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5321.400 If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5321.400 If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5321.400 If the detection description are of 0 1234 10 selection description are of 0 2014.60.113 5324.200 If the detection description are of 0 1234 102 selection description are of 0 2014.60.113 5324.200 If the detection description are of 0 1234 102 selection description are of 0 2014.60.113 534.200 If the detection description are of 0 1234 102 selection description are of 0 2014.60.113 534.200 If the detection description are of 0 1234 selection description are of 0 102.800 </th <th>Manager Markes Manager Net Manager Net<th>State of the second data water of the se</th><th>SNMP Manager</th><th>rs 🗵</th><th></th><th></th><th></th><th></th></th>	Manager Markes Manager Net Manager Net <th>State of the second data water of the se</th> <th>SNMP Manager</th> <th>rs 🗵</th> <th></th> <th></th> <th></th> <th></th>	State of the second data water of the se	SNMP Manager	rs 🗵				
State Numager Advance Numager Hull Updated by	Water / State Name Water Advaca Water Advaca If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 23 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 23 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 23 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 23 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 23 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 55 24 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 15 55 4 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 15 55 4 400 If the state intermember of 1 1234 1f2 State Manager Advaca 2214 Adv 113 15 55 4 400 If the state intermember of 1 1234 1f2 Westor Intermember of 15 15 55 4 400 214 Adv113 15 55 4 400 If the state intermember of 1 1234 Westor Intermember of 15 15 55 4 400 <	State New State New Understate State State New State New State State State	Weager Manager Address Weager Address <	✓ 5 SNMP Ma	inagers	Custom Filter None		🐱 🦻 Filter 🔯 Go To 🔶 N	vew 🎅
Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Calipsi and the series of the Details for a new SNMP Manager, you can temporarily hide the list. Note If you were SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar hyport was SNMP Manager.	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. More Manager Details You wonth of the Streen, you can temporarily hide the list.	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list.	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. • More NNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and the new SNMP Manager. You must click the New button that displays above and below the Details.				Manager Port Updated By		-
Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Collapse of the Details fields on the screen, you can temporarily hide the list. Note If you wine SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar If you wine SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar	State decision of the second state of the	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Constraint of the Details fields on the screen, you can temporarily hide the list. Tote Manager Details for a new SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an erve SNMP Manager. Source and work of the New builton that displays above and below the start of the New builton that displays above and below the screen and scree	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Codeparation of the Details fields on the screen, you can temporarily hide the list. Oten Start Note: Oten S			1.2.3.4	162 stonebranch-user-	01 2014-06-13 15:35:21	1 -0400
Interference amprovage-04 12.24 102 attraction-sect-04 2014-06-13 15.35 2-0400 Image: Database 12.24 102 attraction-sect-04 2014-06-13 15.35 2-0400 Image: Database Image: Database Image: Database 2014-06-13 15.35 42-0400 Image: Database 2014-06-13 15.35 42-0400 Image: Database Image:	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar fyou were SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar fyou were SNMP Manager Details for an existing SNMP Manager, you must click the New button that displays above and below the	in undersach-ammywanager 04 1224 1224 102 atometerach-ammywanager 05 1224 102 atometerach-ammywanager 05 1224 102 atometerach-ammywanager 05 2014-06-13 15:35 42, 4400 Interview of the second of t	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. • Ote If we share the screet a new SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar the want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	stonebrar	nch-snmpmanager-02	1.2.3.4	162 stonebranch-user-	02 2014-06-13 15:35:30	0 -0400
Image: Determine spects 12.34 162 absolution spects 2014-00-13 153-42-440 Image: Determine spects Image: Determine spects Image: Determine spects Image: Determine spects Image: Determine spects Image: Determine spects Image: Prot: 102 Image: Determine spects Image: Determine spects Image: Determine spects Image: Determine spects Image: Prot: 102 Image: Determine spects Image: Determine sp	is senstranch-umpmanager-5 1234 162 stonethranch-user-05 2014-06-13 1535-42-4400 Image: Details Image: Details Image: Details Image: Details Image: Lineary Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details </td <td>Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Details to react a new SNMP Manager, you can temporarily hide the list. • Tote • Note • More • Note • Manager Details for a new SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar • for work of the or create a new SNMP Manager, you must click the New button that displays above and below the</td> <td>Image: Details 12.3 102 structurach-user-65 2014-04-13 15.54.2.400 Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Det</td> <td>stonebrar</td> <td>nch-snmpmanager-03</td> <td>1.2.3.4</td> <td>162 stonebranch-user-</td> <td>03 2014-06-13 15:35:34</td> <td>4 -0400</td>	Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Details to react a new SNMP Manager, you can temporarily hide the list. • Tote • Note • More • Note • Manager Details for a new SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar • for work of the or create a new SNMP Manager, you must click the New button that displays above and below the	Image: Details 12.3 102 structurach-user-65 2014-04-13 15.54.2.400 Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Details Image: Det	stonebrar	nch-snmpmanager-03	1.2.3.4	162 stonebranch-user-	03 2014-06-13 15:35:34	4 -0400
Stelle Manager Database in the set of the data of the set of the data of the set of the data of the	SNUP Manager Data Imager Manager Itame: Imanger Manager Itame:	State Manager Databaser Imager Databaser Version: Imager Manager Databaser Databaser Imager Manager Databaser Manager Adatases Imager Manager Manager Manager Adatases Imager Manager Manager Manager Adatases Imager Manager Manager Manager Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and fyou wive SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and fyou wive SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and fyou wive SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and fyou wive SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and fyou wive SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list of the New button that displays above and below the stateset and the stateset andet stateset and the stateset and the state	Store langue bala Version Ver	stonebrar	nch-snmpmanager-04	1.2.3.4	162 stonebranch-user-	04 2014-06-13 15:35:37	7 -0400
Stuff Manager Name: Version: 1 Manager Address: 1 1 Manager Address: 1 1 Base New 1 1 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. To display more of the Details fields on the screen, you can temporarily hide the list. If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Image: Nume: Image: Name: Manager Address: Image: Name: Manager Pott: 162 Image: Save New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Image: Save Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	StutP Manager Name: Imager Name: Manager Address: Imager Address: Manager Pott: 162 Imager Name: New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Perform in the instructure of fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Imager Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Image Variage Version: 1 Manager Name: Image Variage 1 Manager Port: 162 162 Image Port: 162 162 Image Variage Image Variage 162 Image Variage I		in an				
Stuff Manager Name: Version: 1 Manager Address: 1 1 Manager Address: 1 1 Base New 1 1 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface. • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. To display more of the Details fields on the screen, you can temporarily hide the list. If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Image: Nume: Image: Name: Manager Address: Image: Name: Manager Pott: 162 Image: Save New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Image: Save Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	SWP Manager Name: Version: Manager Name: Nersion: Manager Address: Imager Name: Manager Port: 192 Is save New	Image Variage Version: 1 Manager Name: Image Variage 1 Manager Port: 162 162 Image Port: 162 162 Image Variage Image Variage 162 Image Variage I						
Details Wersion: 1 Manager Address: 1 1 Manager Address: 152 152 Item of the second sec	Petals Version: 1 Manager Address: 1 1 Manager Address: 1 1 Save New 1 1 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. . . Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. . . Potault values for fields, if available, display automatically. . . . To display more of the Details fields on the screen, you can temporarily hide the list. . . Mote If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Petalls Version: 1 Manager Address : 1 1 Manager Address : 1 1 Manager Address : 1 1 Imager Port: 162 1 1 Imager Port: 1 1 1 1 Imager Port: 1 <t< td=""><td>Defails Version: Manager Name: New Manager Name: New Manager Port: 182 If awa New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Pequired fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Imager Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.</td><td>✓ SNMP Mana</td><td>ager Details</td><td></td><td></td><td>👸 Save</td><td>New</td></t<>	Defails Version: Manager Name: New Manager Name: New Manager Port: 182 If awa New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Pequired fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Imager Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	✓ SNMP Mana	ager Details			👸 Save	New
Manager Name: version: Manager Address: Imager Address: Manager Port: 162 It sow New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. It you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Name: version: Manager Address:	Manager Name:	 Manager Name: Version: Manager Address: Manager Port: 152 Save New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Perfault values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	SNMP Manag	ger 🔍 Versions				
Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, are then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Address: Manager Address: Manager Port: 182 Imager Sare New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Imager Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Address: Manager Address: 162 Manager Port: 162 Sore New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. It you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Address: Manager Address: Manager Port: 162 It select Details for a new SNMP Manager, using the field descriptions below as a guide. • Required fields display in boldface . • Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. It you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	Details -					
Inter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface . Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Port: 162 Issue New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Issue Required fields display in boldface . Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, are then want to create a new SNMP Manager, you must click the New button that displays above and below the	Inter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. I Required fields display in boldface . I Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Inter Note I you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Port: 162 Image: New Image: New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Performed fields display in boldface. Image: Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Image: Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	Manag	ger Name :		Version : 1		
Inter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface . Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Port: 162 Issue New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Issue Required fields display in boldface . Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, are then want to create a new SNMP Manager, you must click the New button that displays above and below the	Inter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. I Required fields display in boldface . I Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Inter Note I you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the	Manager Port: 162 Image: New Image: New Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Performed fields display in boldface. Image: Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Image: Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, and then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	Manager	r Address :				
 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 	Man	ager Port : 162				
 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Enter / select Details for a new SNMP Manager, using the field descriptions below as a guide. Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 						
 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 	00	Ne Ivew				
 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Required fields display in boldface. Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 					*.d.,	
 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 						
 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the 	 Default values for fields, if available, display automatically. To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, an then want to create a new SNMP Manager, you must click the New button that displays above and below the Details. 	Enter / sele	ect Details for a new SN	IMP Manager, using the field deso	criptions below as a gu	lide.	
To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	To display more of the Details fields on the screen, you can temporarily hide the list. Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.				criptions below as a gu	ide.	
Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	Note If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	• Re	equired fields display in	boldface.	riptions below as a gu	iae.	
If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	• Re • De	equired fields display in efault values for fields, i	boldface . f available, display automatically.		iae.	
If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the	If you view SNMP Manager Details for an existing SNMP Manager by clicking an SNMP Manager in the list, ar then want to create a new SNMP Manager, you must click the New button that displays above and below the Details.	• Re • De	equired fields display in efault values for fields, i	boldface . f available, display automatically.		ide.	
				• Re • De	equired fields display in efault values for fields, i	boldface . f available, display automatically.		ide.	

SNMP Manager Details

The following SNMP Manager Details is for an existing SNMP Manager. See the field descriptions, below, for a description of all fields that display in the SNMP Manager Details.

SNMP Manager Details: s	stonebranch-snmpmanager-01				_ D X
		🔚 Update	🇊 Delete	S Refresh	X Close
SNMP Manager 🛛 🔍 V	rersions				
Details					
Manager Name :	stonebranch-snmpmanager-01 Version : 1				
Manager Address :	1234				
Manager Port :	162				
Update	🗊 Delete 📄 🔄 Refresh 🛛 🗱 Close				

SNMP Manager Details Field Descriptions

The following table describes the fields, buttons, and tabs that display in the SNMP Manager Details.

Field Name	Description
Details	This section contains detailed information about the SNMP Manager.
Manager Name	Name used within the Controller to identify this resource. Up to 40 alphanumerics. It is the responsibility of the user to develop a workable naming scheme for resources.
Version	System-supplied; version number of the current record, which is incremented by the Controller every time a user updates a record. Click the Versions tab to view previous versions. For details, see Record Versioning.
Manager Address	Name or IP address of the SNMP Manager.
Manager Port	Port used by the SNMP Manager.
Buttons	This section identifies the buttons displayed above and below the SNMP Manager Details that let you perform various actions.
Save	Saves a new SNMP Manager record in the Controller database.
Update	Saves updates to the record.
New	Displays empty (except for default values) Details for creating a new SNMP Manager.
Delete	Deletes the current record.
Refresh	Refreshes any dynamic data displayed in the Details.
Close	For pop-up view only; closes the pop-up view of this SNMP Manager.
Tabs	This section identifies the tabs across the top of the SNMP Manager Details that provide access to additional information about the SNMP Manager.
Versions tab	Stores copies of all previous versions of the current record. See Record Versioning.

MIB File

A MIB file contains the translation of the SNMP notifications sent to the SNMP Manager by the Controller.

A sample MIB file, OPSWISE.MIB.txt, is shipped with all Universal Agent for Windows and UNIX packages.

MIB and SNMP Protocol

SNMP protocol is a simple UDP package containing a set of dot-separated characters defined as ObjectID.

You can use the MIB file to set up the corresponding options Tree; the numbers will tell the server which line to go down. You then can look up inside the server for those results or, more importantly, define alerts on the decision option of the tree-structure that you defined with the MIN file.

If you have a more graphical server, you also may have a GUI showing the different parts of your trees in diagrams or other types of reporting.

SNMP protocol is, in effect, an external Alarm/(simple up to rather complex) Reporting System that searches for the Return Code (Success or Failure) of a task, rather than the actual output of the task. It could tell the Operator, for example: the Return Code is not as expected, add paper to the printer, the machine is low on disk space, or the server just booted up. These messages can be as descriptive as defined and, of course, will depend on the logging capability of the corresponding manager, which in our case is the Controller. It can be thought of as a centralized Information system, where quite a lot of tools and hardware can use for status exchange.

MIB File Location

The MIB file for both UNIX and Windows are included in the samp directory (UNIX) and samples directory (Windows) for Universal Automation Center Agent (UAG):

UNIX	/opt/universal/uagsrv/samp	
Windows	\Program Files\Universal\UAGSrv\samples	