

Universal Connector 4.1.0 Quick Reference

Usage usap COMMAND HOST USER [ADDITIONAL OPTIONS...]

Format

There is a long form and, for most commands and options, a short form available for specifying each command and option on the command line. The long form is not case-sensitive; the short form is case-sensitive.

Commands and options must be prefixed with a dash (-) character. If an option value is specified, the option and its value must be separated by at least one space.

COMMANDS{ ABORT | DISPLAY | GENERATE | MODIFY | PURGE | RAISE EVENT | RUN |
START | SUBMIT | SYNTAX | WAIT | BDCWAIT | MASS ACTIVITY WAIT }

ABORT -abort -jobname -jobid

Long Form	Short Form	Description
-abort	-A	Abort a running job on an SAP system.
-jobname jobname	-j jobname	Name of the SAP job to abort.
-jobid jobid	-b <i>jobid</i>	ID of the SAP job to abort.

DISPLAY { COMMANDS | INTERCEPT_TABLE | JOBDEF | JOBLOG | OUTPUT_DEVICES | PRINT_FORMATS | QSTATE | REPORTS | SELECT | SPOOLLIST | STATUS | SYSLOG | VARIANT | VARIANTS }

COMMANDS -display commands [-cmd] [-opsys]

Long Form	Short Form	Description
-display commands	-D commands	Displays a list of SAP external commands that match the specified criteria.
-cmd external_command_mask	n/a	Complete command name or a mask used to select SAP external commands that match the mask.
-opsys operating_system	n/a	Name of the operating system for which external commands are searched.

INTERCEPTED_JOBS -display intercepted_jobs [-dspclient]

Long Form	Short Form	Description
-display intercepted_jobs	-D intercepted_jobs	Displays intercepted jobs for the connected SAP system.
-dspclient client	n/a	Specific SAP client whose intercepted jobs will be reported.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887

support@stonebranch.com

copyright ©2010 Stonebranch, Inc.



INTERCEPT_TABLE -display intercept_table

Long Form	Short Form	Description
-display intercept_table	-D intercept_table	Displays the contents of the job intercept criteria table for the connected SAP system.

JOBDEF -display jobdef -jobname -jobid

Long Form	Short Form	Description
-display jobdef	-D jobdef	Display the job definition of a SAP job.
-jobname jobname	-j jobname	Name of the SAP job.
-jobid jobid	-b <i>jobid</i>	ID of the SAP job.

JOBLOG -display joblog -jobname -jobid

Long Form	Short Form	Description
-display joblog	-D joblog	Display the joblog of a SAP job.
-jobname jobname	-j jobname	Name of the SAP job.
-jobid jobid	-b jobid	ID of the SAP job.
-max_log_size size	n/a	Maximum size for job logs.

OUTPUT_DEVICES -display output_devices { -short_name | -long_name }

Long Form	Short Form	Description
-display output_devices	-D output_devices	Displays a list of SAP output devices that match the specified criteria.
-short_name technical_device_name_mask	n/a	Complete device name or a mask used to select SAP output devices that match the mask.
-long_name long_device_name_mask	n/a	Complete device name or a mask used to select SAP output devices that match the mask.

PRINT_FORMATS -display print_formats [-printer] [-layout]

Long Form	Short Form	Description
-display print_formats	-D print_formats	Displays a list of print formats that are available for the specified printer.
-printer printer_name	n/a	Name of a printer for which the print formats will be retrieved.
-layout <i>layout</i>	n/a	Complete layout name or a mask used to select printer layouts that match the mask.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887

copyright ©2010 Stonebranch, Inc.



QSTATE -display qstate -qid

Long Form	Short Form	Description
-display qstate	-D qstate	 Display the queue state of a batch input session. The state of the queue is indicated by the following exit codes: 10 = 'C" to be created 12 = ' ' unprocessed 14 = 'F' finished 16 = 'E' error 18 = undefined
-qid QID	-q QID	Queue ID associated with the batch input session.

REPORTS -display reports [-abapname] [-count]

Long Form	Short Form	Description
-display reports	-D reports	Displays a list of ABAP reports that match the specified criteria.
-abapname abapmask	-a abapmask	Complete ABAP name or a mask used to select SAP ABAP reports that match the mask.
-count max_hit_count	n/a	Maximum number of ABAP reports to be returned.

SELECT -display select -jobname [-jobid] [-output] [-selusername] [-fromdate] [-todate] [-fromtime] [-totime] [-nodate] [-withpred] [-released] [-scheduled] [-ready] [-running] [-finished] [-aborted]

Long Form	Short Form	Description
-display select	-D select	Display a list of jobs that match the job selection criteria.
-jobname jobname_pattern	-j jobname_pattern	Complete or partial jobname search criteria using wildcards.
-jobid jobid	-b jobid	Complete or partial jobid search criteria using wildcards.
-output format_string	-o format_string	Comma-delimited list of fields to display. The fields correspond with the fields in the BAPIXMJOB structure defined in the SAP system.
-selusername	n/a	Complete or partial username search criteria using wildcards.
-fromdate date	n/a	Earliest planned start date to include in the selection. Format is YYYY/MM/DD.
-todate date	n/a	Latest planned start date to include in the selection. Format is YYYY/MM/DD.
-fromtime <i>time</i>	n/a	Earliest planned start time to include in the selection. Format is HH:MM:SS.
-totime <i>time</i>	n/a	Latest planned start time to include in the selection. Format is HH:MM:SS.
-nodate option	n/a	Include jobs with no start date in selection criteria if <opt> is YES.</opt>
-withpred option	n/a	Include jobs with predecessors in selection criteria if <opt> is YES.</opt>

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



Long Form	Short Form	Description
-released option	n/a	Include jobs with status released in selection criteria if <opt> is YES.</opt>
-scheduled option	n/a	Include jobs with status scheduled in selection criteria if <opt> is YES.</opt>
-ready option	n/a	Include jobs with status ready in selection criteria if <opt> is YES.</opt>
-running option	n/a	Include jobs with status running in selection criteria if <opt> is YES.</opt>
-finished option	n/a	Include jobs with status finished in selection criteria if <opt> is YES.</opt>
-aborted option	n/a	Include jobs with status aborted in selection criteria if <opt> is YES.</opt>

SPOOLLIST -display spoollist -jobname -jobid -stepnum

Long Form	Short Form	Description
-display spoollist	-D spoollist	Display the spoollists of a SAP job.
-jobname jobname	-j jobname	Name of the SAP job.
-jobid jobid	-b jobid	ID of the SAP job.
-stepnum stepnumber	-n stepnumber	Step number of the SAP job step.
-max_spool_size size	n/a	Maximum size for spool lists.

STATUS -display status -jobname -jobid

Long Form	Short Form	Description
-display status	-D status	Display the status of a SAP job.
-jobname jobname	-j jobname	Name of the SAP job.
-jobid jobid	-b <i>jobid</i>	ID of the SAP job.

SYSLOG	-display syslog -fromdate -todate [-fromtime] [-totime] [-pagelimit] [-targetserver]

Long Form	Short Form	Description
-display syslog	-D syslog	Display a portion of the SAP system log that matches the criteria specified.
-fromdate date	n/a	Earliest date to include in the selection. Format is YYYY/MM/DD.
-todate date	n/a	Latest date to include in the selection. Format is YYYY/MM/DD.
-fromtime time	n/a	Earliest time to include in the selection. Format is HH:MM:SS.
-totime <i>time</i>	n/a	Latest time to include in the selection. Format is HH:MM:SS.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



Long Form	Short Form	Description
-pagelimit <i>limit</i>	n/a	Maximum number of pages that can be returned in the syslog report. Valid values are 1-999. [Default is 999.]
-targetserver server	-r	Name of server to retrieve syslog from. [Default is current server.]

VARIANT -display variant -variant -variant_language -abapname

Long Form	Short Form	Description
-display variant	-D variant	Display the contents of an SAP variant.
-variant variant	-V variant	SAP variant name.
-variant_language language	n/a	Language in which to return the variant description.
-abapname abapname	-a abapname	SAP ABAP program name.

VARIANTS -display variants -abapname [-varselopt]

Long Form	Short Form	Description
-display variants	-D variants	Display the variants of a SAP ABAP program.
-abapname abapname	-a abapname	SAP ABAP program name.
-varselopt option	n/a	Variant selection option:
		• A – Variants that are available for batch and dialog.
		 B – Batch only variants.

GENERATE {JOBDEF | VARDEF}

JOBDEF -generate jobdef -j -b [-xmiaudit]

Long Form	Short Form	Description
-generate jobdef	n/a	Generates a USAP job definition file based on the specified SAP job definition. The generated job definition is written to standard output.
-jobname <i>jobname</i>	-j jobname	Name of the SAP model job.
-jobid jobid	-b <i>jobid</i>	ID of the SAP model job.

VARDEF -generate vardef -variant -abapname [-xmiaudit]

Long Form	Short Form	Description
-generate vardef	n/a	Generates a USAP variant definition file based on the specified variant. The generated variant definition is written to standard output.
-variant variant_name	-V variant_name	SAP variant name.
-abapname abapname	-a abapname	SAP ABAP program name.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



MODIFY

-mod {filename [-jobid] } [START] [WAIT] [PURGE]

Long Form	Short Form	Description
-mod	-M	Modify job or variant in a SAP system.
filename	n/a	USAP definition file containing the modifications of an SAP job or SAP variant.
-jobid <jobid></jobid>	-b <jobid></jobid>	Job ID of an existing SAP job to modify.

PURGE -purge -jobname -jobid

Long Form	Short Form	Description
-purge	-P	Purge a job on the SAP system.
-jobname jobname	-j jobname	Name of the SAP job to purge.
-jobid jobid	-b <i>jobid</i>	ID of the SAP job to purge.

RAISE EVENT -raise_bp_event -event_id [-event_parm]

Long Form	Short Form	Description
-raise_bp_event	-E	Raises the specified SAP background processing event.
-event_id <i>id</i>	n/a	Name of the event.
-event_parm parm	n/a	Optional parameter value for the event.

RUN -run { *job_definition_file* | -jobname -jobid} [-I mmediate] [-targetserver] [-target_jobname] [-target_variant] [-poll]

Long Form	Short Form	Description
-run	-R	Define a job, start the job, wait for the job to complete, write the joblog to stderr, write the spoollist to stdout, and delete the job from the SAP system.
job_definition_file	job_definition_file	Job definition file containing the specification of a SAP job.
-jobname jobname	-j jobname	Existing SAP job name to use as a model for a new SAP job.
-jobid <i>jobid</i>	-b jobid	Job ID of an existing SAP job to use as a model.
-immediate	-i	Attempt to start the job immediately. If the job cannot be started immediately, an error is returned and the job is not waiting to run. [Default is to start the job as soon as possible.]
-targetserver server	-r server	Target server for the job to run on. (Not available on SAP 3.1 and 4.0 systems.)
-target_jobname <i>jobname</i>	n/a	Name to give newly created job. Default is the original jobname. (Only applies when running a pre-existing SAP job.)
-target_variant job step,variant name;	n/a	One or more replacement variants for ABAP program job steps in an SAP job.
-poll seconds	-p seconds	Seconds to wait to check the SAP job status. [Default is 10.]

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887

usap-quickref-4100



START -start -jobname -jobid [-immediate] [-targetserver] [WAIT] [PURGE]

Long Form	Short Form	Description
-start	-S	Start a defined job on the SAP system.
-jobname <i>jobname</i>	-j jobname	Name of the SAP job to start.
-jobid jobid	-b jobid	ID of the SAP job to start.
-immediate	-i	Attempt to start the job immediately. If the job cannot be started immediately, an error is returned and the job is not waiting to run. [Default is to start the job as soon as possible.]
-targetserver server	-r server	Target server for the job to run on. (Not available on SAP 3.1 and 4.0 systems.)

SUBMIT -sub {definition_file | -jobname -jobid} [-target_jobname] [-target_variant] [START] [WAIT] [PURGE]

Long Form	Short Form	Description
-sub	-U	Define a new job or variant to the SAP system.
definition_file	n/a	USAP definition file containing the specification of an SAP job or SAP variant.
-jobname jobname	-j jobname	Existing SAP job name to use as a model for a new SAP job.
-jobid jobid	-b <i>jobid</i>	Existing SAP Job ID to use as a model for a new SAP job
-target_jobname jobname	n/a	Name to give newly created job. Default is original jobname. (Only applies when running a pre-existing SAP job.)
-target_variant job step,variant name; job step,variant name;	n/a	One or more replacement variants for ABAP program job steps in an SAP job.
-max_log_size <i>size</i>	n/a	Maximum size for job logs.
-max_spool_size size	n/a	Maximum size for spool lists.

SYNTAX -syntax filename

Long Form	Short Form	Description
-syntax	-X	Checks the syntax of a Universal Connector job definition file.
filename	n/a	Job definition file to check for valid syntax.



WAIT -wait [-jobname -jobid] [-poll] [-spoollist] [-joblog] [-applog] [-printapprc] [-useapprc] [-transtab] [-purge] [-syslog [-syslogpre] [-syslogpost]] [-max_log_size] [-max_spool_size] [EXITCODES]

Long Form	Short Form	Description
-wait	-W	 Wait for the job to complete. Default final status codes are: active_exit_code [config default = 10] ready_exit_code [config default = 12] scheduled_exit_code [config default = 14] released_exit_code [config default = 16] terminated_exit_code [config default = 8] finished_exit_code [config default = 0] UNKNOWN = 22 NOTE: If -useapprc is YES, and the SAP program sets an application return code, USAP will compare this with the other exit code mapping values. The highest value will be returned as the exit code.
-jobname <i>jobname</i>	-j jobname	Name of the SAP job to wait for.
-jobid <i>jobid</i>	-b jobid	ID of the SAP job to wait for.
-poll seconds	-p seconds	Seconds to wait to check the SAP job status. Default is 10.
-spoollist <opt></opt>	-s <opt></opt>	Specification for whether or not to write the spoollist to standard output. Valid values are YES and NO. [Default is YES.]
-joblog option	-g option	Specification for whether or not to write the joblog to standard error. Valid values are YES and NO. [Default is YES.]
-applog option	n/a	Specification for whether or not the job's application log is returned (<i>option</i> can be YES or NO. Default is YES).
-printapprc option	n/a	Specification for whether or not the job's application return codes are returned (<i>option</i> can be YES or NO. Default is YES).
-useapprc option	n/a	Specification for whether or not the job's application return codes are used to determine the exit code of the Universal Connector job (<i>option</i> can be YES or NO. Default is NO).
-transtab translation_table	-t	Translation table file to use for formatting spoollists.
-purge	-P	Delete the job from the SAP system upon completion.
-syslog option	-y option	Write the syslog to standard error upon unsuccessful completion of job if <opt> is YES.</opt>
		[Default is YES.]
-syslogpre seconds	n/a	Number of seconds prior to job release that will be included in the syslog.
		[Default is 0.]
-syslogpost seconds	n/a	Number of seconds past the job end time that will be included in the syslog. This will cause USAP to sleep for the specified number of seconds after the job ends before retrieving the syslog.
-max_log_size <i>size</i>	n/a	Maximum size for job logs.
-max_spool_size size	n/a	Maximum size for spool lists.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



MASS ACTIVITY WAIT

-mawait [-jobname -jobid] [-poll] [-job_stat_check_interval] [-joblog] [-applog] [-printapprc] [-useapprc] [-transtab] [-purge] [-syslog [-syslogpre] [-syslogpost]] [EXITCODES]

Long Form	Short Form	Description
-mawait	n/a	Wait for the mass activity to complete. Default final status codes are:
		 active_exit_code [config default = 10]
		 ready_exit_code [config default = 12]
		 scheduled_exit_code [config default = 14]
		 released_exit_code [config default = 16]
		 terminated_exit_code [config default = 8]
		 finished_exit_code [config default = 0]
		UNKNOWN = 22
		NOTE: If –useapprc is YES, and the SAP program sets an application return code, USAP will compare this with the other exit code mapping values. The highest value will be returned as the exit code.
-jobname <i>jobname</i>	-j jobname	Name of the SAP job to wait for.
-jobid <i>jobid</i>	-b jobid	ID of the SAP job to wait for.
-poll seconds	-p seconds	Seconds to wait to check the SAP job status. Default is 10.
-job_stat_check_interval	n/a	Seconds that can elapse, without a change in job status, before a call is made to synchronize the actual job status with the SAP stored status. Default is 600.
-joblog option	-g option	Specification for whether or not to write the joblog to standard error.
		Valid values are YES and NO. [Default is YES.]
-applog option	n/a	Specification for whether or not the job's application log is returned (<i>option</i> can be YES or NO. Default is YES).
-printapprc option	n/a	Specification for whether or not the job's application return codes are returned (<i>option</i> can be YES or NO. Default is YES).
-useapprc option	n/a	Specification for whether or not the job's application return codes are used to determine the exit code of the Universal Connector job (<i>option</i> can be YES or NO. Default is NO).
-transtab translation_table	-t	Translation table file to use for formatting spoollists.
-purge	-P	Delete the job from the SAP system upon completion.
-syslog option	-y option	Write the syslog to standard error upon unsuccessful completion of job if <i>option</i> is YES.
		[Default is YES.]
-syslogpre seconds	n/a	Number of seconds prior to job release that will be included in the syslog.
		[Default is 0.]
-syslogpost seconds	n/a	Number of seconds past the job end time that will be included in the syslog. This will cause USAP to sleep for the specified number of seconds after the job ends before retrieving the syslog.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



BDCWAIT -bdcwait [-jobname -jobid] [-poll] [-job_stat_check_interval] [-joblog] [-applog] [-printapprc] [-useapprc] [-transtab] [-purge] [-purge_bdc_map] [-syslog [-syslogpre] [-syslogpost]] [-bdcjobnameptrn] [-bdcjobidptrn] [-bdcqidptrn] [EXITCODES]

Long Form	Short Form	Description
-bdcwait	n/a	 Wait for the batch input session to complete processing. Default final status codes are: qtobecreated_exit_code [config default = 14] qunprocessed_exit_code [config default = 12] qinbackground_exit_code [config default = 10] qerror_exit_code [config default = 16] terminated_exit_code [config default = 8] qfinished_exit_code [config default = 0] UNKNOWN = 22 NOTE: If -useapprc is YES, and the SAP program sets an application return code, USAP will compare this with the other exit code mapping values. The highest value will be returned as the exit code.
-jobname <i>jobname</i>	-j jobname	Name of the SAP job to wait for.
-jobid <i>jobid</i>	-b jobid	ID of the SAP job to wait for.
-poll seconds	-p seconds	Seconds to wait to check the SAP job status. Default is 10.
-job_stat_check_interval	n/a	Seconds that can elapse, without a change in job status, before a call is made to synchronize the actual job status with the SAP stored status. Default is 600.
-joblog option	-g option	Specification for whether or not to write the joblog to standard error (<i>option</i> can be YES or NO. Default is YES].
-applog option	n/a	Specification for whether or not the job's application log is returned (<i>option</i> can be YES or NO. Default is YES).
-printapprc option	n/a	Specification for whether or not the job's application return codes are returned (<i>option</i> can be YES or NO. Default is YES).
-useapprc option	n/a	Specification for whether or not the job's application return codes are used to determine the exit code of the Universal Connector job (<i>option</i> can be YES or NO. Default is NO).
-transtab translation_table	-t	Translation table file to use for formatting spoollists.
-purge	-P	Delete the job from the SAP system upon completion.
-purge_bdc_map option	n/a	Specification for whether or not USAP will delete the batch input session queues that have been processed successfully (<i>option</i> can be YES or NO).
-syslog option	-y option	Write the syslog to standard error upon unsuccessful completion of job if <i>option</i> is YES. [Default is YES.]
-syslogpre seconds	n/a	Number of seconds prior to job release that will be included in the syslog. [Default is 0.]
-syslogpost seconds	n/a	Number of seconds past the job end time that will be included in the syslog. This will cause USAP to sleep for the specified number of seconds after the job ends before retrieving the syslog.
-bdcjobnameptrn pattern	n/a	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



Long Form	Short Form	Description
-bdcjobidptrn pattern	n/a	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
-bdcqidptrn pattern	n/a	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.

OPTIONS { HOST USER [CFT] [COMMAND FILE] [EXIT CODES] [INFORMATIONAL] [LOCAL] [MESSAGE] [RFC] }

HOST {-dest |-ashost -sysnr} -client -max_xbp -saplang -xmiaudit

Long Form	Short Form	Description
-dest destination	-e destination	Destination name in the saprfc.ini.
-ashost hostname	n/a	Host name of an SAP application server.
-sysnr number	n/a	SAP system number of an SAP application server.
-client client	-c client	SAP client number.
-max_xbp version	n/a	Maximum version of the SAP XBP interface that will be used during USAP execution.
-saplang <i>language</i>	n/a	SAP logon language used for the USAP session
-xmiaudit <i>level</i>	n/a	Sets the XMI audit level to be used for the execution of the command. The amount of information logged in the XMI log increases with higher audit level values.
		Valid values are 0, 1, 2, and 3. Default is 0.

USER -userid -pwd

Long Form	Short Form	Description
-userid userid	-u <i>userid</i>	Remote SAP user ID with which the command runs.
-pwd password	-w password	Remote SAP user ID's password.

CFT [-cmdid] [-restart] [-autorestartok] [-cft_abap] [-cft_cmd_prefix] [-cft_secure_cft] [-cft_target_host]

Long Form	Short Form	Description
-cmdid <i>id</i>	-C	Command identifier: associates an SAP job with the Universal Connector command that started it. This value facilitates fault tolerance/restartability.
-restart option	n/a	Identifies whether or not this instance of the USAP job is a restart attempt. <opt> can be NO, YES or AUTO.</opt>
		If YES or AUTO, -cmdid is required.
-autorestartok option	n/a	Controls whether or not 'AUTO' is allowed for the -restart option. <opt> can be YES or NO. Default is NO.</opt>
-cft_cmd_prefix <i>prefix</i>	n/a	Prefix command required for the operating system of the target host. This option is used with (and only applies to) the

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887

usap-quickref-4100



Long Form	Short Form	Description
		command ID option.
-cft_target_host host	n/a	Target host to use for the command ID job step when the command ID option is used.
-cft_abap program	n/a	ABAP program to use for the command ID job step
-cft_secure_cft option	n/a	Mode of client fault tolerance to be used for the command invocation.

COMMAND FILE

[-file | -encryptedfile [-key]]

Long Form	Short Form	Description
-file file	-f	Name of a plain text command options file.
-encryptedfile file	-x	Name of an encrypted command options file.
-key <i>key</i>	-К	Key used to encrypt the encrypted command options file.

EXIT CODES [-activeec] [-readyec] [-scheduledec] [-releasedec] [-terminatedec] [-finishedec]

Long Form	Short Form	Description
-activeec exitcode	n/a	USAP exit code for the job active status.
-readyec exitcode	n/a	USAP exit code for the job ready status.
-scheduledec exitcode	n/a	USAP exit code for the job scheduled status.
-releasedec exitcode	n/a	USAP exit code for the job released status.
-terminatedec exitcode	n/a	USAP exit code for the job terminated status.
-finishedec exitcode	n/a	USAP exit code for the job finished status.

INFORMATIONAL { -help | -version }

Long Form	Short Form	Description
-help	-h	Writes help text.
-version	-V	Writes program version and exit.

LOCAL [-system_id] [-bif_directory] [-plf_directory]

Long Form	Short Form	Description
-system_id id ^z	n/a	Local Universal Broker with which USAP must register.
-bif_directory directory ^u	n/a	Broker Interface File (BIF) directory where the Universal Broker interface file is located
-plf_directory directory "	n/a	Program Lock File (PLF) directory where the program lock files are located.
^z Valid only with z/OS. ^u Valid only with UNIX.		



MESSAGE [-level] [-lang] [-trace_file_lines] [-trace_table]

Long Form	Short Form	Description
-level level	-l <level></level>	Message level: trace, audit, info, warn, or error.
-lang <i>language</i>	-L <lang></lang>	Message and text language.
-trace_file_lines lines	n/a	Maximum number of lines to write to the trace table.
-trace_table size, condition	n/a	Trace table size, and under what condition it is written to a file.

RFC

[-rfc_listen_interval] [-rfc_logon_retry_count] [-rfc_logon_retry_interval] [-rfc_retry_count] [-rfc_retry_interval] [-rfc_timeout] [-rfc_trace_dir]

Long Form	Short Form	Description
-rfc_listen_interval interval	n/a	Number of seconds that will elapse between RFC listen calls. These are polling calls that are performed repeatedly to determine if an RFC event is available.
-rfc_logon_retry_count count	n/a	Number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.
-rfc_logon_retry_interval interval	n/a	Number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.
-rfc_retry_count count	n/a	Number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.
-rfc_retry_interval interval	n/a	Number of seconds that will elapse between a failed RFC call and the retry of that RFC call.
-rfc_timeout <i>interval</i>	n/a	Time constraint on all RFC functions, with the exception of blocking connection calls: the number of seconds that can elapse before USAP considers an RFC call to have timed out.
-rfc_trace_dir path	n/a	Directory where RFC trace files will be written. The default value is /tmp.



ENVIRONMENT VARIABLES

The following table contains the environment variables that Universal Connector uses. The first column is their equivalent command line option. Command line options override environment variable settings.

Command Line Option	Environment Variable
-userid	USAPUSERID
-pwd	USAPPWD
-level	USAPDLEVEL
-lang	USAPDLANG
-sub	USAPSUBMIT
-mod	USAPMODIFY
-run	USAPRUN
-start	USAPSTART
-abort	USAPABORT
-purge	USAPPURGE
-wait	USAPWAIT
-syntax	USAPSYNTAX
-dest	USAPDEST
-client	USAPCLIENT
-targetserver	USAPTARGETSRV
-jobname	USAPJOBNAME
-jobid	USAPJOBID
-stepnum	USAPSTEPNUM
-abapname	USAPABAPNAME
-varselopt	USAPVARSELOPT
-poll	USAPPOLL
-transtab	USAPTRANSTAB
-spoollist	USAPSPOOLLIST
-joblog	USAPJOBLOG
-output	USAPOUTPUT
-selusername	USAPSELUSERNAME
-fromdate	USAPFROMDATE
-todate	USAPTODATE
-fromtime	USAPFROMTIME
-totime	USAPTOTIME
-nodate	USAPNODATE
-withpred	USAPWITHPRED
-released	USAPRELEASED
-scheduled	USAPSCHEDULED

Customer Support: North America (+1) 877 366-7887 ext. 6 [toll-free] • Europe +49 (0) 700 5566 7887



Command Line Option	Environment Variable
-ready	USAPREADY
-running	USAPRUNNING
-finished	USAPFINISHED
-aborted	USAPABORTED
-xmiaudit	USAPXMIAUDIT
-activeec	USAPACTIVEEXITCODE
-readyec	USAPREADYEXITCODE
-scheduledec	USAPSCHEDULEDEXITCODE
-releasedec	USAPRELEASEDEXITCODE
-terminatedec	USAPTERMINATEDEXITCODE
-finishedec	USAPFINISHEDEXITCODE
-rfc_timeout	USAP_RFC_TIMEOUT
-rfc_logon_timeout	USAP_RFC_LOGON_TIMEOUT
-rfc_logon_retry_interval	USAP_RFC_LOGON_RETRY_INTERVAL
-rfc_logon_retry_count	USAP_RFC_LOGON_RETRY_COUNT
-rfc_listen_interval	USAP_RFC_LISTEN_INTERVAL
-rfc_retry_interval	USAP_RFC_RETRY_INTERVAL
-rfc_retry_count	USAP_RFC_RETRY_COUNT

Example

The following example:

- 1. Defines a SAP job based on the job definition in file sapjob1.usp.
- 2. Starts the job.
- 3. Waits for its completion.

The job's joblog is written to standard error and the job's spoollists are written to standard output.

usap -userid MYUSER -pwd MYPASS -dest BIN_HS0011 -client 900 -sub sapjob1.usp -start -wait