



**stonebranch**

Universal Connector for PeopleSoft 6.8.x

Reference Guide

© 2020 by Stonebranch, Inc. All Rights Reserved.

1. Universal Connector for PeopleSoft 6.8.x Reference Guide	4
1.1 PeopleSoft Web Services	7
1.2 Universal Connector for PeopleSoft for UNIX	8
1.3 Universal Connector for PeopleSoft for Windows	9
1.4 Universal Connector for PeopleSoft Commands	12
1.4.1 CANCEL PROCESS - UPPS Command	14
1.4.2 DELETE PROCESS - UPPS Command	15
1.4.3 DISPLAY OUTPUT FORMATS - UPPS Command	16
1.4.4 DISPLAY OUTPUT TYPES - UPPS Command	18
1.4.5 DISPLAY PRCS GET REPORT - UPPS Command	21
1.4.6 DISPLAY PRCS GET REQUEST - UPPS Command	22
1.4.7 DISPLAY PRCS GET SERVER CONSTRAINTS - UPPS Command	24
1.4.8 DISPLAY PRCS PARAMS - UPPS Command	26
1.4.9 DISPLAY PRCS PRINT JOB HTML REPORT - UPPS Command	28
1.4.10 DISPLAY PRCS PRINT JOB REQUEST REPORT - UPPS Command	30
1.4.11 DISPLAY PRCS PRINT SCHED HTML REPORT - UPPS Command	32
1.4.12 DISPLAY PRCS PROMPT - UPPS Command	34
1.4.13 DISPLAY PROCESS NAMES - UPPS Command	36
1.4.14 DISPLAY REQUESTS - UPPS Command	38
1.4.15 HOLD PROCESS - UPPS Command	40
1.4.16 START JOBSET - UPPS Command	41
1.4.17 SUBMIT PROCESS - UPPS Command	45
1.4.18 WAIT for PROCESS - UPPS Command	48
1.5 Universal Connector for PeopleSoft Exit Codes	50
1.6 Universal Connector for PeopleSoft Configuration Options for Program Execution	51
1.6.1 HOST Options - Universal Connector for PeopleSoft	52
1.6.2 USER Options - Universal Connector for PeopleSoft	53
1.6.3 COMMAND FILE Options - Universal Connector for PeopleSoft	54
1.6.4 INFORMATIONAL Options - Universal Connector for PeopleSoft	56
1.6.5 INSTALLATION Options - Universal Connector for PeopleSoft	57
1.6.6 LOCAL Options - Universal Connector for PeopleSoft	58
1.6.7 MESSAGE Options - Universal Connector for PeopleSoft	59
1.6.8 SSL Options - Universal Connector for PeopleSoft	60
1.7 Universal Connector for PeopleSoft Configuration Options	61
1.7.1 BIF_DIRECTORY - UPPS configuration option	65
1.7.2 CA_CERTIFICATES - UPPS configuration option	66
1.7.3 CERTIFICATE - UPPS configuration option	67
1.7.4 CERTIFICATE_EXPIRATION_NOTICE - UPPS configuration option	68
1.7.5 CNT_FILTER - UPPS configuration option	69
1.7.6 CONTENT_ID - UPPS configuration option	70
1.7.7 DEFINITION_FILE_FORMAT - UPPS configuration option	71
1.7.8 DISTRIBUTION_STATUS - UPPS configuration option	72
1.7.9 ENCRYPT_FILE - UPPS configuration option	73
1.7.10 ENCRYPTION_KEY - UPPS configuration option	74
1.7.11 ENDPOINT - UPPS configuration option	75
1.7.12 FILE_NAME - UPPS configuration option	76
1.7.13 FILTER_UNIT - UPPS configuration option	77
1.7.14 FILTER_VALUE - UPPS configuration option	78
1.7.15 FROM_DATE - UPPS configuration option	79
1.7.16 HELP - UPPS configuration option	80
1.7.17 HOST - UPPS configuration option	81
1.7.18 INSTALLATION_DIRECTORY - UPPS configuration option	82
1.7.19 ITEM_INSTANCE - UPPS configuration option	83
1.7.20 JOB_NAME - UPPS configuration option	84
1.7.21 LANGUAGE_CODE - UPPS configuration option	85
1.7.22 MAIN_JOB_NAME - UPPS configuration option	86
1.7.23 MAIN_SCHED_NAME - UPPS configuration option	87
1.7.24 MESSAGE_LANGUAGE - UPPS configuration option	88
1.7.25 MESSAGE_LEVEL - UPPS configuration option	89
1.7.26 OPERATOR_ID - UPPS configuration option	90
1.7.27 OUTPUT_DESTINATION_FORMAT - UPPS configuration option	91
1.7.28 OUTPUT_DESTINATION_STRING - UPPS configuration option	92
1.7.29 OUTPUT_DESTINATION_TYPE - UPPS configuration option	93
1.7.30 OUTPUT_FORMAT - UPPS configuration option	94
1.7.31 PASSWORD - UPPS configuration option	95
1.7.32 PLF_DIRECTORY - UPPS configuration option	96
1.7.33 POLL - UPPS configuration option	97
1.7.34 PORT - UPPS configuration option	98
1.7.35 PRINT_APPLICATION_MESSAGE - UPPS configuration option	99
1.7.36 PRINT_DISTRIBUTION_LIST - UPPS configuration option	100
1.7.37 PRINT_JOB_TREE - UPPS configuration option	101
1.7.38 PRINT_MESSAGE_LIST - UPPS configuration option	102
1.7.39 PRINT_NOTIFY_LIST - UPPS configuration option	103
1.7.40 PRINT_PARAMETER_LIST - UPPS configuration option	104
1.7.41 PRINT_SYSTEM_MESSAGE - UPPS configuration option	105
1.7.42 PRIVATE_KEY - UPPS configuration option	106
1.7.43 PRIVATE_KEY_PWD - UPPS configuration option	107
1.7.44 PROCESS_INSTANCE - UPPS configuration option	108
1.7.45 PROCESS_INSTANCE_FROM - UPPS configuration option	109


1.7.46	PROCESS_INSTANCE_TO - UPPS configuration option	110
1.7.47	PROCESS_FILE_NAME - UPPS configuration option	111
1.7.48	PROCESS_NAME - UPPS configuration option	112
1.7.49	PROCESS_REQUEST_COUNT - UPPS configuration option	113
1.7.50	PROCESS_TYPE - UPPS configuration option	114
1.7.51	PROMPT - UPPS configuration option	115
1.7.52	RECURRENCE_NAME - UPPS configuration option	116
1.7.53	REPORT - UPPS configuration option	117
1.7.54	REPORT_FOLDER_NAME - UPPS configuration option	118
1.7.55	RETENTION_DAYS - UPPS configuration option	119
1.7.56	RETURN_JOB_LOG - UPPS configuration option	120
1.7.57	RETURN_SPOOL_LIST - UPPS configuration option	121
1.7.58	RUN_CONTROL_ID - UPPS configuration option	122
1.7.59	RUN_DATE_TIME - UPPS configuration option	123
1.7.60	RUN_STATUS - UPPS configuration option	124
1.7.61	SERVER_NAME - UPPS configuration option	125
1.7.62	SERVER_RUN - UPPS configuration option	126
1.7.63	SSL_CIPHER_LIST - UPPS configuration Option	127
1.7.64	TIME_ZONE - UPPS configuration option	129
1.7.65	TO_DATE - UPPS configuration option	130
1.7.66	TRACE_FILE_LINES - UPPS configuration option	131
1.7.67	TRACE_TABLE - UPPS configuration option	132
1.7.68	USER_ID - UPPS configuration option	133
1.7.69	VERIFY_HOST_NAME - UPPS configuration option	134
1.7.70	VERIFY_PEER - UPPS configuration option	135
1.7.71	VERSION - UPPS configuration option	136
1.8	Universal Connector for PeopleSoft Job Definition Files	137
1.8.1	XML Job Definition File Syntax	138

# Universal Connector for PeopleSoft 6.8.x Reference Guide

- [Overview](#)
  - [Functionality](#)
- [Supported PeopleSoft Versions](#)
- [Detailed Information](#)

## Overview


Universal Connector for PeopleSoft Process Scheduler (UPPS) controls background processing within a PeopleSoft system either from a command line or from a Universal Controller task. The command line interface allows any computer (and therefore any scheduling tool) on the network to manage PeopleSoft Process Scheduler background processing tasks via the local command line.



You indicate to Universal Connector for PeopleSoft which PeopleSoft system to connect to and what background processing tasks to perform. Universal Connector for PeopleSoft connects to the PeopleSoft system and processes your request.

Universal Connector for PeopleSoft uses the PeopleTools web service APIs to enable seamless integration with the PeopleSoft Process Scheduler.

The following diagram outlines how Universal Connector for PeopleSoft integrates with PeopleTools. In this diagram Universal Connector for PeopleSoft performs the role of the "Client Application" to interact with the ProcessRequest service in order to manage scheduling activities for processes, jobs, and jobSets in the PeopleSoft Process Scheduler.



For Detailed Information drop the z/OS Link/Section.

## Functionality

Universal Connector for PeopleSoft provides the functionality to integrate SAP systems into both local administrative tools and enterprise system management infrastructures.

Specifically, Universal Connector for PeopleSoft allows you to:

- Schedule processes, jobs, and jobSets
- Start processes, jobs, and jobSets
- Monitor processes, jobs, and jobSets
- Return output associated with completed or failed processes, jobs, and jobSets
- Hold processes, jobs, and jobSets
- Cancel processes, jobs, and jobSets
- Restart processes, jobs, and jobSets
- Delete processes, jobs, and jobSets
- Display various process request information
- Display Job and JobSet schedule information
- Display process parameters
- Display output produced by processes
- Display server constraint information
- Display various Process Scheduler prompt information

## Supported PeopleSoft Versions

Universal Connector for PeopleSoft supports PeopleSoft 8.42 and later.

## Detailed Information

The following pages provide additional detailed information for Universal Connector for PeopleSoft:

- [Universal Connector for PeopleSoft for UNIX](#)
- [Universal Connector for PeopleSoft for Windows](#)

- [Universal Connector for PeopleSoft Commands](#)
- [Universal Connector for PeopleSoft Exit Codes](#)
- [Universal Connector for PeopleSoft Configuration Options for Program Execution](#)
- [Universal Connector for PeopleSoft Configuration Options](#)
- [Universal Connector for PeopleSoft Job Definition Files](#)

# PeopleSoft Web Services

- [PeopleSoft PROCESSREQUEST Web Service](#)
- [Communicating with PeopleSoft Web Services](#)

## PeopleSoft PROCESSREQUEST Web Service

The Universal Connector for PeopleSoft Process Scheduler (UPPS) relies on the functionality of the PROCESSREQUEST web service provided by the PeopleSoft Integration Broker.

If the service is not already available on the Integration Broker, it will have to be provided before UPPS will be able carry out its functionality for that system. If necessary, the Provide Web Service Wizard of the PeopleSoft Integration Broker can easily perform the tasks required to make the PROCESSREQUEST service available.

The wizard can be opened by going to:

PeopleTools->Integration Broker->Web Services->Provide Web Services

All service operations of the PROCESSREQUEST web service should be enabled.

Refer to PeopleSoft documentation for details of using the Provide Web Service Wizard.

## Communicating with PeopleSoft Web Services

UPPS requires specific connection information to communicate with the web services offered by the PeopleSoft Integration Broker. The required UPPS configuration options are described in the [HOST Options](#) section of this documentation.

This section describes where to look in the PeopleSoft system to find the values needed for those configuration options.

The main value required for communicating with the PeopleSoft web services is specified in the the [ENDPOINT](#) configuration option. This value is the path to the web service on the Integration Broker.

The value defined for a specific PeopleSoft system can be obtained by going to:

PeopleTools->Integration Broker->Configuration->Service Configuration

From there, click on the Setup Target Locations link, which will provide a dialog containing a Web Service Target Locations section. This section specifies the HTTP and HTTPS endpoints used by the Integration Broker for web services.

Typical target locations will look similar to the following:

<b>Target Location</b>	<a href="http://qapsft.stone.branch:8000/PSIGW/PeopleSoftServiceListeningConnector/PSFT_HR">http://qapsft.stone.branch:8000/PSIGW/PeopleSoftServiceListeningConnector/PSFT_HR</a>
<b>Secure Target Location</b>	<a href="https://qapsft.stone.branch:8443/PSIGW/PeopleSoftServiceListeningConnector/PSFT_HR">https://qapsft.stone.branch:8443/PSIGW/PeopleSoftServiceListeningConnector/PSFT_HR</a>

Given the Secure Target Location above, the connection portion of a UPPS command line would look like this:

```
>upps -i qapsft.stone.branch -psendpoint https://qapsft.stone.branch:8443/PSIGW/PeopleSoftServiceListeningConnector/PSFT\_HR
```

# Universal Connector for PeopleSoft for UNIX

- [Introduction](#)
- [Usage](#)
- [Command Line Syntax](#)
  - [Example](#)

## Introduction

This information is specific to Universal Connector for PeopleSoft (UPPS) UNIX-based operating systems.

## Usage

Universal Connector for PeopleSoft for UNIX executes as a command line application.

Each command line execution contains:

1. Universal Connector for PeopleSoft command (and argument).
2. Configuration options (required and optional) associated with program execution, not with specific commands.
3. Configuration options associated with the specified command.

Each execution of Universal Connector for PeopleSoft performs an operation specified by the command. The configuration options describe information / actions for that operation.

## Command Line Syntax

The following figure illustrates the command line syntax of Universal Connector for PeopleSoft for UNIX.

```
upps {CANCEL | DELETE | DISPLAY | HOLD | START | SUBMIT | WAIT} HOSTUSER [COMMAND FILE | INFORMATIONAL | INSTALL
ATION | LOCAL | MESSAGE | SSL] [Command-Specific Options]
```

The names enclosed in {BRACES} (for example, [CANCEL](#)) identify command groups. For each execution of upps, a single command is specified from one of these groups. One or more configuration options associated with each command also can be used to specify additional information / actions for the execution. See [Universal Connector for PeopleSoft Commands](#) for detailed information on the commands, and their associated configuration options, in each command group.

The names not enclosed in {BRACES} or [BRACKETS], [HOST](#) and [USER](#), identify categories of configuration options that are associated with program execution and from which one or more configuration options are required. The names enclosed in [BRACKETS] (for example, [COMMAND FILE](#)) identify categories of configuration options that are associated with program execution and from which options are not required. See [Universal Connector for PeopleSoft Configuration Options for Program Execution](#) for detailed information on configuration options associated with program execution, not with one or more commands.

The [Command-Specific Options](#) are configuration options associated with one more more Commands and which are not required.

## Example

The following is an example of a command line syntax executing Universal Connector for PeopleSoft:

```
upps -sub file.usp -host Server1 -psendpoint 192.168.30.17 -userid 123 -pwd ABC -lang english -level info
```



# Universal Connector for PeopleSoft for Windows

- [Introduction](#)
- [Usage](#)
- [Command Line Syntax](#)
  - [Example](#)

## Introduction

This information is specific to Universal Connector for PeopleSoft (UPPS) for Windows-based operating systems.

## Usage

Universal Connector for PeopleSoft for Windows executes as a command line application.

Each command line execution contains:

1. Universal Connector for PeopleSoft command (and argument).
2. Configuration options associated with that command.
3. Configuration options (required and optional) not associated with any specific command.

Each execution of Universal Connector for PeopleSoft performs an operation specified by the command. The configuration options describe information / actions for that operation.

## Command Line Syntax

The following figure illustrates the command line syntax of Universal Connector for PeopleSoft for Windows.

```

upps {
  CANCEL
  |
  DELETE
  |
  DISPLAY
  |
  HOLD
  |
  START
  |
  SUBMIT
  |
  WAIT}
HOST
USER
[
COMMAND FILE | INFORMATIONAL | INSTALLATION | LOCAL | MESSAGE | SSL
] [
  Command-Specific Options
]

```

The names enclosed in {BRACES} (for example, [CANCEL](#)) identify command groups. For each execution of upps, a single command is specified from one of these groups. One or more configuration options associated with each command also can be used to specify additional information / actions for the execution. See [Universal Connector for PeopleSoft Commands](#) for detailed information on the commands, and their associated configuration options, in each command group.

The names not enclosed in {BRACES} or [BRACKETS], [HOST](#) and [USER](#), identify categories of configuration options that are associated with program execution and from which one or more configuration options are required. The names enclosed in [BRACKETS] (for example, [COMMAND FILE](#)) identify categories of configuration options that are associated with program execution and from which options are not required. See [Universal Connector for PeopleSoft Configuration Options for Program Execution](#) for detailed information on configuration options associated with program execution, not with one or more commands.

The [Command-Specific Options](#) are configuration options associated with one more more Commands and which are not required.

## Example

The following is an example of a command line syntax executing Universal Connector for PeopleSoft:

```
upps
-sub
file.usp
-host
Server1
-psendpoint
192.168.30.17
-userid
123
-pwd
ABC
-lang
english
-level
info
```

# Universal Connector for PeopleSoft Commands

- [Universal Connector for PeopleSoft Commands](#)
- [Command Groups](#)
  - [Command Description](#)
  - [Command Line Syntax](#)
  - [Command Argument](#)
  - [Command Options](#)

## Universal Connector for PeopleSoft Commands

This page identifies and provides links to detailed information on all commands of Universal Connector for PeopleSoft\_.

Each command has configuration options associated with it that can be used to specify additional information / actions for an execution of that command.

(For information on configuration options not associated with one or more specific commands, see [Universal Connector for PeopleSoft Configuration Options for Program Execution.](#))

## Command Groups

Universal Connector for PeopleSoft groups commands into areas of common functionality, as shown in the following table. Each row identifies a command group, the commands in that group, and the type of operation performed by those commands.

Each command name is a link to the following information about that command:

### Command Description

Description of the operation(s) performed by the command.

### Command Line Syntax

Syntax of the command and its options on the command line.

### Command Argument

Command line expression (short and/or long form) and description of the command argument.

### Command Options

Description of the configuration options associated with the option and a link to detailed information about those options.

Command Groups	Description
<b>CANCEL</b> <ul style="list-style-type: none"> <li>• <a href="#">CANCEL PROCESS Command</a></li> </ul>	The CANCEL command group contains a single command, CANCEL PROCESS, that cancels a job or process instance.
<b>DELETE</b> <ul style="list-style-type: none"> <li>• <a href="#">DELETE PROCESS Command</a></li> </ul>	The DELETE command group contains a single command, DELETE PROCESS, that deletes a job or process instance.

<p><b>DISPLAY</b></p> <ul style="list-style-type: none"> <li>• <a href="#">DISPLAY OUTPUT FORMATS Command</a></li> <li>• <a href="#">DISPLAY OUTPUT TYPES Command</a></li> <li>• <a href="#">DISPLAY PRCS GET REPORT Command</a></li> <li>• <a href="#">DISPLAY PRCS GET REQUEST Command</a></li> <li>• <a href="#">DISPLAY PRCS GET SERVER CONSTRAINTS Command</a></li> <li>• <a href="#">DISPLAY PRCS PARAMS Command</a></li> <li>• <a href="#">DISPLAY PRCS PRINT JOB HTML REPORT Command</a></li> <li>• <a href="#">DISPLAY PRCS PRINT JOB REQUEST REPORT Command</a></li> <li>• <a href="#">DISPLAY PRCS PRINT SCHED HTML REPORT Command</a></li> <li>• <a href="#">DISPLAY PRCS PROMPT Command</a></li> <li>• <a href="#">DISPLAY PROCESS NAMES Command</a></li> <li>• <a href="#">DISPLAY REQUESTS Command</a></li> </ul>	<p>The DISPLAY command group contains commands that display various types of PeopleSoft data.</p>
<p><b>HOLD</b></p> <ul style="list-style-type: none"> <li>• <a href="#">HOLD PROCESS Command</a></li> </ul>	<p>The HOLD command group contains a single command, HOLD PROCESS, that places a job or process instance on hold</p>
<p><b>START</b></p> <ul style="list-style-type: none"> <li>• <a href="#">START JOBSET Command</a></li> </ul>	<p>The START command group contains a single command, START JOBSET, that starts a jobset.</p>
<p><b>SUBMIT</b></p> <ul style="list-style-type: none"> <li>• <a href="#">SUBMIT PROCESS Command</a></li> </ul>	<p>The SUBMIT command group contains a single command, SUBMIT PROCESS, that schedules a job or process.</p>
<p><b>WAIT</b></p> <ul style="list-style-type: none"> <li>• <a href="#">WAIT for PROCESS</a></li> </ul>	<p>The WAIT command group contains a single command, WAIT for PROCESS, that waits for a job or process instance to complete.</p>

# CANCEL PROCESS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Configuration Options](#)
- [Example](#)

## Description

The CANCEL PROCESS command cancels the specified process instance in the PeopleSoft system.

## Command Line Syntax

The following figure illustrates the command line syntax of the CANCEL PROCESS command, using the command line, long form of its [configuration options](#).

```
upps -cancel -processinstance number
```

## Configuration Options

The following table describes all CANCEL PROCESS configuration options and provides the command line, long form of each option illustrated in the [CANCEL PROCESS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_INSTANCE</a>	-processinstance	Process instance number identifying the process to be canceled.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -cancel -processinstance 140596
UNV6823I Process instance 71729184 was successfully cancelled.
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DELETE PROCESS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DELETE PROCESS command deletes the specified process instance from the PeopleSoft system.

## Command Line Syntax

The following figure illustrates the command line syntax of the DELETE PROCESS command, using the command line, long form of its [configuration options](#).

```
-delete -processinstancenumber
```

## Configuration Options

The following table describes all DELETE PROCESS configuration options and provides the command line, long form of each option illustrated in the [DELETE PROCESS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_INSTANCE</a>	-processinstance	Process instance number identifying the process to be deleted.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -delete -processinstance 140593
UNV6822I Process instance 44924272 was successfully deleted.
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY OUTPUT FORMATS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY OUTPUT FORMATS command displays a list of available output destination formats.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY OUTPUT FORMATS command, using the command line, long form of its [configuration options](#).

```
-display prcs_get_outputformats
[-processtypetype][-processnamename][-outputdestinationtype][-langcodecode][-outfmt {text | xml}]
```

## Command Argument

The DISPLAY OUTPUT FORMATS command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY OUTPUT FORMATS command argument, **prcs\_get\_outputformats**, displays a list of available output destination formats for the specified process resource.

## Configuration Options

The following table describes all DISPLAY OUTPUT FORMATS configuration options and provides the command line, long form of each option illustrated in the [DISPLAY OUTPUT FORMATS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_TYPE</a>	-processtype	Filter requests by this process type.
<a href="#">PROCESS_NAME</a>	-processname	Filter requests by this process name.
<a href="#">OUTPUT_DESTINATION_TYPE</a>	-outputdestinationtype	Filter requests by this output destination type.
<a href="#">LANGUAGE_CODE</a>	-langcode	Filter requests by this language code.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example



```
uapps -userid PS1 -pwd PS1 -host gapsft.stone.branch -port 8000 -display prcs_get_outputformats -processtype
"AppEngine" -processname "PSXPQRYRPT" -outputdestinationtype "WEB"
```

```
sname PSXPQRYRPT -outputdestinationtype WEB
Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value...: WEB
Output Format Value.: Rich Text File (*.rtf)
Is Active.....: Yes
Is Default Type.....: No
```

```
Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value...: WEB
Output Format Value.: Text Files (*.txt)
Is Active.....: Yes
Is Default Type.....: No
```

```
Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value...: WEB
Output Format Value.: Acrobat (*.pdf)
Is Active.....: Yes
Is Default Type.....: No
```

```
Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value...: WEB
Output Format Value.: HTML Documents (*.htm)
Is Active.....: Yes
Is Default Type.....: Yes
```

```
Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value...: WEB
Output Format Value.: Microsoft Excel Files (*.xls)
Is Active.....: Yes
Is Default Type.....: No
```

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

# DISPLAY OUTPUT TYPES - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY OUTPUT TYPES command displays a list of available output types for the specified process resource.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY OUTPUT TYPES command, using the command line, long form of its [configuration options](#).

```
-display prcs_get_outputtypes
[-processtype type][-processname name][-langcode code][-outfmt {text | xml}]
```

## Command Argument

The DISPLAY OUTPUT TYPES command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY OUTPUT TYPES command argument, **prcs\_get\_outputtypes**, displays a list of available output types for the specified process resource.

## Configuration Options

The following table describes all DISPLAY OUTPUT TYPES configuration options and provides the command line, long form of each option illustrated in the [DISPLAY OUTPUT TYPES command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_TYPE</a>	-processtype	Filter requests by this process type.
<a href="#">PROCESS_NAME</a>	-processname	Filter requests by this process name.
<a href="#">LANGUAGE_CODE</a>	-langcode	Filter requests by this language code.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_get_outputtypes -processtype
"AppEngine"

Process Type.....: AppEngine
Process Name.....: -
Output Type Value.: FILE
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
```

```

Process Name.....: -
Output Type Value.: WINDOW
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: -
Output Type Value.: EMAIL
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: -
Output Type Value.: WEB
Is Active.....: Yes
Is Default Type...: Yes

Process Type.....: AppEngine
Process Name.....: PSCONQRS
Output Type Value.: FILE
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSCONQRS
Output Type Value.: WINDOW
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSCONQRS
Output Type Value.: WEB
Is Active.....: Yes
Is Default Type...: Yes

Process Type.....: AppEngine
Process Name.....: PSCONQRS
Output Type Value.: IB Node
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: FILE
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: WINDOW
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: EMAIL
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: WEB
Is Active.....: Yes
Is Default Type...: Yes

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: FEED
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSQUERY
Output Type Value.: IB Node
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine
Process Name.....: PSXPQRYRPT
Output Type Value.: FILE
Is Active.....: Yes
Is Default Type...: No

Process Type.....: AppEngine

```

```
Process Name.....: PSXPQYRPT  
Output Type Value.: PRINTER  
Is Active.....: Yes  
Is Default Type...: No
```

```
Process Type.....: AppEngine  
Process Name.....: PSXPQYRPT  
Output Type Value.: WINDOW  
Is Active.....: Yes  
Is Default Type...: No
```

```
Process Type.....: AppEngine  
Process Name.....: PSXPQYRPT  
Output Type Value.: EMAIL  
Is Active.....: Yes  
Is Default Type...: No
```

```
Process Type.....: AppEngine  
Process Name.....: PSXPQYRPT  
Output Type Value.: WEB  
Is Active.....: Yes  
Is Default Type...: Yes
```

```
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PRCS GET REPORT - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS GET REPORT command displays a report from the PeopleSoft Report Repository.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS GET REPORT command, using the command line, long form of its [configuration options](#).

```
-display prcs_getreport-contentidID [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS GET REPORT command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS GET REPORT command argument, **prcs\_getreport**, displays a report from the PeopleSoft Report Repository.

## Configuration Options

The following table describes all DISPLAY PRCS GET REPORT configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS GET REPORT command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">CONTENT_ID</a>	-contentid	Content ID that identifies the report to be returned from the report repository.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_getreport -contentid 29615

Report URL: http://qapsft.stone.branch:8000/psreports/ps/29615/AE_TREEMOVER_140591.stdout
PeopleTools 8.55.09 - Application Engine Server
Copyright (c) 1988-2018 Oracle and/or its affiliates.
All Rights Reserved
PSAESRV started service request at 13.33.57 2018-02-08
No filename provided (2,901) TREEMOVER.Deleting.GBL.default.1900-01-01.Step01.OnExecute PCPC:167 Statement:5
Process 140591 ABENDED at Step TREEMOVER.Deleting.Step01 (PeopleCode) -- RC = 8 (108,524)
Process %s ABENDED at Step %s.%s.%s (Action %s) -- RC = %s
PSAESRV completed service request at 13.33.57 2018-02-08

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PRCS GET REQUEST - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS GET REQUEST command displays Get process request information for a specific request instance.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS GET REQUEST command, using the command line, long form of its [configuration options](#).

```
-display prcs_getrequest-processinstancenumber [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS GET REQUEST command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS GET REQUEST command argument, **prcs\_getrequests**, displays the Get process request information for a specific request instance.

## Configuration Options

The following table describes all DISPLAY PRCS GET REQUEST configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS GET REQUEST command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_INSTANCE</a>	-processinstance	Process instance number identifying the request to be returned.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command: <ul style="list-style-type: none"> <li>• text: output will be formatted for human consumption.</li> <li>• xml: output will be formatted as XML.</li> </ul>

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_getrequest -processinstance 140595
```

```
Process Instance.....: 140595  
Process Name.....: TREEMOVER  
Process Type.....: Application Engine  
Run Control Id.....: ESS1A  
Server Name Run.....: PRCS1090  
Operator Id.....: PS1  
Request Date Time.....: 2018-02-08-13.39.30.095806  
Run Date Time.....: 2018-02-08-13.39.29.000000  
Begin Date Time.....: 2018-02-08-13.47.06.608259  
End Date Time.....: 2018-02-08-13.47.21.682346  
Output Destination Format.: TXT  
Output Destination Type...: WEB  
Run Status.....: No Success  
Distribution Status.....: Posted  
Content Id.....: 29618
```

```
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PRCS GET SERVER CONSTRAINTS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS GET SERVER CONSTRAINTS command displays server constraint information for servers matching the specified criteria.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS GET SERVER CONSTRAINTS command, using the command line, long form of its [configuration options](#).

```
-display prcs_getserverconstraints
[-servername][-processtype][-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS GET SERVER CONSTRAINTS command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS GET SERVER CONSTRAINTS command argument, **prcs\_getserverconstraints**, displays server constraint information for servers matching the specified criteria.

## Configuration Options

The following table describes all DISPLAY PRCS GET SERVER CONSTRAINTS configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS GET SERVER CONSTRAINTS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">SERVER_NAME</a>	-servername	Specific server name for which constraints will be returned.
<a href="#">PROCESS_TYPE</a>	-processtype	Specific process type for which constraints will be returned.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example



```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_getserverconstraints -processtype  
"Application Engine"
```

```
Server Name..: PRCS1090  
Process Type.: Application Engine  
Current Load.: 0  
Max Load.....: 3
```

```
Server Name..: PSCDB  
Process Type.: Application Engine  
Current Load.: 0  
Max Load.....: 1
```

```
Server Name..: PSNT  
Process Type.: Application Engine  
Current Load.: 0  
Max Load.....: 3
```

```
Server Name..: PSOS390  
Process Type.: Application Engine  
Current Load.: 0  
Max Load.....: 3
```

```
Server Name..: PSUNX  
Process Type.: Application Engine  
Current Load.: 0  
Max Load.....: 6
```

```
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PRCS PARAMS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS PARAMS command displays the list of parameter values for a PeopleSoft job or process.

### Note

 The job or process must have generic prompting enabled and runtime parameters defined.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS PARAMS command, using the command line, long form of its [configuration options](#).

```
-display prcs_params {-jobname name | -processname name} -processtype type [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS PARAMS command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS PARAMS command argument, **prcs\_params**, displays the list of parameter values for a PeopleSoft job or process.

## Configuration Options

The following table describes all DISPLAY PRCS PARAMS configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS PARAMS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">JOB_NAME</a>	-jobname	Job name for which parameters will be returned.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command: <ul style="list-style-type: none"> <li>• text: output will be formatted for human consumption.</li> <li>• xml: output will be formatted as XML.</li> </ul>
<a href="#">PROCESS_NAME</a>	-processname	Name of the PeopleSoft process for which parameters will be returned.
<a href="#">PROCESS_TYPE</a>	-processtype	Type of PeopleSoft process for which parameter names will be returned.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_params -processname TREEMOVER
```

```
Process Name.....: TREEMOVER  
Process Type.....: Application Engine  
Record Name.....: RUN_TREEMOVER  
Record Field Name.....: FILENAME  
Parameter Name.....: File Name  
Application Class Method: .
```

```
Process Name.....: TREEMOVER  
Process Type.....: Application Engine  
Record Name.....: RUN_TREEMOVER  
Record Field Name.....: TREE_NAME  
Parameter Name.....: Tree Name  
Application Class Method: .
```

```
Process Name.....: TREEMOVER  
Process Type.....: Application Engine  
Record Name.....: RUN_TREEMOVER  
Record Field Name.....: TREE_EFFDT  
Parameter Name.....: Effective Date of Tree  
Application Class Method: .
```

```
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PRCS PRINT JOB HTML REPORT - UPPS

## Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS PRINT JOB HTML REPORT command displays a report with all items in a job or jobset, as defined in the job definition component.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS PRINT JOB HTML REPORT command, using the command line, long form of its [configuration options](#).

```
-display prcs_print_jobhtmlreport-jobnamename [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS PRINT JOB HTML REPORT command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS PRINT JOB HTML REPORT command argument, **prcs\_print\_jobhtmlreport**, displays a report with all items in a job or jobset, as defined in the job definition component.

## Configuration Options

The following table describes all DISPLAY PRCS PRINT JOB HTML REPORT configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS PRINT JOB HTML REPORT command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">JOB_NAME</a>	-jobname	Job name for which parameters will be returned.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example

```
uups -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_print_jobhtmlreport -jobname  
CC_TEST
```

```
<span class='PSTEXT' ><strong>CC_TEST<  
/strong></span><br /><span  
class='PSTEXT' >1 FGHR003A: 60 Day Probation Term Notices (Application Engine)</span><br /><span class='PSTEXT' >2 TREEMOVER:  
Tree Mover (Application Engine)</span><br /><p>&nbsp;</p>
```

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

# DISPLAY PRCS PRINT JOB REQUEST REPORT - UPPS

## Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS PRINT JOB REQUEST REPORT command displays a report containing the current status of a specific process, job, or jobset.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS PRINT JOB REQUEST REPORT command, using the command line, long form of its [configuration options](#).

```
-display prcs_print_jobrequestreport-processinstancenumber[-iteminstancenumber][-printjobtree {yes | no}]
[-printdistlist {yes | no}]
[-printsystemmessage {yes | no}]
[-printapplicationmessage {yes | no}]
[-printparamlist {yes | no}]
[-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS PRINT JOB REQUEST REPORT command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS PRINT JOB REQUEST REPORT command argument, **prcs\_print\_jobrequestreport**, displays a report containing the current status of a specific process, job, or jobset.

## Configuration Options

The following table describes all DISPLAY PRCS PRINT JOB REQUEST REPORT configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS PRINT JOB REQUEST REPORT command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_INSTANCE</a>	-processinstance	Process instance number identifying the job, jobset, or process.
<a href="#">ITEM_INSTANCE</a>	-iteminstance	Instance number of the scheduled job or jobset.
<a href="#">PRINT_JOB_TREE</a>	-printjobtree	Specification for whether or not the job tree is included in the report.
<a href="#">PRINT_DIST_LIST</a>	-printdistlist	Specification for whether or not the report-recipient distribution list is included in the report.
<a href="#">PRINT_SYSTEM_MESSAGE</a>	-printsystemmessage	Specification for whether or not system messages are included in the report.
<a href="#">PRINT_APPLICATION_MESSAGE</a>	-printapplicationmessage	Specification for whether or not application messages are included in the report.
<a href="#">PRINT_PARAM_LIST</a>	-printparamlist	Specification for whether or not the parameter list for job items are included in the report.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command.

## Example

```

upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_print_jobrequestreport -
processinstance 140596

<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.0 Transitional//EN"><HTML><HEAD><TITLE>Job Report</TITLE><META
content="text/html; charset=windows-1252" http-equiv=Content-Type><STYLE type=text/css>
.PSHEADER {BACKGROUND-COLOR: rgb(51,51,153); COLOR: rgb(255,255,255); FONT-FAMILY: "Arial","sans-serif"; FONT-
SIZE: 9pt; FONT-STYLE: normal; FONT-WEIGHT: bold}
.PSEVENROW {BACKGROUND-COLOR: rgb(255,255,255); COLOR: rgb(0,0,0); FONT-FAMILY: "Arial","sans-serif"; FONT-
SIZE: 9pt; FONT-STYLE: normal; FONT-WEIGHT: normal}
.PSODDROW {BACKGROUND-COLOR: rgb(226,226,226); COLOR: rgb(0,0,0); FONT-FAMILY: "Arial","sans-serif"; FONT-SIZE:
9pt; FONT-STYLE: normal; FONT-WEIGHT: normal}
</STYLE><META content="MSHTML 5.00.3103.1000" name=GENERATOR></HEAD><BODY><span class='PSTEXT' ><strong>CC_TEST</strong></span><br /><span class='PSTEXT' >1 FGHR003A: 60
Day Probation Term Notices (Application Engine)</span><br /><span class='PSTEXT' >2 TREEMOVER: Tree Mover (Application Engine)<
/span><br /><p>&nbsp;</p><TABLE cellpadding=2 cellspacing=0 width="100%"><TBODY><TR><TD><TABLE border=1
cellpadding=3 cellspacing=0 width="100%"><TBODY><TR><TH colspan="3" bordercolor=rgb(51,51,153)
><p align="left">Instance: 140596</p></TH><TH colspan="9" bordercolor=rgb(51,51,153)>Job Name:
CC_TEST - CC_TEST</TH></TR><TR><TH colspan="3" bordercolor=rgb(51,51,153)><p align="left"
>Mode: Serial</p></TH><TH colspan="9" bordercolor=rgb(51,51,153)>&nbsp;</TH></TR><TR><TH
class='PSHEADER' width="5%">Seq.</TH><TH class='PSHEADER' width="10%">Instance</TH><TH class='PSHEADER'
width="10%">Process Name</TH><TH class='PSHEADER' width="15%">Description</TH><TH class='PSHEADER'
width="10%">Process
Type</TH><TH class='PSHEADER' width="5%">Run Status</TH><TH class='PSHEADER' width="10%">Run Control ID</TH><TH
class='PSHEADER' width="5%">Type</TH><TH class='PSHEADER' width="8%">Output
Format</TH><TH class='PSHEADER' width="8%">Server Name</TH><TH class='PSHEADER' width="7%">Begin Date/Time<
/TH><TH class='PSHEADER' width="7%">End Date/Time</TH></TR><TR><TD class='PSEVENROW' align="center" width="5%"
>1</TD><TD class='PSEVENROW' align="center" width="8%">140597</TD><TD class='PSEVENROW' width="10%"><a
href=http://qapsft.stone.branch:8000/psc/ps/EMPLOYEE/PSFT_HR/c/CDM_RPT.CDM_RPT.GBL?
Page=CDM_RPT_INDEX&Action=U&CDM_ID=29619>FGHR003A/a</TD>
<TD class='PSEVENROW' width="15%">60 Day Probation Term Notices</TD><TD class='PSEVENROW' align="
center" width="10%">Application Engine</TD><TD class='PSEVENROW' align="center" width="8%">Success</TD><TD
class='PSEVENROW' align="center" width="5%">ESS1A</TD><TD class='PSEVENROW' align="center" width="5%">Web<
/td><TD class='PSEVENROW' align="center" width="8%">Text Files (*.txt)</TD><TD class='PSEVENROW' align="
center" width="8%">PRCS1090</TD><TD class='PSEVENROW' align="center" width="7%">2018-02-08-14.01.09.302245</TD><TD
class='PSEVENROW' align="center" width="7%">2018-02-08-14.01.09.302245</TD></TR><TR><TD
class='PSEVENROW' colspan="2">&nbsp;</TD><TD class='PSEVENROW' colspan="10"><p><strong>Parameter:</strong><
/p><p>psae -CT ORACLE -CD HR92U19 -CO "PS1" -CP OPRPSWD -R ESS1A -I 140597 -AI FGHR003A -OT 6 -FP "/home/psadm2
/psft/pt/8.55/appserv/prcs/PRCSODM/log_output/AE_FGHR003A_140597/" -OF 14</p><p><strong>Distribution List:</strong><
/strong></p><table border="1" cellpadding="3" cellspacing="0" bordercolor="#CCCCCC"><tr><td class='PSEVENROW'
><strong>Type</strong></td><td class='PSEVENROW' ><strong>Name</strong></td></tr><tr><td class='PSEVENROW'
>User</td><td class='PSEVENROW' >PS</td></tr><tr><td class='PSEVENROW' >User</td><td class='PSEVENROW' >PS1<
/td></tr></table><p><strong>Application Messages:</strong></p><p><strong>Published message with ID 6c706d4e-0d02-11e8-
b10f-f5bb5f09b289 to create entry in folder GENERAL. (65,435)</p><p>Successfully posted generated files to the
report repository (65,71)</p></td></tr><tr><td class='PSODDROW' align="center" width="5%">2</td><td
class='PSODDROW' align="center" width="8%">140598</td><td class='PSODDROW' width="10%">TREEMOVER</td><td
class='PSODDROW' width="15%">Tree Mover</td><td class='PSODDROW' align="center" width="10%">Application
Engine</td><td class='PSODDROW' align="center" width="8%">Cancelled</td><td class='PSODDROW' align="center"
width="5%">ESS1A</td><td class='PSODDROW' align="center" width="5%">Web</td><td class='PSODDROW' align="
center" width="8%">Text Files (*.txt)</td><td class='PSODDROW' align="center" width="8%">PRCS1090</td><td
class='PSODDROW' align="center" width="7%">2018-02-08-14.01.10.463487</td><td class='PSODDROW' align="center"
width="7%">2018-02-08-14.01.13.250880</td></tr><tr><td class='PSODDROW' colspan="2">&nbsp;</td><TD
class='PSODDROW' colspan="10"><p><strong>Parameter:</strong></p><p>psae -CT ORACLE -CD HR92U19 -CO "PS1" -CP
OPRPSWD -R ESS1A -I 140598 -AI TREEMOVER -OT 6 -FP "/home/psadm2/psft/pt/8.55/appserv/prcs/PRCSODM/log_output
/AE_TREEMOVER_140598/" -OF 14</p><p><strong>Distribution List:</strong></p><table border="1" cellpadding="3"
cellspacing="0" bordercolor="#CCCCCC"><tr><td class='PSODDROW' ><strong>Type</strong></td><td class='PSODDROW'
><strong>Name</strong></td></tr><tr><td class='PSODDROW' >User</td><td class='PSODDROW' >PS</td></tr><tr><td
class='PSODDROW' >User</td><td class='PSODDROW' >PS1</td></tr></table><p><strong>Application Messages:</strong><
/strong></p><p>PeopleCode Exit(1) Abort invoked by Application at TREEMOVER.Export.Step01. (108,543)</p><p>Process
140598 ABENDED at Step TREEMOVER.Export.Step01 (PeopleCode) -- RC = ? (108,524)</p><p>140598 TREEMOVER Export
Step01 PeopleCode ? %7 %8 %9 (65,30)</p><p>Published message with ID 761ff1a2-0d02-11e8-b10f-f5bb5f09b289 to
create entry in folder GENERAL. (65,435)</p><p>Successfully posted generated files to the report repository
(65,71)</p></td></tr></tbody></table><p>&nbsp;</p></td></tr></tbody></table><BR></BODY></HTML>

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

```

# DISPLAY PRCS PRINT SCHED HTML REPORT - UPPS

## Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS PRINT SCHED HTML REPORT command displays a report listing all items in a job or jobset, as defined in the Scheduled Jobset Definition component.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS PRINT SCHED HTML REPORT command, using the command line, long form of its [configuration options](#).

```
-display prcs_print_schedhtmlreport -mainschedname name -mainjobname name [-printjobtree {yes | no}]
[-printdistlist {yes | no}]
[-printnotifylist {yes | no}]
[-printmessagelist {yes | no}]
[-printparamlist {yes | no}]
[-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS PRINT SCHED HTML REPORT command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS PRINT SCHED HTML REPORT command argument, **prcs\_print\_schedhtmlreport**, displays a report listing all items in a job or jobset, as defined in the Scheduled Jobset Definition component.

## Configuration Options

The following table describes all DISPLAY PRCS PRINT SCHED HTML REPORT configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS PRINT SCHED HTML REPORT command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">MAIN_SCHED_NAME</a>	-mainschedname	Name of the jobset schedule.
<a href="#">MAIN_JOB_NAME</a>	-mainjobname	Name of the job within the jobset schedule.
<a href="#">PRINT_JOB_TREE</a>	-printjobtree	Specification for whether or not the job tree is included in the report.
<a href="#">PRINT_DIST_LIST</a>	-printdistlist	Specification for whether or not the report-recipient distribution list is included in the report.
<a href="#">PRINT_NOTIFY_LIST</a>	-printnotifylist	Specification for whether or not the notify list is included in the report.
<a href="#">PRINT_MESSAGE_LIST</a>	-printmessagelist	Specification for whether or not the messages that will be emailed upon completion of a job item are included in the report.
<a href="#">PRINT_APPLICATION_MESSAGE</a>	-printmplicationessage	Specification for whether or not the messages specified from the Process Definition or Job Definition page are included in the report.



PRINT_PARAM_LIST	-pirntparamlist	Specification for whether or not the parameter list for job items are included in the report.
OUTPUT_FORMAT	-outfmt	Format of the output for this command.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_print_schedhtmlreport -
mainschedname ESSJS1 -mainjobname ESSJ1
```

```
<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.0 Transitional//EN"><HTML><HEAD><TITLE>Job Report</TITLE><META
content="text/html; charset=windows-1252" http-equiv=Content-Type><STYLE type=text/css>
.PSHEADER {BACKGROUND-COLOR: rgb(51,51,153); COLOR: rgb(255,255,255); FONT-FAMILY: "Arial","sans-serif"; FONT-
SIZE: 9pt; FONT-STYLE: normal; FONT-WEIGHT: bold}
.PSEVENROW {BACKGROUND-COLOR: rgb(255,255,255); COLOR: rgb(0,0,0); FONT-FAMILY: "Arial","sans-serif"; FONT-
SIZE: 9pt; FONT-STYLE: normal; FONT-WEIGHT: normal}
.PSODDROW {BACKGROUND-COLOR: rgb(226,226,226); COLOR: rgb(0,0,0); FONT-FAMILY: "Arial","sans-serif"; FONT-SIZE:
9pt; FONT-STYLE: normal; FONT-WEIGHT: normal}
</STYLE><META content="MSHTML 5.00.3103.1000" name=GENERATOR></HEAD><BODY><span class='PSTEXT' ><strong>ESSJS1</strong></span><br /><span class='PSTEXT' ><strong>ESSJ1</strong></span><br /><span class='PSTEXT' >1 ABS001: Employee Absence
Report (SQR Report)</span><br /><p>&nbsp;</p><TABLE cellpadding=2 cellspacing=0 width="100%"
><TBODY><TR><TD><TABLE border=1 cellpadding=3 cellspacing=0 width="100%"><TBODY><tr><th class='PSHEADER'
colspan="10" bordercolor=rgb(51,51,153)><p align="left">Job Name: ESSJ1 - ESSJ1</p></th></tr><tr><th
class='PSHEADER' colspan="3" bordercolor=rgb(51,51,153)><p align="left">Mode: Serial</p></th><th
class='PSHEADER' colspan="7" bordercolor=rgb(51,51,153)>&nbsp;</th></tr><tr><th class='PSHEADER' width="5%"
>Seq.</th><th class='PSHEADER' width="10%">Process Name</th><th class='PSHEADER' width="15%">Description<
/th><th class='PSHEADER' width="10%">Process Type</th><th class='PSHEADER' width="10%">Run Control ID</th><th
class='PSHEADER' width="5%">Type</th><th class='PSHEADER' width="8%">Output
Format</th><th class='PSHEADER' width="10%">Destination</th><th class='PSHEADER' width="8%">Server Option<
/th><th class='PSHEADER' width="5%">Run Time</th></tr><tr><td class='PSEVENROW' align="center" width="5%">1<
/td><td class='PSEVENROW' width="10%">ABS001</td><td class='PSEVENROW' width="15%">Employee Absence Report<
/td><td class='PSEVENROW' align="center" width="10%">SQR Report</td><td class='PSEVENROW' align="center"
width="5%">ESSRCID1</td><td class='PSEVENROW' align="center" width="5%">Web</td><td class='PSEVENROW' align="
center" width="8%">Acrobat (*.pdf)</td><td class='PSEVENROW' align="center" width="10%">Distribution List<
/td><td class='PSEVENROW' align="center" width="8%">Any Server&nbsp;</td><td class='PSEVENROW' align="center"
width="5%">&nbsp;</td></tr><tr><td class='PSEVENROW' colspan="2">&nbsp;</td><td class='PSEVENROW' colspan="8"
><p><strong>Parameter:</strong></p><p>-CT ORACLE -CS %SERVER% -CD HR92U19 -CA %ACCESSID% -CAP %ACCESSPSWD% -RP
ABS001 -I %INSTANCE% -R ESSRCID1 -CO PS1 -OT 2 -OP "%OUTDEST%" -OF 1 -LG </p><p><strong>Distribution List:<
/strong></p><table border="1" cellpadding="3" cellspacing="0" bordercolor="#CCCCCC"><tr><td class='PSEVENROW'
><strong>Type</strong></td><td class='PSEVENROW' ><strong>Name</strong></td></tr><tr><td class='PSEVENROW'
>User </td><td class='PSEVENROW' >PS </td></tr></table></td></tr></TBODY></TABLE><p> </p></TD></TR><
/TBODY></TABLE><BR></BODY></HTML>
```

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

# DISPLAY PRCS PROMPT - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PRCS PROMPT command displays a list of the specified prompt values available in the PeopleSoft system.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PRCS PROMPT command, using the command line, long form of its [configuration options](#).

```
-display prcs_prompt-prompt {RunStatus | DistributionStatus | ServerName | ProcessTypes | OperatorId | RecurrenceName | Time zones} [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PRCS PROMPT command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PRCS PROMPT command argument, **prcs\_prompt**, requests the display of the list of the specified prompt values available in the PeopleSoft system.

## Configuration Options

The following table describes all DISPLAY PRCS PROMPT configuration options and provides the command line, long form of each option illustrated in the [DISPLAY PRCS PROMPT command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROMPT</a>	-prompt	Type of prompt values that will be displayed: <ul style="list-style-type: none"> <li>• RunStatus</li> <li>• DistributionStatus</li> <li>• ServerName</li> <li>• ProcessTypes</li> <li>• OperatorId</li> <li>• RecurrenceName</li> </ul> PROMPT values are case sensitive.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command: <ul style="list-style-type: none"> <li>• text: output will be formatted for human consumption.</li> <li>• xml: output will be formatted as XML.</li> </ul>

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_prompt -prompt ProcessTypes
```

```
Application Engine  
XML Publisher  
Cube Builder  
COBOL SQL  
Crw Online  
Crystal  
Data Mover  
Database Agent  
Essbase Cube Builder  
Message Agent API  
Optimization Engine  
PSJob  
SQR Process  
SQR Report  
SQR Report For WF Delivery  
Winword  
nVision-Report  
nVision-ReportBook
```

```
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY PROCESS NAMES - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY PROCESS NAMES command displays the list of process names in the PeopleSoft system for a specified process type.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY PROCESS NAMES command, using the command line, long form of its [configuration options](#).

```
-display process_names-processtypeprocess_type [-outfmt {text | xml}]
```

## Command Argument

The DISPLAY PROCESS NAMES command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY PROCESS NAMES command argument, **process\_names**, requests the display of the list of process names in the PeopleSoft system for the specified process type.

## Configuration Options

The following table describes all DISPLAY PROCESS NAMES configuration options and provides the command line, long form of each option illustrated in the DISPLAY PROCESS NAMES [command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_TYPE</a>	-processtype	Type of process for which process names will be returned.
<a href="#">OUTPUT_FORMAT</a>	-outfmt	Format of the output for this command: <ul style="list-style-type: none"> <li>• text: output will be formatted for human consumption.</li> <li>• xml: output will be formatted as XML.</li> </ul>

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display process_names -processtype PSJob  
3CBL  
3SQR  
ACA1095C  
AETST001  
ALLTYPES  
APP004DG  
APP007DG  
BEN110_J  
....  
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.
```

# DISPLAY REQUESTS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The DISPLAY REQUESTS command displays a list of request status information records from the PeopleSoft system that match the specified criteria.

## Command Line Syntax

The following figure illustrates the command line syntax of the DISPLAY REQUESTS command, using the command line, long form of its [configuration options](#).

```
-display prcs_findrequests
{
[-processinstancefromprocess_instance]
[-processinstancetoprocess_instance]
[-operatoridid]
[-processtypetype]
[-processname]
[-serverrunserver]
[-runstatusstatus]
[-distributionstatusstatus]
[-langcodecode]
[-filtervaluevalue-filterunit {All | Days | Hours | Minutes} | {[-fromDateyyyy-mm-dd] [-toDateyyyy-mm-dd]}]
[-processrequestcountcount]
[-outfmt {text | xml}]
}
```

## Command Argument

The DISPLAY REQUESTS command can be expressed as either:

- -D (Short form)
- -display (Long form)

The DISPLAY REQUESTS command argument, **prcs\_findrequests**, displays a list of request status information records from the PeopleSoft system that match the specified criteria.

## Configuration Options

The following table describes all DISPLAY REQUESTS configuration options and provides the command line, long form of each option illustrated in the [DISPLAY REQUESTS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PROCESS_INSTANCE_FROM</a>	-processinstancefrom	Starting (lower) process instance ID in a range of instance IDs to be displayed.
<a href="#">PROCESS_INSTANCE_TO</a>	-processinstanceto	Ending (upper) process instance ID in a range of instance IDs to be displayed.
<a href="#">OPERATOR_ID</a>	-operatorid	Filter requests by this operator ID.
<a href="#">PROCESS_TYPE</a>	-processtype	Filter requests by this process type.
<a href="#">PROCESS_NAME</a>	-processname	Filter requests by this process name.
<a href="#">SERVER_RUN</a>	-serverrun	Filter requests by this server name.
<a href="#">RUN_STATUS</a>	-runstatus	Filter requests by this run status.

DISTRIBUTION_STATUS	-distributionstatus	Filter requests by this distribution status.
LANGUAGE_CODE	-langcode	Filter requests by this language code.
FILTER_VALUE	-filtervalue	Integer value that will be interpreted in <b>FILTER_UNIT</b> units to provide a time range for filtering requests.
FILTER_UNIT	-filterunit	Unit used to interpret <b>FILTER_VALUE</b> to provide a time range for filtering requests.
FROM_DATE	-FromDate	Explicit <b>from</b> date in the form of yyyy-mm-dd.
TO_DATE	-ToDate	Explicit <b>from</b> date in the form of yyyy-mm-dd.
PROCESS_REQUEST_COUNT	- processrequestcount	Limit to the number of requests that will be returned.
OUTPUT_FORMAT	-outfmt	Format of the output for this command.

## Example

```

upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -display prcs_findrequests -operatorid PS1 -
runstatus Cancel
Process Instance.....: 140596
Process Name.....: CC_TEST
Process Type.....: PSJob
Job Name.....: CC_TEST
Run Control Id.....: ESS1A
Server Name Requested.....:
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.00.47.427040
Run Date Time.....: 2018-02-08-14.00.47.000000
Begin Date Time.....: 2018-02-08-14.00.54.203951
End Date Time.....: 2018-02-08-14.01.13.266331
Output Destination Format.: (None)
Output Destination Type...: NONE
Recurrence Name.....:
Run Status.....: Cancel
Distribution Status.....: N/A

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

```

# HOLD PROCESS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Configuration Options](#)
- [Example](#)

## Description

The HOLD PROCESS command places the specified process instance on hold in the PeopleSoft system.

## Command Line Syntax

The following figure illustrates the command line syntax of the HOLD PROCESS command, using the command line, long form of its [configuration options](#).

```
upps -hold -processinstance number
```

## Configuration Options

The following table describes all HOLD PROCESS configuration options and provides the command line, long form of each option illustrated in the [HOLD PROCESS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
PROCESS_INSTANCE	-processinstance	Process instance number identifying the process to be placed on hold.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -hold -processinstance 140601

UNV6838E SOAP fault: (SOAP-ENV:Server) null
UNV6812E Error performing SOAP request: PRQ_UPDATEREQUEST_REQ
UNV6826I Error updating process request:
UNV0152D 02DD-1 14:38:39,xpstcpip.c,298,connect,10035,'Resource temporarily unavailable.'
UNV6827I Unable to hold process instance 57966384

UNV6800E Universal Connector for PeopleSoft Process Scheduler ending unsuccessfully with exit code 202.
```



# START JOBSET - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Configuration Options](#)
- [Example](#)

## Description

The START JOBSET command starts a JobSet based on the settings defined in the Process Scheduler's Scheduled JobSet Definition component.

## Command Line Syntax

The following figure illustrates the command line syntax of the START JOBSET command, using the command line, long form of its [configuration options](#).

```


-start
-MainSchedName
name
-MainJobName
name
[
-wait
[
-poll
seconds]
[
-PrintJobTree
{yes | no}]
[
-PrintDistList
{yes | no}]
[
-PrintSystemMessage
{yes | no}]
[
-PrintApplicationMessage
{yes | no}]
[
-PrintParamList
{yes | no}]
[
-report
{yes | no}]
[
-cntfilter
filterList]
]

```

## Configuration Options

The following table describes all START JOB configuration options and provides the command line, long form of each option illustrated in the [START JOB command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">CNT_FILTER</a>	-cntfilter	Comma-delimited list of report file suffixes that will not be returned.
<a href="#">POLL</a>	-poll	Length of time to wait between status calls to the PeopleSoft system.
<a href="#">PRINT_APPLICATION_MESSAGE</a>	-printapplicationmessage	Specification for whether or not application messages are printed for the monitored processes when the work completes.

<a href="#">PRINT_DIST_LIST</a>	-printdistlist	Specification for whether or not to print the report-recipient distribution list for the monitored process when the work completes.
<a href="#">PRINT_JOB_TREE</a>	-printjobtree	Specification for whether or not to print the job tree when the monitored process completes.
<a href="#">PRINT_PARAM_LIST</a>	-printparamlist	Specification for whether or not the parameter list for job items are included in the report.
<a href="#">PRINT_SYSTEM_MESSAGE</a>	-printsystemmessage	Specification for whether or not system messages for the monitored processes when the work completes.
<a href="#">REPORT</a>	-Report	Specification for whether or not the reports associated with a process are returned.
<a href="#">WAIT for PROCESS</a>	-wait	<p>Specification that UPPS will monitor the specified process to completion.</p> <p>Note  In the <a href="#">START_JOBSET command line syntax</a>, the <a href="#">WAIT for PROCESS</a> (-wait) is a UPPS command used as a configuration option.</p>

## Example

```

upps
-userid
PS1
-pwd
PS1
-host
qapsft.stone.branch
-port
8000 -start
-mainschedname
ESSJS1
-mainjobname

```

```

ESSJ1
UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

UNV6817I Process status for ESSJ1/140604 is now queued.
UNV6817I Process status for ABS001/140605 is now queued.
UNV6817I Process status for ESSJ1/140604 is now processing.
UNV6817I Process status for ABS001/140605 is now success.
Process Instance.....: 140605
Process Name.....: ABS001
Process Type.....: SQR Report
Run Control Id.....: ESSRCID1
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.41.04.845735
Run Date Time.....: 2018-02-08-14.41.04.924835
Begin Date Time.....: 2018-02-08-14.41.21.000000
End Date Time.....: 2018-02-08-14.41.21.000000
Output Destination Format.: PDF
Output Destination Type...: WEB
Run Status.....: success
Distribution Status.....: n/a

UNV6817I Process status for ESSJ1/140604 is now success.
UNV6834I Distribution status for ESSJ1/140604 is now posting.
Process Instance.....: 140604
Process Name.....: ESSJ1
Process Type.....: PSJob
Run Control Id.....: ESSRCID1
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.41.04.845735
Run Date Time.....: 2018-02-08-14.41.04.924835
Begin Date Time.....: 2018-02-08-14.41.20.481711
End Date Time.....: 2018-02-08-14.41.35.582383
Output Destination Format.: (None)
Output Destination Type...: NONE
Run Status.....: success
Distribution Status.....: posting

UNV6834I Distribution status for ABS001/140605 is now posted.
Process Instance.....: 140605
Process Name.....: ABS001
Process Type.....: SQR Report
Run Control Id.....: ESSRCID1
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.41.04.845735
Run Date Time.....: 2018-02-08-14.41.04.924835
Begin Date Time.....: 2018-02-08-14.41.21.000000
End Date Time.....: 2018-02-08-14.41.35.530627
Output Destination Format.: PDF
Output Destination Type...: WEB
Run Status.....: success
Distribution Status.....: posted
Content Id.....: 29624
...

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

```

# SUBMIT PROCESS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Command Argument](#)
- [Configuration Options](#)
- [Example](#)

## Description

The SUBMIT PROCESS command submits a process, job, or jobset to the PeopleSoft Process Scheduler for execution.

## Command Line Syntax

The following figure illustrates the command line syntax of the SUBMIT PROCESS command, using the command line, long form of its [configuration options](#).

```
-sub
{
  {filename -deffmt {xml | upps} [-RunControlIdID] [-ProcessTypetype]} |
  {-RunControlIdID-ProcessTypetype} {-ProcessNamename | -JobNamename}}
  [-ServerName name]
  [-RunDateTime dateTime]
  [-TimeZone zone]
  [-RecurrenceName name]
  [-OutputDestinationType type]
  [-OutputDestinationFormat format]
  [-OutputDestinationString string]
  [-ReportFolderName name]
  [-ProcessFileName name]
  [-RetentionDays days]
}
[-wait [-poll seconds]
  [-PrintJobTree {yes | no}]
  [-PrintDistList {yes | no}]
  [-PrintSystemMessage {yes | no}]
  [-PrintApplicationMessage {yes | no}]
  [-PrintParamList {yes | no}]
  [-report {yes | no}]
  [-cntfilter filterList]
]
```

### Note



As the command line syntax illustrates, you can specify all of the options before the `-wait` on the command line to override values (if present) in the definition file.

## Command Argument

The SUBMIT PROCESS command can be expressed as either:

- `-U` (Short form)
- `-sub` (Long form)

The SUBMIT PROCESS command argument, `filename/ddname`, specifies the process, job, or jobset or submitted to the PeopleSoft Process Scheduler for execution.

## Configuration Options

The following table describes all SUBMIT PROCESS configuration options and provides the command line, long form of each option illustrated in the [SUBMIT PROCESS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
CNT_FILTER	-cntfilter	Comma-delimited list of report file suffixes that will not be returned.
DEFINITION_FILE_FORMAT	-deffmt	Format of the definition file.
JOB_NAME	-JobName	Name of the job being referenced by a command.
OUTPUT_DESTINATION_FORMAT	- OutputDestination Format	Override of the default output format for the submitted process.
OUTPUT_DESTINATION_STRING	- OutputDestination String	Override for the file path or printer destination for the output, if the output type for a submitted process is File or Printer.
OUTPUT_DESTINATION_TYPE	- OutputDestination Type	Type of output for a submitted process.
PROCESS_FILE_NAME	-ProcessFileName	Override for the dependent file name for the submitted process.
PROCESS_NAME	-ProcessName	Name of a PeopleSoft process for which parameter names will be returned.
PROCESS_TYPE	-ProcessType	Specific type of PeopleSoft process.
RECURRENCE_NAME	-RecurrenceName	Named recurrence definition to apply to the process submission.
REPORT	-Report	Specification for whether or not the reports associated with a process are returned.
REPORT_FOLDER_NAME	- ReportFolderName	Override for the folder name for the main job or process.
RETENTION_DAYS	-RetentionDays	Override for the retention days defined for a submitted process.
RUN_CONTROL_ID	-RunControlId	Run control ID to be used for the process submission.
RUN_DATE_TIME	-RunDateTime	Custom run date time for the submitted process.
SERVER_NAME	-ServerName	Specific server name for which constraints will be returned.
TIME_ZONE	-TimeZone	Time zone to use for the <a href="#">RUN_DATE_TIME</a> configuration option.
POLL	-poll	Length of time to wait between status calls to the PeopleSoft system.
PRINT_APPLICATION_MESSAGE	- printapplicationmessage	Specification for whether or not application messages are printed for the monitored processes when the work completes.
PRINT_DIST_LIST	-printdistlist	Specification for whether or not to print the report-recipient distribution list for the monitored process when the work completes.
PRINT_JOB_TREE	-printjobtree	Specification for whether or not to print the job tree when the monitored process completes.
PRINT_PARAM_LIST	-printparamlist	Specification for whether or not the parameter list for job items are included in the report.
PRINT_SYSTEM_MESSAGE	- printsystemmessage	Specification for whether or not system messages for the monitored processes when the work completes.
WAIT for PROCESS	-wait	Specification that UPPS will monitor the specified process to completion.  Note  In the <a href="#">SUBMIT_PROCESS</a> command line syntax, the <a href="#">WAIT for PROCESS</a> (-wait) is a UPPS command used as a configuration option.

## Example

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -sub .\TM_parms.txt -processname TREEMOVER -
runcontrolid ESS1A -processtype "Application Engine"
```

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 0.

```
upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -sub .\TM_parms.txt -processname TREEMOVER -
runcontrolid ESS1A -processtype "Application Engine" -wait
```

UNV6817I Process status for TREEMOVER/140607 is now queued.

UNV6817I Process status for TREEMOVER/140607 is now no success.

```
Process Instance.....: 140607
Process Name.....: TREEMOVER
Process Type.....: Application Engine
Run Control Id.....: ESS1A
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.44.14.514964
Run Date Time.....: 2018-02-08-14.44.14.000000
Begin Date Time.....: 2018-02-08-14.44.23.302174
End Date Time.....: 2018-02-08-14.44.23.500502
Output Destination Format.: TXT
Output Destination Type...: WEB
Run Status.....: no success
Distribution Status.....: n/a
```

UNV6834I Distribution status for TREEMOVER/140607 is now posted.

```
Process Instance.....: 140607
Process Name.....: TREEMOVER
Process Type.....: Application Engine
Run Control Id.....: ESS1A
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.44.14.514964
Run Date Time.....: 2018-02-08-14.44.14.000000
Begin Date Time.....: 2018-02-08-14.44.23.302174
End Date Time.....: 2018-02-08-14.44.38.407472
Output Destination Format.: TXT
Output Destination Type...: WEB
Run Status.....: no success
Distribution Status.....: posted
Content Id.....: 29626
```

```
*****
Report URL.....: http://qapsft.stone.branch:8000/psreports/ps/29626/AE_TREEMOVER_140607.stdout
Report Description.: Redirected Terminal Output
*****
PeopleTools 8.55.09 - Application Engine Server
Copyright (c) 1988-2018 Oracle and/or its affiliates.
All Rights Reserved
PSAESRV started service request at 14.44.23 2018-02-08
Begin: PeopleSoft TreeMover (125,2)
A file with the name ESS1A-TreeExpl already exists. Cannot overwrite. (125,498)
PeopleSoft TreeMover Completed Unsuccessfully. (125,5)
End: PeopleSoft TreeMover (125,3)
PeopleCode Exit(1) Abort invoked by Application at TREEMOVER.Export.Step01. (108,543)
Process 140607 ABENDED at Step TREEMOVER.Export.Step01 (PeopleCode) -- RC = ? (108,524)
Process %s ABENDED at Step %s.%s.%s (Action %s) -- RC = %s
PSAESRV completed service request at 14.44.23 2018-02-08
```

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 6.

# WAIT for PROCESS - UPPS Command

- [Description](#)
- [Command Line Syntax](#)
- [Configuration Options](#)
- [Example](#)

## Description

The WAIT for PROCESS command monitors a specified job, jobset, or process in the PeopleSoft system to completion.

Optionally, the various outputs associated with the monitored processes can be retrieved.

## Command Line Syntax

The following figure illustrates the command line syntax of the WAIT for PROCESS command, using the command line, long form of its [configuration options](#).

```
-wait -processinstance number
[-pollseconds][-printjobtree {yes | no}]
[-printdistlist {yes | no}]
[-printsystemmessage {yes | no}]
[-printapplicationmessage {yes | no}]
[-printparamlist {yes | no}]
[-report {yes | no}]
[-cntfilter filterList]
```

## Configuration Options

The following table describes all WAIT for PROCESS configuration options and provides the command line, long form of each option illustrated in the [WAIT for PROCESS command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">CNT_FILTER</a>	-cntfilter	Comma-delimited list of report file suffixes that will not be returned.
<a href="#">POLL</a>	-poll	Length of time to wait between status calls to the PeopleSoft system.
<a href="#">PRINT_JOB_TREE</a>	-printjobtree	Specification for whether or not to print the job tree when the monitored process completes.
<a href="#">PRINT_DIST_LIST</a>	-printdistlist	Specification for whether or not to print the report-recipient distribution list for the monitored process when the work completes.
<a href="#">PRINT_APPLICATION_MESSAGE</a>	-printapplicationmessage	Specification for whether or not application messages are printed for the monitored processes when the work completes.
<a href="#">PRINT_SYSTEM_MESSAGE</a>	-printsystemmessage	Specification for whether or not system messages for the monitored processes when the work completes.
<a href="#">PRINT_PARAM_LIST</a>	-printparamlist	Specification for whether or not the parameter list for job items are included in the report.
<a href="#">PROCESS_INSTANCE</a>	-processinstance	Process instance number for the job, jobset, or process.
<a href="#">REPORT</a>	-Report	Specification for whether or not the reports associated with a process are returned.

## Example



```

upps -userid PS1 -pwd PS1 -host qapsft.stone.branch -port 8000 -wait -processinstance 140608

UNV6817I Process status for TREEMOVER/140608 is now no success.
UNV6834I Distribution status for TREEMOVER/140608 is now posted.
Process Instance.....: 140608
Process Name.....: TREEMOVER
Process Type.....: Application Engine
Run Control Id.....: ESS1A
Server Name Run.....: PRCS1090
Operator Id.....: PS1
Request Date Time.....: 2018-02-08-14.46.26.623556
Run Date Time.....: 2018-02-08-14.46.26.000000
Begin Date Time.....: 2018-02-08-14.46.39.774941
End Date Time.....: 2018-02-08-14.46.54.970106
Output Destination Format.: TXT
Output Destination Type...: WEB
Run Status.....: no success
Distribution Status.....: posted
Content Id.....: 29627
*****
Report URL.....: http://qapsft.stone.branch:8000/psreports/ps/29627/AE_TREEMOVER_140608.stdout
Report Description.: Redirected Terminal Output
*****
PeopleTools 8.55.09 - Application Engine Server
Copyright (c) 1988-2018 Oracle and/or its affiliates.
All Rights Reserved
PSAESRV started service request at 14.46.39 2018-02-08
Begin: PeopleSoft TreeMover (125,2)
A file with the name ESS1A-TreeExp1 already exists. Cannot overwrite. (125,498)
PeopleSoft TreeMover Completed Unsuccessfully. (125,5)
End: PeopleSoft TreeMover (125,3)
PeopleCode Exit(1) Abort invoked by Application at TREEMOVER.Export.Step01. (108,543)
Process 140608 ABENDED at Step TREEMOVER.Export.Step01 (PeopleCode) -- RC = ? (108,524)
Process %s ABENDED at Step %s.%s.%s (Action %s) -- RC = %s
PSAESRV completed service request at 14.46.39 2018-02-08

UNV6830E Universal Connector for PeopleSoft Process Scheduler ending with exit code 6.

```

# Universal Connector for PeopleSoft Exit Codes

- [Overview](#)
- [WAIT Exit Codes](#)
- [All Other Command Exit Codes](#)

## Overview

The exit code of Universal Connector for PeopleSoft depends on the command being issued.

This page identifies the exit codes for the various Universal Connector for PeopleSoft commands.

## WAIT Exit Codes

If the WAIT command is specified, UPPS will return a value that indicates the state of the monitored process, job, or jobSet.

The following table lists the exit code value associated with the possible completion states.

Job Completion Status in PeopleSoft Process Scheduler	Exit Code
Error	8
No Success	6
Cancelled	4
Warning	2
Success	0
Error in UPPS processing (see <a href="#">#All Other Command Exit Codes</a> ).	> 200

## All Other Command Exit Codes

If UPPS is not performing the WAIT command, the exit code indicates the success of the requested actions.

The following table lists the UPPS exit codes.

Description	Exit Code
Successfully completed all requested actions.	0
General purpose return code indicating that an error level condition occurred in processing. Refer to messages written to standard error for details.	202
General purpose return code indicating that a fatal level condition occurred in processing. Refer to messages written to standard error for details.	203
Error in the configuration file or command options. Refer to the messages written to standard error for details.	220
Error initializing the message processing options	221

# Universal Connector for PeopleSoft Configuration Options for Program Execution

## Overview

Many configuration options of Universal Connector for PeopleSoft are associated with one or more specific Universal Connector for PeopleSoft [commands](#).

However, some configuration options are not associated with commands, but with program execution. Some of these options are required for every execution of Universal Connector for PeopleSoft; others are optional for any execution.

These options are categorized into logical areas of application, as shown in the following table.

The name of each category is a link to the following information:

- **Description:** Description of the options in the category.
- **Options syntax:** Syntax of the options on the command line.
- **Options:** Description of the configuration options in the category and a link to detailed information about those options.

### Note



For information on configuration options that are associated with one or more specific commands, see [Universal Connector for PeopleSoft Commands](#).

## Universal Connector for PeopleSoft Configuration Options for Program Execution - Categories

Option Categories	Description
<b>Required</b>	
<a href="#">HOST Options</a>	Specifies the PeopleSoft host to which a connection should be made.
<a href="#">USER Options</a>	Identifies the PeopleSoft user account with which the command executes.
<b>Optional</b>	
<a href="#">COMMAND FILE Options</a>	Specifies an additional source of command options.
<a href="#">INFORMATIONAL Options</a>	Requests information pertaining to the PeopleSoft program.
<a href="#">INSTALLATION Options</a>	Specifies UPPS options required for installation (Windows and UNIX).
<a href="#">LOCAL Options</a>	Specifies UPPS options required for local broker registration.
<a href="#">MESSAGE Options</a>	Requests information pertaining to the UPPS program.
<a href="#">SSL Options</a>	Configures the environment and behavior of HTTPS connections with the PeopleSoft system.

# HOST Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [HOST Options List](#)

## Description

The HOST configuration options are required to establish connections and consume web services on a PeopleSoft system.

## Command Line Syntax

The following figure illustrates the command line syntax of the [HOST options](#), using their command line, long form.

```
-host host [-port port] -psendpoint endpoint
```

## HOST Options List

The following table describes all HOST configuration options and provides the command line, long form of each option illustrated in the [HOST options command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">HOST</a>	-host	Host name of a PeopleSoft application server.
<a href="#">PORT</a>	-port	Port number for the PeopleSoft application server.
<a href="#">ENDPOINT</a>	-psendpoint	Web Service endpoint for the PROCESSREQUEST service.

# USER Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [USER Options List](#)

## Description

The USER options are required to establish an RFC connection to a PeopleSoft system. They establish the PeopleSoft user identity.

## Command Line Syntax

The following figure illustrates the command line syntax of the [USER options](#), using their command line, long form.

```
-useriduserid-pwdpassword
```

## USER Options List

The following table describes all USER options and provides the command line, long form of each option illustrated in the USER options [command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">PASSWORD</a>	-pwd	Password for the PeopleSoft user ID.
<a href="#">USER_ID</a>	-userid	PeopleSoft user ID with which to logon to the PeopleSoft system.

# COMMAND FILE Options - Universal Connector for PeopleSoft

- [Description](#)
- [Plain Text File](#)
  - [Command Line Syntax \(Plain Text Options\)](#)
  - [COMMAND FILE \(Plain Text\) Options List](#)
- [Encrypted File](#)
  - [Command Line Syntax \(Encrypted Options\)](#)
  - [COMMAND FILE \(Encrypted\) Options List](#)

## Description

The COMMAND FILE options are used to specify a file as a source of configuration options used for a command execution. The options read from a command file are processed exactly like options from any other input source.

Encrypted command files are an excellent place to store sensitive data such as user IDs and passwords. Use the [Universal Encrypt](#) utility to encrypt a plain text command file.

### Note

All options, including required and command-specific options, can be placed in a command file.

Universal Connector for PeopleSoft can process both plain text and encrypted command files. Either type of file can be used, but not both. If both are specified, the plain text file will be used.

## Plain Text File

### Command Line Syntax (Plain Text Options)

The following figure illustrates the command line syntax of the [COMMAND FILE \(Plain Text\) options](#), using their command line, long form.

```
-file [filename]
```

### COMMAND FILE (Plain Text) Options List

The following table describes all COMMAND FILE (Plain Text) options and provides the command line, long form of each option illustrated in the [COMMAND FILE \(Plain Text\) options command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">FILE_NAME</a>	-file	Name of a plain text command file.

## Encrypted File

### Command Line Syntax (Encrypted Options)

The following figure illustrates the command line syntax of the [COMMAND FILE \(Encrypted\) options](#), using their command line, long form.

```
-encryptedfile [filename [-keykey] ]
```

### COMMAND FILE (Encrypted) Options List

The following table describes all COMMAND FILE (Encrypted) options and provides the command line, long form of each option illustrated in the COMMAND FILE (Encrypted) options [command line syntax](#), above.

<b>Configuration Option Name</b>	<b>Command Line Long Form</b>	<b>Description</b>
<a href="#">ENCRYPT_FILE</a>	-encryptedfile	Name of an encrypted command file.
<a href="#">ENCRYPTION_KEY</a>	-key	Key used to encrypt the command file.

# INFORMATIONAL Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [INFORMATIONAL Options List](#)

## Description

The INFORMATIONAL options request information pertaining to the PeopleSoft program.

## Command Line Syntax

The following figure illustrates the command line syntax of the [INFORMATIONAL options](#), using their command line, long form.

```
-help-version
```

## INFORMATIONAL Options List

The following table describes all INFORMATIONAL options and provides the command line, long form of each option illustrated in the INFORMATIONAL options [command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">HELP</a>	-help	Writes command line help.
<a href="#">VERSION</a>	-version	Writes UPPS version and copyright information.



# INSTALLATION Options - Universal Connector for PeopleSoft

- [Description](#)
- [Configuration File Syntax](#)
- [INSTALLATION Options List](#)

## Description

The INSTALLATION options are required for product installation.

Note



INSTALLATION options can be specified only in the configuration file. They have no command line or environment variable parameters.

## Configuration File Syntax

The following figure illustrates the configuration file syntax of the [INSTALLATION options](#).

```
installation_directorydirectory
```

## INSTALLATION Options List

The following table describes all INSTALLATION options and provides the configuration file format of each option illustrated in the [INSTALLATION options configuration file syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">INSTALLATION_DIRECTORY</a>	installation_directory	Location in which UPPS is installed.

# LOCAL Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [LOCAL Options List](#)

## Description

The LOCAL options are required for local broker registration.

## Command Line Syntax

The following table illustrates the command line syntax of the [LOCAL options](#), using their command line, long form.

```
-bif_directorydirectory-plf_directorydirectory
```

## LOCAL Options List

The following table describes all LOCAL options and provides the command line, long form of each option illustrated in the LOCAL options [command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">BIF_DIRECTORY</a>	-bif_directory	For UNIX only: Broker Interface File (BIF) directory where the Universal Broker interface file is located.
<a href="#">PLF_DIRECTORY</a>	-plf_directory	For UNIX only: Program Lock File (PLF) directory where the program lock files are located.

# MESSAGE Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [MESSAGE Options List](#)

## Description

The MESSAGE options specify different characteristics of Universal Connector for PeopleSoft messages.

## Command Line Syntax

The following table illustrates the command line syntax of the [MESSAGE options](#), using their command line, long form.

```
-lang language -level {trace|audit|info|warn|error}
-trace_file_lines lines -trace_table size, condition
```

## MESSAGE Options List

The following table describes all MESSAGE options and provides the command line, long form of each option illustrated in the MESSAGE options [command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">MESSAGE_LANGUAGE</a>	-lang	Language in which messages are written.
<a href="#">MESSAGE_LEVEL</a>	-level	Level of messages to be written.
<a href="#">TRACE_FILE_LINES</a>	-trace_file_lines	Maximum number of lines to write to the trace file.
<a href="#">TRACE_TABLE</a>	-trace_table	Trace table size and under what conditions it is written to a file.

# SSL Options - Universal Connector for PeopleSoft

- [Description](#)
- [Command Line Syntax](#)
- [SSL Options List](#)

## Description

The SSL options are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. The SSL configuration options can be used with any command, but they only impact HTTPS connections.

## Command Line Syntax

The following figure illustrates the command line syntax of the [SSL options](#), using their command line, long form.

```
{-ssl_cipher_listlist [-ca_certsfile] [-certfile] [-daysnumber] [-private_keyfile [-private_key_pwdpassword]] [-verify_host_nameoption] [-verify_peeroption]}
```

## SSL Options List

The following table describes all SSL configuration options and provides the command line, long form of each option illustrated in the [SSL options command line syntax](#), above.

Configuration Option Name	Command Line Long Form	Description
<a href="#">SSL_CIPHER_LIST</a>	-ssl_cipher_list	SSL cipher suites acceptable for use by the SSL protocol.
<a href="#">CERTIFICATE</a>	-cert	File name of the PEM-formatted <a href="#">X.509 certificate</a> that identifies Universal Connector for PeopleSoft.
<a href="#">CERTIFICATE_EXPIRATION_NOTICE</a>	-days	number of days prior to certificate expiration to begin issuing informational messages about the expiration.
<a href="#">CA_CERTIFICATES</a>	-ca_certs	Location of the PEM-formatted trusted Certificate Authority (CA) <a href="#">X.509 certificates</a> file.
<a href="#">PRIVATE_KEY</a>	-port	Path of the UPPS PEM-formatted RSA private key.
<a href="#">PRIVATE_KEY_PWD</a>	-port	Password for the UPPS <a href="#">PRIVATE_KEY</a> .
<a href="#">VERIFY_HOST_NAME</a>	-verify_host_name	Specification for whether or not the server's <a href="#">X.509 certificate</a> host name field must be verified.
<a href="#">VERIFY_PEER</a>	-verify_peer	Specification for whether or not the server's <a href="#">X.509 certificate</a> is verified.

# Universal Connector for PeopleSoft Configuration Options

- [Overview](#)
- [Configuration Options Information](#)
  - [Description](#)
  - [Usage](#)
  - [Values](#)
  - [<Additional Information>](#)
  - [Command Usage](#)
- [Configuration Options List](#)

## Overview

This page provides links to detailed information for all configuration options of Universal Connector for PeopleSoft.

The options are listed alphabetically, without regard to any specific operating system.

## Configuration Options Information

For each configuration option, these pages provides the following information.

### Description

Describes the configuration option and how it is used.

### Usage

Provides a table of the following information:

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<Format / Value>					
Command Line, Long Form	<Format / Value>					
Environment Variable	<Format / Value>					
Configuration File Keyword	<Format / Value>					

### Method

Identifies the different methods used to specify Universal Connector configuration options:

- Command Line Option, Short Form
- Command Line Option, Long Form
- Environment Variable
- Configuration File Keyword

Note



Each option can be specified using one or more methods.

### Syntax

Identifies the syntax of each method that can be used to specify the option:

- Format: Specific characters that identify the option.
- Value: Type of value(s) to be supplied for this method.

Note



If a Method is not valid for specifying the option, the Syntax field contains **n/a**.

### (Operating System)

Identifies the operating systems for which each method of specifying the option is valid:

- IBM i
- HP NonStop
- UNIX
- Windows
- z/OS

## Values

Identifies all possible values for the specified value type.

Defaults are identified in **bold type**.

## <Additional Information>

Identifies any additional information specific to the option.

## Command Usage

Provides links to the Universal Connector commands that use the option.

If the option is associated with program execution, not commands, this section provides a link to the appropriate option category in [Universal Connector for PeopleSoft Configuration Options for Program Execution](#).

# Configuration Options List

The following table identifies all Universal Connector configuration options.

Option	Description
<a href="#">BIF_DIRECTORY</a>	Broker Interface Directory that specifies the location of the Universal Broker interface file.
<a href="#">CA_CERTIFICATES</a>	Location of the PEM-formatted trusted Certificate Authority (CA) X.509 certificates file.
<a href="#">CERTIFICATE</a>	File name of the PEM-formatted <a href="#">X.509 certificate</a> that identifies Universal Connector for PeopleSoft.
<a href="#">CERTIFICATE_EXPIRATION_NOTICE</a>	Number of days prior to certificate expiration to begin issuing informational messages about the expiration.
<a href="#">CNT_FILTER</a>	Comma-delimited list of report file suffixes that will not be returned.
<a href="#">CONTENT_ID</a>	Content ID that identifies the report to be returned from the report repository.
<a href="#">DEFINITION_FILE_FORMAT</a>	Format of the definition file.
<a href="#">DISTRIBUTION_STATUS</a>	Distribution status by requests are filtered.
<a href="#">ENCRYPT_FILE</a>	Name of an encrypted text command file.
<a href="#">ENCRYPTION_KEY</a>	Key used to encrypt the command file.
<a href="#">ENDPOINT</a>	Web Service endpoint for the PROCESSREQUEST service.
<a href="#">FILE_NAME</a>	Name of a plain text command file.
<a href="#">FILTER_UNIT</a>	Unit used to interpret FILTER_VALUE configuration option to provide a time range for filtering requests.
<a href="#">FILTER_VALUE</a>	Integer value that will be interpreted in FILTER_UNIT configuration option units to provide a time range for filtering requests.
<a href="#">FROM_DATE</a>	Explicit <b>from</b> date in the form of yyyy-mm-dd.
<a href="#">HELP</a>	Displays a description of command line options and their format.
<a href="#">HOST</a>	Host name of a PeopleSoft application server.
<a href="#">INSTALLATION_DIRECTORY</a>	Location in which UPPS is installed.
<a href="#">ITEM_INSTANCE</a>	Instance number of a scheduled job or jobset.
<a href="#">JOB_NAME</a>	Name of the job being referenced by a command.

LANGUAGE_CODE	Filter requests by language code.
MAIN_JOB_NAME	Filter requests by language code.
MAIN_SCHED_NAME	Name of the jobset schedule.
MESSAGE_LANGUAGE	Language in which messages are written.
MESSAGE_LEVEL	Level of messages to written.
OPERATOR_ID	Filter requests by this operator ID.
OUTPUT_DESTINATION_FORMAT	Override of the default output format for the submitted process.
OUTPUT_DESTINATION_STRING	Override for the file path or printer destination for the output, if the output type for a submitted process is File or Printer.
OUTPUT_DESTINATION_TYPE	Type of output for a submitted process.
OUTPUT_FORMAT	Format of the output from a PeopleSoft process.
PASSWORD	Password for the PeopleSoft user ID.
PLF_DIRECTORY	Program Lock File directory that specifies the location of the UPPS program lock file.
POLL	Length of time to wait between status calls to the PeopleSoft system.
PORT	Port number for the PeopleSoft application server.
PRINT_APPLICATION_MESSAGE	Specification for whether or not the application messages for the monitored processes are included in the Job Report.
PRINT_DISTRIBUTION_LIST	Specification for whether or not the report-recipient distribution list is included in the Job Report.
PRINT_JOB_TREE	Specification for whether or not the job tree is included in the Job Report.
PRINT_MESSAGE_LIST	Specification for whether or not the messages that will be emailed upon completion of a job item are included in the report.
PRINT_NOTIFY_LIST	Specification for whether or not the job notify list is included in the report.
PRINT_PARAMETER_LIST	Specification for whether or not the parameter list job items are included in the Job Report.
PRINT_SYSTEM_MESSAGE	Specification for whether or not to print the system messages for the monitored processes are included in the Job Report.
PRIVATE_KEY	Path of the Universal Connector for PeopleSoft PEM-formatted RSA private key.
PRIVATE_KEY_PWD	Password for the Universal Connector for PeopleSoft PEM-formatted RSA <a href="#">PRIVATE_KEY</a> .
PROCESS_INSTANCE	PeopleSoft process instance number identifying the request to be returned.
PROCESS_INSTANCE_FROM	Starting (lower) process instance ID in a range of instance IDs to be displayed.
PROCESS_INSTANCE_TO	Ending (upper) process instance ID in a range of instance IDs to be displayed.
PROCESS_FILE_NAME	Override for the dependent file name for the submitted process.
PROCESS_NAME	Name of a PeopleSoft process for which parameter names will be returned.
PROCESS_REQUEST_COUNT	Limit of the number of requests that will be returned.
PROCESS_TYPE	Specific type of PeopleSoft process.
PROMPT	Type of prompt values in the PeopleSoft system that will be displayed by the <a href="#">DISPLAY PRCS PROMPT</a> command.
RECURRENCE_NAME	Named recurrence definition to apply to the process submission.
REPORT	Specification for whether or not the reports associated with a process are returned.
REPORT_FOLDER_NAME	Override for the folder name for the main job or process.
RETENTION_DAYS	Override for the retention days defined for a submitted process.
RUN_CONTROL_ID	Run control ID to be used for the process submission.
RUN_DATE_TIME	Custom run date time for the submitted process.
RUN_STATUS	Specification to filter requests by run status.
SERVER_NAME	Specific server name for which constraints will be returned.

<a href="#">SERVER_RUN</a>	Specification to filter requests by this server name.
<a href="#">SSL_CIPHER_LIST</a>	SL cipher suites acceptable for use by the SSL protocol.
<a href="#">TIME_ZONE</a>	Time zone to use for the <a href="#">RUN_DATE_TIME</a> configuration option.
<a href="#">TO_DATE</a>	Latest date to use for job selection or syslog request.
<a href="#">TRACE_FILE_LINES</a>	Maximum number of lines to write to the trace file.
<a href="#">TRACE_TABLE</a>	Trace table size and under what conditions it is written to a file.
<a href="#">USER_ID</a>	PeopleSoft user ID with which to logon to the PeopleSoft system.
<a href="#">VERIFY_HOST_NAME</a>	Specification for whether or not the server's <a href="#">X.509 certificate</a> host name field must be verified.
<a href="#">VERIFY_PEER</a>	Specification for whether or not the authenticity of the PeopleSoft server's <a href="#">X.509 certificate</a> is verified.
<a href="#">VERSION</a>	Writes UPPS version and copyright information.



# BIF\_DIRECTORY - UPPS configuration option

## Description

The BIF\_DIRECTORY option specifies the Broker Interface File (BIF) directory where the Universal Broker interface file, **ubroker.bif**, is located.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-bif_directory <i>directory</i>			✓		
Environment Variable	UPPSBIFDIRECTORY= <i>directory</i>			✓		
Configuration File Keyword	n/a					

## Values

*directory* is the name of the BIF directory.

**Default** = `/var/opt/universal`.

## Command Usage

The BIF\_DIRECTORY option is a [LOCAL](#) option.

LOCAL options are associated with program execution, not commands. They are required for local broker registration.

# CA\_CERTIFICATES - UPPS configuration option

## Description

The CA\_CERTIFICATES option specifies the location of the PEM-formatted trusted Certificate Authority (CA) X.509 certificates file.

Trust CA certificates are required if peer authentication is desired.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ca_certs <i>file</i>			✓	✓	
Environment Variable	UPPSCACERTS= <i>file</i>			✓	✓	
Configuration File Keyword	ca_certificates <i>file</i>			✓	✓	

## Values

<b>UNIX</b>	<i>file</i> is the path name of the X.509 certificates file. Relative paths are relative to the current working directory.
<b>Windows</b>	<i>file</i> is the path name of the X.509 certificates file. Relative paths are relative to the current working directory.

## Command Usage

The CA\_CERTIFICATES option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# CERTIFICATE - UPPS configuration option

## Description

The CERTIFICATE option specifies the file name of the PEM-formatted [X.509 certificate](#) that identifies Universal Connector for PeopleSoft.

A UPPS X.509 certificate is required if the Universal Broker requires client authentication.

Note



If the CERTIFICATE option is used, the [PRIVATE\\_KEY](#) option is required.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cert <i>file</i>			✓	✓	
Environment Variable	UPPSCERT= <i>file</i>			✓	✓	
Configuration File Keyword	certificate <i>file</i>			✓	✓	

## Values

<b>UNIX</b>	<i>file</i> is the path name of the X.509 certificate file. Relative paths are relative to the current working directory.
<b>Windows</b>	<i>file</i> is the path name of the X.509 certificate file. Relative paths are relative to the current working directory.

## Command Usage

The CERTIFICATE option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# CERTIFICATE\_EXPIRATION\_NOTICE - UPPS configuration option

## Description

The CERTIFICATE\_EXPIRATION\_NOTICE option specifies the number of days prior to certificate expiration to begin issuing informational messages about the expiration.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-days <i>number</i>			✓	✓	
Environment Variable	UPPSDAYSTILEXPIRE= <i>number</i>			✓	✓	
Configuration File Keyword	days_til_expire <i>number</i>			✓	✓	

## Values

*number* is the number of days prior to certificate expiration to begin issuing informational messages about the expiration.

**Default is 15.**

## Command Usage

The CERTIFICATE\_EXPIRATION\_NOTICE option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# CNT\_FILTER - UPPS configuration option

## Description

The CNT\_FILTER option specifies a comma-delimited list of report file suffixes that will not be returned.

CNT\_FILTER is used to filter out types of reports from being returned for a process.

For example, it can be used to prevent PDF and/or XLS reports from being returned: `-cntfilter pdf,xls`

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	<code>-cntfilter list</code>			✓	✓	
Environment Variable	<code>UPPSCNTFILTER=list</code>			✓	✓	
Configuration File Keyword	<code>content_filter list</code>			✓	✓	

## Value

*filterList* is a comma-delimited list of report file suffixes that will not be returned.

For example: `pdf,xls`

**Default is pdf.**

## Command Usage

The CNT\_FILTER option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# CONTENT\_ID - UPPS configuration option

## Description

The CONTENT\_ID option specifies the content ID that identifies the report to be returned from the report repository.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-contentid <i>ID</i>			✓	✓	
Environment Variable	UPPS_CONTENTID= <i>ID</i>			✓	✓	
Configuration File Keyword	contentid <i>ID</i>			✓	✓	

## Value

*ID* is the ID that identifies the report to be returned from the report repository

## Command Usage

The CONTENT\_ID option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY PRCS GET REPORT](#)

# DEFINITION\_FILE\_FORMAT - UPPS configuration option

## Description

The DEFINITION\_FILE\_FORMAT option specifies the format of the definition file.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-deffmt <i>format</i>			✓	✓	
Environment Variable	UPPSDEFFMT= <i>format</i>			✓	✓	
Configuration File Keyword	deffmt <i>format</i>			✓	✓	

## Value

*format* is the format of the definition file.

Valid values:

- **xml**  
Definition file contains XML that describes the request.
- **upps**  
Definition file contains a UPPS script that describes the request.

## Command Usage

The DEFINITION\_FILE\_FORMAT option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# DISTRIBUTION\_STATUS - UPPS configuration option

## Description

The DISTRIBUTION\_STATUS option specifies filter requests by distribution status.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-distributionstatus <i>status</i>			✓	✓	
Environment Variable	UPPS_DISTRIBUTIONSTATUS= <i>status</i>			✓	✓	
Configuration File Keyword	distributionstatus <i>status</i>			✓	✓	

## Value

*status* is the distribution status by which you want to filter requests.

## Command Usage

The DISTRIBUTION\_STATUS option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)



# ENCRYPT\_FILE - UPPS configuration option

## Description

The ENCRYPT\_FILE option specifies the file name of an encrypted text command file.

If ENCRYPT\_FILE does not specify a file name, the command file is read from stdin.

### Note



If both the ENCRYPT\_FILE and FILE\_NAME options are used, ENCRYPT\_FILE is ignored.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-x <i>name</i>			✓	✓	
Command Line, Long Form	-encryptedfile <i>name</i>			✓	✓	
Environment Variable	UPPSENCRYPTEDFILE= <i>name</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is the name (ddname for z/OS) of the encrypted text command file.

## Command Usage

The ENCRYPT\_FILE option is a [COMMAND FILE](#) option.

COMMAND FILE options are associated with program execution, not commands. They are used to specify a file as a source of configuration options used for a command execution.

# ENCRYPTION\_KEY - UPPS configuration option

## Description

The ENCRYPTION\_KEY option specifies the key used to encrypt the command file.

This key acts much like a password for the encrypted command file. If a key was used to encrypt a command file (when Universal Encrypt was run), that same key must be specified to decrypt the file; otherwise, the decryption will fail.

If no key is specified, a default value is provided.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-K <i>key</i>			✓	✓	
Command Line, Long Form	-key <i>key</i>			✓	✓	
Environment Variable	n/a					
Configuration File Keyword	n/a					

## Value

*key* is the name of the key used to encrypt the command file.

## Command Usage

The ENCRYPTION\_KEY option is a [COMMAND FILE](#) option.

COMMAND FILE options are associated with program execution, not commands. They are used to specify a file as a source of configuration options used for a command execution.

# ENDPOINT - UPPS configuration option

## Description

The ENDPOINT option specifies the Web Service endpoint for the PROCESSREQUEST service.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-psendpoint <i>URL</i>			✓	✓	
Environment Variable	UPPSENDPOINT <i>URL</i>			✓	✓	
Configuration File Keyword	peoplesoftendpoint <i>URL</i>			✓	✓	

## Value

*URL* is the web address of a PeopleSoft application server.

## Example

-psendpoint [https://qapsft.stone.branch:8443/PSIGW/PeopleSoftServiceListeningConnector/PSFT\\_HR](https://qapsft.stone.branch:8443/PSIGW/PeopleSoftServiceListeningConnector/PSFT_HR)

## Command Usage

The ENDPOINT option is a **HOST** option.

HOST options are associated with program execution, not commands. They are required to establish a connection with a PeopleSoft system.

# FILE\_NAME - UPPS configuration option

## Description

The FILE\_NAME option specifies the file name of a plain text command file.

If FILE\_NAME does not specify a file name, the command file is read from stdin.

### Note



If both the FILE\_NAME and ENCRYPT\_FILE options are used, ENCRYPT\_FILE is ignored.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-f <i>name</i>			✓	✓	
Command Line, Long Form	-file <i>name</i>			✓	✓	
Environment Variable	UPPSFILE= <i>name</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is the name of the plain text command file.

## Command Usage

The FILE\_NAME option is a [COMMAND FILE](#) option.

COMMAND FILE options are associated with program execution, not commands. They are used to specify a file as a source of configuration options used for a command execution.

# FILTER\_UNIT - UPPS configuration option

## Description

The FILTER\_UNIT option specifies the unit used to interpret [FILTER\\_VALUE](#) configuration option to provide a time range for filtering requests.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-filterunit <i>unit</i>			✓	✓	
Environment Variable	UPPSFILTERUNIT= <i>unit</i>			✓	✓	
Configuration File Keyword	filterunit <i>unit</i>			✓	✓	

## Value

*unit* is the integer value that will be interpreted in [FILTER\\_VALUE](#) configuration option units to provide a time range for filtering requests.

Valid values:

- All: Requests will not be filtered by date.
- Days: Specifies a time range filter for the last [FILTER\\_VALUE](#) days.
- Hours: Specifies a time range filter for the last [FILTER\\_VALUE](#) hours.
- Minutes: Specifies a time range filter for the last [FILTER\\_VALUE](#) minutes.

## Command Usage

The FILTER\_UNIT option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# FILTER\_VALUE - UPPS configuration option

## Description

The FILTER\_VALUE option specifies an integer value that will be interpreted in [FILTER\\_UNIT](#) configuration option units to provide a time range for filtering requests.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-filtervalue <i>value</i>			✓	✓	
Environment Variable	UPPSFILTERVALUE= <i>code</i>			✓	✓	
Configuration File Keyword	filtervalue <i>value</i>			✓	✓	

## Value

*value* is the integer value that will be interpreted in [FILTER\\_UNIT](#) configuration option units to provide a time range for filtering requests.

## Command Usage

The FILTER\_VALUE option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# FROM\_DATE - UPPS configuration option

## Description

The FROM\_DATE option specifies an explicit **from** date in the form of yyyy-mm-dd.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-fromdate <i>date</i>			✓	✓	✓
Environment Variable	UPPSFROMDATE= <i>date</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*date* is the earliest date to use for job selection or syslog request.

The format of *date* is:

YYYY/MM/DD

## Command Usage

The FROM\_DATE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY REQUESTS](#)

# HELP - UPPS configuration option

## Description

The HELP option displays a description of the Universal Connector for PeopleSoft command line options and their format.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-h			✓	✓	
Command Line, Long Form	-help			✓	✓	
Environment Variable	n/a					
Configuration File Keyword	n/a					

## Value

(There are no values required for this option.)

## Command Usage

The HELP option is an [INFORMATIONAL](#) option.

INFORMATIONAL options are associated with program execution, not commands. They request information pertaining to the UPPS program.



# HOST - UPPS configuration option

## Description

The HOST option specifies the host name of a PeopleSoft application server.

HOST, in conjunction with the [PORT](#) option, is used to define a connection to a PeopleSoft system.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<i>i hostname</i>					
Command Line, Long Form	-host <i>hostname</i>			✓	✓	
Environment Variable	UPPSHOST= <i>hostname</i>			✓	✓	
Configuration File Keyword	host <i>hostname</i>			✓	✓	

## Value

*hostname* is the host name of a PeopleSoft application server.

## Example

```
-host " qapsft.stone.branch "
```

### Note



The space following the opening quotation mark for the -host value is required for Universal Connector for PeopleSoft to properly parse a typical -host value.

## Command Usage

The HOST option is a [HOST](#) option.

HOST options are associated with program execution, not commands. They are required to establish a connection with a PeopleSoft system.

# INSTALLATION\_DIRECTORY - UPPS configuration option

## Description

The INSTALLATION\_DIRECTORY option specifies the location in which Universal Connector for PeopleSoft is installed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	n/a					
Environment Variable	n/a					
Configuration File Keyword	installation_directory <i>directory</i>			✓	✓	

## Values

*directory* is the path name for the Universal Connector for PeopleSoft installation file.

## Defaults

<b>UNIX</b>	/opt/universal/upps
<b>Windows 64-bit install</b>	C:\Program Files\Universal\UagSrv

## Command Usage

The INSTALLATION\_DIRECTORY option is an [INSTALLATION](#) option.

INSTALLATION options are associated with program execution, not commands. They are required for product installation.

# ITEM\_INSTANCE - UPPS configuration option

## Description

The ITEM\_INSTANCE option specifies the instance number of a scheduled job or jobset.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-iteminstance <i>number</i>			✓	✓	
Environment Variable	UPPSITEMINSTANCE= <i>number</i>			✓	✓	
Configuration File Keyword	iteminstance <i>number</i>			✓	✓	

## Value

*number* is the instance number of the scheduled job or jobset.

## Command Usage

The ITEM\_INSTANCE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)

# JOB\_NAME - UPPS configuration option

## Description

The JOB\_NAME option specifies the name of the job being referenced by a command.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-JobName <i>name</i>			✓	✓	
Environment Variable	UPPS_JOBNAME= <i>option</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is the job name being referenced by the command.

## Command Usage

The JOB\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PARAMS](#)
- [DISPLAY PRCS PRINT JOB HTML REPORT](#)
- [SUBMIT PROCESS](#)

# LANGUAGE\_CODE - UPPS configuration option

## Description

The LANGUAGE\_CODE option specifies filter requests by language code.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-langcode <i>code</i>			✓	✓	
Environment Variable	UPPSLANGCODE= <i>code</i>			✓	✓	
Configuration File Keyword	langcode <i>code</i>			✓	✓	

## Value

*code* is the language code by which you want to filter requests.

## Command Usage

The LANGUAGE\_CODE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY OUTPUT FORMATS](#)
- [DISPLAY OUTPUT TYPES](#)
- [DISPLAY REQUESTS](#)

# MAIN\_JOB\_NAME - UPPS configuration option

## Description

The MAIN\_JOB\_NAME option specifies the name of the job within the jobset schedule.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-mainjobname <i>name</i>			✓	✓	
Environment Variable	UPPSMAINJOBNAME= <i>name</i>			✓	✓	
Configuration File Keyword	mainjobname <i>name</i>			✓	✓	

## Value

*name* is the name of the job within the jobset schedule.

## Command Usage

The MAIN\_JOB\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT SCHED HTML REPORT](#)

# MAIN\_SCHED\_NAME - UPPS configuration option

## Description

The MAIN\_SCHED\_NAME option specifies the name of the jobset schedule.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-mainschedname <i>name</i>			✓	✓	
Environment Variable	UPPSMAINSCHEDNAME= <i>name</i>			✓	✓	
Configuration File Keyword	mainschedname <i>name</i>			✓	✓	

## Value

*name* is the name of the jobset schedule.

## Command Usage

The MAIN\_SCHED\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT SCHED HTML REPORT](#)

# MESSAGE\_LANGUAGE - UPPS configuration option

## Description

The MESSAGE\_LANGUAGE option specifies the language in which messages are written.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-L <i>language</i>			✓	✓	
Command Line, Long Form	-lang <i>language</i>			✓	✓	
Environment Variable	UPPSLANG= <i>language</i>			✓	✓	
Configuration File Keyword	language <i>language</i>			✓	✓	

## Value

*language* is the language in which messages are written.

The first three characters of the language are used as a three-character suffix to form the name of a Universal Message Catalog (UMC) file. UMC files are in the **nls** product directory.

**Default is ENGLISH.**

## Command Usage

The MESSAGE\_LANGUAGE option is a [MESSAGE](#) option.

MESSAGE options are associated with program execution, not commands. They specify different characteristics of **upps** messages.



# MESSAGE\_LEVEL - UPPS configuration option

## Description

The MESSAGE\_LEVEL option specifies level of messages to write.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-l <i>level</i>			✓	✓	
Command Line, Long Form	-level <i>level</i>			✓	✓	
Environment Variable	UPPSLEVEL= <i>level</i>			✓	✓	
Configuration File Keyword	message_level <i>level</i>			✓	✓	

## Value

*level* is the level of messages to write.

Valid values for level are:

- **trace**  
Activates tracing and generates a trace file to which UPPS writes trace messages used for debugging.

Note



Use **trace** only as directed by Stonebranch, Inc. Customer Support.

- **audit**  
Issues audit, informational, warning, and error messages.
- **info**  
Issues informational, warning, and error messages.
- **warn**  
Issues warning and error messages.
- **error**  
Issues error messages only.

## Default

<b>UNIX</b>	Default is <b>warn</b> .
<b>Windows</b>	Default is <b>warn</b> .

## Command Usage

The MESSAGE\_LEVEL option is a [MESSAGE](#) option.

MESSAGE options are associated with program execution, not commands. They specify different characteristics of **upps** messages.

# OPERATOR\_ID - UPPS configuration option

## Description

The OPERATOR\_ID option specifies filter requests by this operator ID.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-operatorid <i>ID</i>			✓	✓	
Environment Variable	UPPSOPERATORID= <i>ID</i>			✓	✓	
Configuration File Keyword	operatorid <i>ID</i>			✓	✓	

## Value

*ID* is the operator ID by which you want to filter requests.

## Command Usage

The OPERATOR\_ID option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# OUTPUT\_DESTINATION\_FORMAT - UPPS configuration option

## Description

The OUTPUT\_DESTINATION\_FORMAT option specifies an override of the default output format for the submitted process.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-OutputDestinationFormat <i>format</i>			✓	✓	
Environment Variable	UPPS_OUTPUTDESTINATIONFORMAT= <i>option</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*format* is the output format for a submitted process.

For valid values, refer to Oracle documentation for the PeopleSoft Process Scheduler.

One valuable reference can be found here:

[https://docs.oracle.com/cd/E91187\\_01/pt855pbr2/eng/pt/tprs/task\\_SchedulingProcessRequests-c07170.html#uba875df3-64ee-4123-b1bf-64a25a86c9d2](https://docs.oracle.com/cd/E91187_01/pt855pbr2/eng/pt/tprs/task_SchedulingProcessRequests-c07170.html#uba875df3-64ee-4123-b1bf-64a25a86c9d2)

Refer to section Selecting Output Types and Formats for relevant information.

## Command Usage

The OUTPUT\_DESTINATION\_FORMAT option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# OUTPUT\_DESTINATION\_STRING - UPPS configuration option

## Description

The OUTPUT\_DESTINATION\_STRING option specifies an override for the file path or printer destination for the output, if the output type for a submitted process is File or Printer.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-OutputDestinationString <i>string</i>			✓	✓	
Environment Variable	UPPS_OUTPUTDESTINATIONSTRING= <i>string</i>			✓	✓	
Configuration File Keyword	n/a			✓	✓	

## Value

*string* is the file path or printer destination for the output.

## Command Usage

The OUTPUT\_DESTINATION\_STRING option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# OUTPUT\_DESTINATION\_TYPE - UPPS configuration option

## Description

The OUTPUT\_DESTINATION\_TYPE option specifies the type of output for a submitted process.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-OutputDestinationType <i>type</i>			✓	✓	
Environment Variable	UPPS_OUTPUTDESTINATIONTYPE= <i>type</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*type* is the output type for a submitted process.

Valid values can be obtained by using the [DISPLAY OUTPUT TYPES](#) command.

## Command Usage

The OUTPUT\_DESTINATION\_TYPE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY OUTPUT FORMATS](#)
- [SUBMIT PROCESS](#)

# OUTPUT\_FORMAT - UPPS configuration option

## Description

The OUTPUT\_FORMAT option specifies the format of the output from a PeopleSoft process.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-outfmt <i>format</i>			✓	✓	
Environment Variable	UPPSOUTFMT= <i>format</i>			✓	✓	
Configuration File Keyword	outfmt <i>format</i>			✓	✓	

## Value

*format* is the format of the output from a PeopleSoft process.

Valid values for *format* are:

- **test**  
Output will be formatted for human consumption.
- **xml**  
Output will be formatted as XML.

## Command Usage

The OUTPUT\_FORMAT option is used in the following Universal Connector commands:

- [DISPLAY PRCS GET REPORT](#)
- [DISPLAY PRCS GET REQUEST](#)
- [DISPLAY PRCS GET SERVER CONSTRAINTS](#)
- [DISPLAY OUTPUT FORMATS](#)
- [DISPLAY OUTPUT TYPES](#)
- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [DISPLAY PRCS PROMPT](#)
- [DISPLAY PROCESS NAMES](#)

# PASSWORD - UPPS configuration option

## Description

The PASSWORD option specifies the password for the PeopleSoft user ID.

If the password is not specified and the command is executed from a console, Universal Connector for PeopleSoft prompts for a password.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-w password</code>			✓	✓	
Command Line, Long Form	<code>-pwd password</code>			✓	✓	
Environment Variable	<code>UPPSPWD=password</code>			✓	✓	
Configuration File Keyword	<code>password password</code>			✓	✓	

## Value

*password* is the password for the PeopleSoft user ID.

## Command Usage

The PASSWORD option is a [USER](#) option.

USER options are associated with program execution, not commands. They are required to establish an RFC connection to a PeopleSoft system.

# PLF\_DIRECTORY - UPPS configuration option

## Description

The PLF\_DIRECTORY option specifies the Program Lock File (PLF) directory where the program lock files are located.

A program lock file is created and used by the UPPS process to store manager process termination information for the Universal Broker.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-plf_directory <i>directory</i>			✓		
Environment Variable	UPPSPLFDIRECTORY= <i>directory</i>			✓		
Configuration File Keyword	n/a					

## Values

*directory* is the name of the PLF directory.

**Default is=** /var/opt/universal/tmp.

## Command Usage

The PLF\_DIRECTORY option is a [LOCAL](#) option.

LOCAL options are associated with program execution, not commands. They are required for local broker registration.



# POLL - UPPS configuration option

## Description

The POLL option specifies the length of time to wait between status calls to the PeopleSoft system.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-poll <i>seconds</i>			✓	✓	
Environment Variable	UPPSPOLL= <i>seconds</i>			✓	✓	
Configuration File Keyword	poll <i>seconds</i>			✓	✓	

## Value

*seconds* is the length of time to wait between status calls to the PeopleSoft system.

**Default is 10.**

## Command Usage

The POLL option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# PORT - UPPS configuration option

## Description

The PORT option specifies the port number for the PeopleSoft application server. .

PORT, in conjunction with the [HOST](#) option, is used to define a connection to a PeopleSoft system.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-port_number_			✓	✓	
Environment Variable	UPPSPORT <i>number</i>			✓	✓	
Configuration File Keyword	port <i>number</i>			✓	✓	

## Value

*number* is the port number for a PeopleSoft application server.

## Example

```
-port 123
```

## Command Usage

The PORT option is a [HOST](#) option.


HOST options are associated with program execution, not commands. They are required to establish a connection with a PeopleSoft system.

# PRINT\_APPLICATION\_MESSAGE - UPPS configuration option

## Description

The PRINT\_APPLICATION\_MESSAGE option controls whether or not the application messages for the monitored processes are included in the Job Report.

### Note

 If PRINT\_APPLICATION\_MESSAGE, PRINT\_DISTRIBUTION\_LIST, PRINT\_JOB\_TREE, PRINT\_PARAMETER\_LIST, AND PRINT\_SYSTEM\_MESSAGE all are set to **no**, the Job Report is not printed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printapplicationmmessage <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTAPPLICATIONMESSAGE= <i>option</i>			✓	✓	
Configuration File Keyword	printapplicationmessage <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the application messages for the monitored processes are included in the Job Report.

Valid values:

- **yes**  
The messages are included in the Job Report.
- **no**  
The messages are not included in the Job Report.

## Command Usage

The PRINT\_SYSTEM\_MESSAGE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [SUBMIT PROCESS](#)

# PRINT\_DISTRIBUTION\_LIST - UPPS configuration option

## Description

The PRINT\_DISTRIBUTION\_LIST option controls whether or not the report-recipient distribution list is included in the Job Report.

### Note

If PRINT\_APPLICATION\_MESSAGE, PRINT\_DISTRIBUTION\_LIST, PRINT\_JOB\_TREE, PRINT\_PARAMETER\_LIST, AND PRINT\_SYSTEM\_MESSAGE all are set to **no**, the Job Report is not printed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printdistlist <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTDISTLIST= <i>option</i>			✓	✓	
Configuration File Keyword	printdistlist <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the report-recipient distribution list is included in the Job Report.

Valid values:

- **yes**  
Job distribution list is included in the Job Report.
- **no**  
Job distribution list is not included in the Job Report.

## Command Usage

The PRINT\_DISTRIBUTION\_LIST option is used in the following Universal Connector for PeopleSoft commands:


- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [SUBMIT PROCESS](#)

# PRINT\_JOB\_TREE - UPPS configuration option

## Description

The PRINT\_JOB\_TREE option controls whether or not the job tree is included in the Job Report.

### Note

 If PRINT\_APPLICATION\_MESSAGE, PRINT\_DISTRIBUTION\_LIST, PRINT\_JOB\_TREE, PRINT\_PARAMETER\_LIST, AND PRINT\_SYSTEM\_MESSAGE all are set to **no**, the Job Report is not printed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printjobtree <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTJOBTREE= <i>option</i>			✓	✓	
Configuration File Keyword	printjobtree <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the job tree is included in the Job Report.

Valid values:

- **yes**  
Job tree is included in the Job Report.
- **no**  
Job tree is not included in the Job Report.

## Command Usage

The PRINT\_JOB\_TREE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [SUBMIT PROCESS](#)

# PRINT\_MESSAGE\_LIST - UPPS configuration option

## Description

The PRINT\_MESSAGE\_LIST option specifies whether or not the messages that will be emailed upon completion of a job item are included in the report.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printmessagelist <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTMESSAGELIST= <i>option</i>			✓	✓	
Configuration File Keyword	printmessagelist <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the messages that will be emailed upon completion of a job item are included in the report.

Valid values:

- **yes**  
Messages are included in the report.
- **no**  
Messages are not included in the report.

## Command Usage

The PRINT\_MESSAGE\_LIST option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT SCHED HTML REPORT](#)

# PRINT\_NOTIFY\_LIST - UPPS configuration option

## Description

The PRINT\_NOTIFY\_LIST option specifies whether or not the job notify list is included in the report.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printnotifylist <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTNOTIFYLIST= <i>option</i>			✓	✓	
Configuration File Keyword	printnotifylist <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the notify list is included in the report

Valid values:

- **yes**  
Job notify list is included in the report.
- **no**  
Job notify list is not included in the report.

## Command Usage

The PRINT\_NOTIFY\_LIST option is used in the following Universal Connector for PeopleSoft commands:


- [DISPLAY PRCS PRINT SCHED HTML REPORT](#)

# PRINT\_PARAMETER\_LIST - UPPS configuration option

## Description

The PRINT\_PARAMETER\_LIST option controls whether or not the parameter list job items are included in the Job Report.

### Note

 If PRINT\_APPLICATION\_MESSAGE, PRINT\_DISTRIBUTION\_LIST, PRINT\_JOB\_TREE, PRINT\_PARAMETER\_LIST, AND PRINT\_SYSTEM\_MESSAGE all are set to **no**, the Job Report is not printed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printparamlist <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTPARAMLIST= <i>option</i>			✓	✓	
Configuration File Keyword	printparamlist <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the parameter list job items are included in the Job Report.

Valid values:

- **yes**  
The parameter list is included in the Job Report.
- **no**  
The parameter list is not included in the Job Report.

## Command Usage

The PRINT\_PARAMETER\_LIST option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [DISPLAY PRCS PRINT SCHED HTML REPORT](#)
- [SUBMIT PROCESS](#)




# PRINT\_SYSTEM\_MESSAGE - UPPS configuration option

## Description

The PRINT\_SYSTEM\_MESSAGE option controls whether or not to print the system messages for the monitored processes are included in the Job Report.

### Note

 If PRINT\_APPLICATION\_MESSAGE, PRINT\_DISTRIBUTION\_LIST, PRINT\_JOB\_TREE, PRINT\_PARAMETER\_LIST, AND PRINT\_SYSTEM\_MESSAGE all are set to **no**, the Job Report is not printed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printssystemmessage <i>option</i>			✓	✓	
Environment Variable	UPPSPRINTSYSTEMMESSAGE= <i>option</i>			✓	✓	
Configuration File Keyword	printssystemmessage <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not to print the system messages for the monitored processes are included in the Job Report.

Valid values:

- **yes**  
The messages are included in the Job Report.
- **no**  
The messages are not included in the Job Report.

## Command Usage

The PRINT\_SYSTEM\_MESSAGE option is used in the following Universal Connector for PeopleSoft commands:


- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [SUBMIT PROCESS](#)

# PRIVATE\_KEY - UPPS configuration option

## Description

The PRIVATE\_KEY option specifies the location of the PEM-formatted RSA private key that corresponds to the X.509 certificates specified by the CERTIFICATE option.

Note

 PRIVATE\_KEY is required only if a certificate is specified by CERTIFICATE.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-private_key <i>file</i>			✓	✓	
Environment Variable	UPPSPRIVATEKEY= <i>file</i>			✓	✓	
Configuration File Keyword	private_key <i>file</i>			✓	✓	

## Values

<b>UNIX</b>	<i>file</i> is the path of the PEM-formatted RSA private key file that corresponds to the X.509 certificates.
<b>Windows</b>	<i>file</i> is the path of the PEM-formatted RSA private key file that corresponds to the X.509 certificates.

## Command Usage

The PRIVATE\_KEY option is an SSL option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# PRIVATE\_KEY\_PWD - UPPS configuration option

## Description

The PRIVATE\_KEY\_PWD option specifies the password or passphrase for the PEM-formatted RSA private key specified with the [PRIVATE\\_KEY](#) option.

### Note



Whether or not the password is required depends on whether or not it is required by the private key.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	<code>-private_key_pwd password</code>			✓	✓	
Environment Variable	<code>UPPSPRIVATEKEYPWD=password</code>			✓	✓	
Configuration File Keyword	<code>private_key_password=password</code>			✓	✓	

## Values

*password* is the password for the private key.

## Command Usage

The PRIVATE\_KEY\_PWD option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# PROCESS\_INSTANCE - UPPS configuration option

## Description

The PROCESS\_INSTANCE option specifies a PeopleSoft process instance number identifying the request to be returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processinstance <i>number</i>			✓	✓	
Environment Variable	UPPSPROCESSINSTANCE= <i>number</i>			✓	✓	
Configuration File Keyword	processinstance <i>number</i>			✓	✓	

## Value

*number* is the process instance number identifying the request to be returned.

## Command Usage

The PROCESS\_INSTANCE option is used in the following Universal Connector for PeopleSoft commands:

- [CANCEL PROCESS](#)
- [DELETE PROCESS](#)
- [DISPLAY PRCS GET REQUEST](#)
- [DISPLAY PRCS PRINT JOB REQUEST REPORT](#)
- [HOLD PROCESS](#)
- [WAIT for PROCESS](#)

# PROCESS\_INSTANCE\_FROM - UPPS configuration option

## Description

The PROCESS\_INSTANCE\_FROM option specifies the starting (lower) process instance ID in a range of instance IDs to be displayed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processinstancefrom <i>ID</i>			✓	✓	
Environment Variable	UPPSPROCESSINSTANCEFROM= <i>ID</i>			✓	✓	
Configuration File Keyword	processinstancefrom <i>ID</i>			✓	✓	

## Value

*ID* is the starting (lower) process instance ID in a range of instance IDs to be displayed.

## Command Usage

The PROCESS\_INSTANCE\_FROM option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# PROCESS\_INSTANCE\_TO - UPPS configuration option

## Description

The PROCESS\_INSTANCE\_TO option specifies the ending (upper) process instance ID in a range of instance IDs to be displayed.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processinstanceto <i>ID</i>			✓	✓	
Environment Variable	UPPSPROCESSINSTANCETO= <i>ID</i>			✓	✓	
Configuration File Keyword	processinstanceto <i>ID</i>			✓	✓	

## Value

*ID* is the ending (upper) process instance ID in a range of instance IDs to be displayed.

## Command Usage

The PROCESS\_INSTANCE\_TO option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# PROCESS\_FILE\_NAME - UPPS configuration option

## Description

The PROCESS\_FILE\_NAME option specifies an override for the dependent file name for the submitted process.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ProcessFileName <i>name</i>			✓	✓	
Environment Variable	UPPS_PROCESSFILENAME= <i>name</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is the override for the dependent file name for the submitted process.

## Command Usage

The PROCESS\_FILE\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# PROCESS\_NAME - UPPS configuration option

## Description

The PROCESS\_NAME option specifies the name of a PeopleSoft process for which parameter names will be returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processname <i>name</i>			✓	✓	
Environment Variable	UPPS_PROCESSNAME= <i>name</i>			✓	✓	
Configuration File Keyword	processname <i>name</i>			✓	✓	

## Value

*name* is a name of the PeopleSoft process for which parameters will be returned.

## Command Usage

The PROCESS\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY OUTPUT FORMATS](#)
- [DISPLAY OUTPUT TYPES](#)
- [DISPLAY PRCS PARAMS](#)



# PROCESS\_REQUEST\_COUNT - UPPS configuration option

## Description

The PROCESS\_REQUEST\_COUNT option specifies the limit of the number of requests that will be returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processrequestcount <i>number</i>			✓	✓	
Environment Variable	UPPSPROCESSREQUESTCOUNT= <i>number</i>			✓	✓	
Configuration File Keyword	processrequestcount <i>number</i>			✓	✓	

## Value

*number* is the limit of the number of requests that will be returned.

## Command Usage

The PROCESS\_REQUEST\_COUNT option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# PROCESS\_TYPE - UPPS configuration option

## Description

The PROCESS\_TYPE option specifies a specific type of PeopleSoft process.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-processtype <i>type</i>			✓	✓	
Environment Variable	UPPS_PROCESSTYPE= <i>type</i>			✓	✓	
Configuration File Keyword	processtype <i>type</i>			✓	✓	

## Value

*type* is a specific type of PeopleSoft process.

You can obtain the list of process types either of two ways:

- From the PeopleSoft Process Scheduler directly.
- Use the UPPS DISPLAY PROMPT command to get the "prompt" values. For example:

Valid values for *type* are:

- Application Engine
- XML Publisher
- Cube Builder
- COBOL SQL
- Crw Online
- Crystal
- Data Mover
- Database Agent
- Essbase Cube Builder
- Message Agent API
- Optimization Engine
- PSJob
- SQR Process
- SQR Report
- SQR Report For WF Delivery
- Winword
- nVision-Report
- nVision-ReportBook

## Command Usage

The PROCESS\_TYPE option is used in the following Universal Connector commands:

- [DISPLAY OUTPUT FORMATS](#)
- [DISPLAY OUTPUT TYPES](#)
- [DISPLAY PRCS GET SERVER CONSTRAINTS](#)
- [DISPLAY PROCESS NAMES](#)

# PROMPT - UPPS configuration option

## Description

The PROMPT option specifies the type of prompt values in the PeopleSoft system that will be displayed by the [DISPLAY PRCS PROMPT](#) command.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-prompt <i>types</i>			✓	✓	
Environment Variable	UPPSPROMPT= <i>types</i>			✓	✓	
Configuration File Keyword	prompt <i>types</i>			✓	✓	

## Value

*values* is the type(s) of prompt values that will be displayed.

Valid values for *values* are:

- RunStatus
- DistributionStatus
- ServerName
- ProcessTypes
- OperatorId
- RecurrenceName

The prompt *values* are case sensitive.

## Command Usage

The PROMPT option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PROCESS NAMES](#)

# RECURRENCE\_NAME - UPPS configuration option

## Description

The RECURRENCE\_NAME option specifies the named recurrence definition to apply to the process submission.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-RecurrenceName <i>name</i>			✓	✓	
Environment Variable	UPPS_RECURRENCE_NAME= <i>name</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is a valid recurrence name defined to the PeopleSoft Process Scheduler.

### Note



The `DISPLAY PRCS PROMPT` UPPS command can be used to get list of valid recurrence names.

## Command Usage

The RECURRENCE\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# REPORT - UPPS configuration option

## Description

The REPORT option specifies whether or not the reports associated with a process are returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-report <i>option</i>			✓	✓	
Environment Variable	UPPSREPORT= <i>option</i>			✓	✓	
Configuration File Keyword	print_report <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not reports associated with a process are returned.

Valid values:

- **yes**  
The reports are returned.
- **no**  
The reports are not returned.

**Default is yes.**

## Command Usage

The REPORT option is used in the following Universal Connector for PeopleSoft commands:


- [SUBMIT PROCESS](#)

# REPORT\_FOLDER\_NAME - UPPS configuration option

## Description

The REPORT\_FOLDER\_NAME option specifies an override for the folder name for the main job or process.

### Note

 For a process within a job, use the override for job item node (<JobItem> section) in a request definition file.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ReportFolderName <i>name</i>			✓	✓	
Environment Variable	UPPS_REPORTFOLDERNAME= <i>name</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*name* is the report folder name.

## Command Usage

The REPORT\_FOLDER\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# RETENTION\_DAYS - UPPS configuration option

## Description

The RETENTION\_DAYS option specifies an override for the retention days defined for a submitted process.

For a process within a job, enter the override for job item (<JobItem> section) in a request definition file.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-RetentionDays <i>number</i>			✓	✓	
Environment Variable	UPPS_RETENTIONDAYS= <i>number</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*number* is the number of days that reports generated by the submitted process should be retained by the PeopleSoft system.

## Command Usage

The RETENTION\_DAYS option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# RETURN\_JOB\_LOG - UPPS configuration option

## Description

The RETURN\_JOB\_LOG option specifies whether or not the job's job log is returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-g <i>option</i>			✓	✓	
Command Line, Long Form	-joblog <i>option</i>			✓	✓	
Environment Variable	UPPS_JOBLOG= <i>option</i>			✓	✓	
Configuration File Keyword	print_joblog <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the job log is returned.

Valid values for *option* are:

- **yes**  
Job log is returned to standard out.
- **no**  
Job log is not returned.

**Default is yes.**

## Command Usage

The RETURN\_JOB\_LOG option is used in the following Universal Connector commands:



# RETURN\_SPOOL\_LIST - UPPS configuration option

## Description

The RETURN\_SPOOL\_LIST option specifies whether or not the spool lists of all job steps are returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-s <i>option</i>			✓	✓	
Command Line, Long Form	-spoolist <i>option</i>			✓	✓	
Environment Variable	UPPS_SPOOLLIST= <i>option</i>			✓	✓	
Configuration File Keyword	print_spoolist <i>option</i>			✓	✓	

## Value

*option* is the specification for whether or not the spool lists are returned.

Valid values for *option* are:

- **yes**  
Spool lists are returned to standard out.
- **no**  
Spool lists are not returned.

**Default is yes.**

## Command Usage

The RETURN\_SPOOL\_LIST option is used in the following Universal Connector commands:

# RUN\_CONTROL\_ID - UPPS configuration option

## Description

The RUN\_CONTROL\_ID option specifies the run control ID to be used for the process submission.

This can be an existing run control ID or a new one to be created for this instance.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-RunControlId <i>ID</i>			✓	✓	
Environment Variable	UPPS_RUNCONTROLID= <i>ID</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*ID* is the run control ID to be used for process submission.

## Command Usage

The RUN\_CONTROL\_ID option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# RUN\_DATE\_TIME - UPPS configuration option

## Description

The RUN\_DATE\_TIME option specifies a custom run date time for the submitted process.

If this option is not specified, the PeopleSoft Process Scheduler will run the process upon receiving the request.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-RunDateTime <i>date,time</i>			✓	✓	
Environment Variable	UPPS_RUNDATETIME= <i>time</i>			✓	✓	
Configuration File Keyword	n/a			✓	✓	

## Value

*date,time* is the custom run date time for the submitted process.

The format is 2017-04-28 01.11.37.000000.

## Command Usage

The RUN\_DATE\_TIME option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# RUN\_STATUS - UPPS configuration option

## Description

The RUN\_STATUS option specifies filter requests by run status.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-runstatus <i>status</i>			✓	✓	
Environment Variable	UPPSRUNSTATUS= <i>status</i>			✓	✓	
Configuration File Keyword	runstatus <i>status</i>			✓	✓	

## Value

*status* is the run status by which you want to filter requests.

## Command Usage

The RUN\_STATUS option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# SERVER\_NAME - UPPS configuration option

## Description

The SERVER\_NAME option specifies a specific server name for which constraints will be returned.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-servername <i>name</i>			✓	✓	
Environment Variable	UPPS_SERVERNAME= <i>name</i>			✓	✓	
Configuration File Keyword	servername <i>name</i>			✓	✓	

## Value

*name* is the name of a specific server for which constraints will be returned.

## Command Usage

The SERVER\_NAME option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY PRCS GET SERVER CONSTRAINTS](#)

# SERVER\_RUN - UPPS configuration option

## Description

The SERVER\_RUN option specifies filter requests by this server name.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-serverrun <i>server</i>			✓	✓	
Environment Variable	UPPSSERVERRUN= <i>server</i>			✓	✓	
Configuration File Keyword	serverrun <i>server</i>			✓	✓	

## Value

*server* is the name of the server by which you want to filter requests.

## Command Usage

The SERVER\_RUN option is used in the following Universal Connector for PeopleSoft command:

- [DISPLAY REQUESTS](#)

# SSL\_CIPHER\_LIST - UPPS configuration Option

## Description

The SSL\_CIPHER\_LIST option specifies the SSL cipher suites acceptable for use by the SSL protocol.

The SSL protocol uses the cipher suites to specify which encryption and message authentication (or message digest) algorithms to use.


## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ssl_cipher_list <i>list</i>			✓	✓	
Environment Variable	UPPSSSLCIPHERLIST= <i>list</i>			✓	✓	
Configuration File Keyword	ssl_cipher_list <i>list</i>			✓	✓	

## Values

*list* is a comma-separated list of SSL cipher suites. The following table identifies the list of SSL cipher suites supported for this option.

The list is in default order, with the most preferred suite first and the least preferred suite last.

Cipher Suite	Description
AES256-GCM-SHA384	256-bit AES encryption in Galois Counter Mode, SHA-2 384-bit message digest.
AES256-SHA	256-bit AES encryption with SHA-1 message digest.
AES128-GCM-SHA256	128-bit AES encryption in Galois Counter Mode, SHA-2 256-bit message digest.
AES128-SHA	128-bit AES encryption with SHA-1 message digest.
RC4-SHA	128-bit RC4 encryption with SHA-1 message digest.
RC4-MD5	128-bit RC4 encryption with MD5 message digest.
DES-CBC3-SHA	128-bit Triple-DES encryption with SHA-1 message digest.
DES-CBC-SHA	128-bit DES encryption with SHA-1 message digest.  Note  As of Universal Agent 6.7.0.0, DES-CBC-SHA is supported only on HP-UX.  Additionally, any 6.7.x Agents on HP-UX that accept connections from, or attempt connections to, 6.7.x Agents on other platforms must be configured with at least one currently supported cipher suite besides DES-CBC-SHA. Therefore, those HP-UX Agents cannot be configured only with DES-CBC-SHA in their list of cipher suites.
NULL-SHA256	No encryption and SHA-2 256-bit message digest.
NULL-SHA	No encryption and SHA-1 message digest.
NULL-MD5	No encryption and MD5 message digest.

## Command Usage

The `SSL_CIPHER_LIST` option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.



# TIME\_ZONE - UPPS configuration option

## Description

The TIME\_ZONE option specifies the time zone to use for the [RUN\\_DATE\\_TIME](#) configuration option.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-TimeZone <i>zone</i>			✓	✓	
Environment Variable	UPPS_TIMEZONE= <i>zone</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*zone* is a valid time zone abbreviation.

## Command Usage

The TIME\_ZONE option is used in the following Universal Connector for PeopleSoft commands:

- [SUBMIT PROCESS](#)

# TO\_DATE - UPPS configuration option

## Description

The TO\_DATE option specifies the latest date to use for job selection or syslog request.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-todate <i>date</i>			✓	✓	✓
Environment Variable	UPPSTODATE= <i>date</i>			✓	✓	
Configuration File Keyword	n/a					

## Value

*date* is the latest date to use for job selection or syslog request.

The format of *date* is:

YYYY/MM/DD

## Command Usage

The TO\_DATE option is used in the following Universal Connector for PeopleSoft commands:

- [DISPLAY REQUESTS](#)

# TRACE\_FILE\_LINES - UPPS configuration option

## Description

The TRACE\_FILE\_LINES option specifies the maximum number of lines to write to the trace file.

A trace file is generated when the MESSAGE\_LEVEL option is set to **trace**. The trace file will wrap around when the maximum number of lines has been reached and start writing trace entries after the trace header lines.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-tracefilelines <i>lines</i>			✓	✓	
Environment Variable	UPPSTRACEFILELINES= <i>lines</i>			✓	✓	
Configuration File Keyword	trace_file_lines <i>lines</i>			✓	✓	

## Value

*lines* is the maximum number of lines to write to the trace file.

**Default is 500,000,000.**

## Command Usage

The TRACE\_FILE\_LINES option is a MESSAGE option.

MESSAGE options are associated with program execution, not commands. They specify different characteristics of **upps** messages.

# TRACE\_TABLE - UPPS configuration option

## Description

The TRACE\_TABLE option specifies the size of a wrap-around trace table, and under what conditions the table is written to a file when the process ends.

Trace data can be written to a file / data set as it is produced, or it can be written to a table maintained in memory.

The trace table is written to a file / data set when the program ends under the conditions specified in this option. Tracing is activated, and a trace file is generated, when the MESSAGE\_LEVEL option is set to **trace**.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-trace_table size, condition			✓	✓	
Environment Variable	n/a					
Configuration File Keyword	trace_table size, condition			✓	✓	

## Values

size is the size (in bytes) of the table.

The size can be suffixed with either of the following characters:

- **M**  
Indicates that the size is specified in megabytes.
- **K**  
Indicates that the size is specified in kilobytes.

For example, 50M indicates that 50 X 1,048,576 bytes of memory is allocated for the trace table.

**Default is 0 (trace table is not used).**

condition is the condition under which the trace table is written.

Valid values for condition are:

- **error**  
Write the trace table if the program ends with a non-zero exit code.
- **always**  
Write the trace table when the program ends regardless of the exit code.
- **never**  
Never write the trace table.

**Default is never.**

## Command Usage

The TRACE\_TABLE option is a MESSAGE option.

MESSAGE options are associated with program execution, not commands. They specify different characteristics of **upps** messages.

# USER\_ID - UPPS configuration option

## Description

The USER\_ID option specifies the PeopleSoft user ID with which to logon to the PeopleSoft system.

If the user ID is not specified and the command is executed from a console, Universal Connector for PeopleSoft prompts for a user ID.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-u <i>userid</i></code>			✓	✓	
Command Line, Long Form	<code>-userid <i>userid</i></code>			✓	✓	
Environment Variable	<code>UPPSUSERID=<i>userid</i></code>			✓	✓	
Configuration File Keyword	<code>userid <i>userid</i></code>			✓	✓	

## Value

*userid* is the PeopleSoft user ID with which to logon to the PeopleSoft system.

## Command Usage

The USER\_ID option is a [USER](#) option.

USER options are associated with program execution, not commands. They are required to establish an RFC connection to a PeopleSoft system.

# VERIFY\_HOST\_NAME - UPPS configuration option

## Description

The VERIFY\_HOST\_NAME option specifies whether or not the PeopleSoft server's [X.509 certificate](#) host name is verified.

The identity is verified by matching the host specified in the [ENDPOINT](#) configuration option URL value to a Common Name field or a Subject Alternate Name field in the PeopleSoft server's certificate.

If verification fails, the session is rejected and UPPS terminates.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-verify_host_name <i>option</i>			✓	✓	
Environment Variable	UPPSVERIFYHOSTNAME= <i>option</i>			✓	✓	
Configuration File Keyword	verify_host_name <i>option</i>			✓	✓	

## Values

*option* is the specification for whether or not the [X.509 certificate](#) host name must be verified.

Valid values for *option* are:

- **yes**  
Verify the server's host name.
- **no**  
Do not verify the server's host name.

**Default is yes.**

## Command Usage

The VERIFY\_HOST\_NAME option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# VERIFY\_PEER - UPPS configuration option

## Description

The VERIFY\_PEER option specifies whether or not the authenticity of the PeopleSoft server's [X.509 certificate](#) is verified.

In order to verify the authenticity of the server's certificate, the [CA\\_CERTIFICATES](#) configuration option must point to a valid list of certificate authority certificates.

If verification fails, the session is rejected and UPPS terminates.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-verify_peer <i>option</i>			✓	✓	
Environment Variable	UPPSVERIFYPEER= <i>option</i>			✓	✓	
Configuration File Keyword	verify_peer <i>option</i>			✓	✓	

## Values

*option* is the specification for whether or not the authenticity of the PeopleSoft server's [X.509 certificate](#) is verified.

Valid values for option are:

- **yes**  
Verify the server's certificate.
- **no**  
Do not verify the server's certificate.

**Default is yes.**

## Command Usage

The VERIFY\_PEER option is an [SSL](#) option.

SSL options are associated with program execution, not commands. They are used to configure the environment and behavior of HTTPS connections with the PeopleSoft system. They can be used with any command, but they only impact HTTPS connections.

# VERSION - UPPS configuration option

## Description

The VERSION option writes Universal Connector for PeopleSoft version and copyright information.

## Usage

Method	Syntax	IBM i	HP NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-v			✓	✓	
Command Line, Long Form	-version			✓	✓	
Environment Variable	n/a					
Configuration File Keyword	n/a					

## Value

(There are no values required for this option.)

## Command Usage

The VERSION option is an [INFORMATIONAL](#) option.

INFORMATIONAL options are associated with program execution, not commands. They request information pertaining to the UPPS program.



# Universal Connector for PeopleSoft Job Definition Files

## Universal Connector Job Definition Files

Job definition files contain statements that specify the attributes of jobs. These job definitions are used by the SUBMIT, MODIFY, and RUN commands to define or modify jobs in an SAP system.

Universal Connector supports several different job types. The following pages provide a detailed description of the syntax options and requirements for each type of job definition.

- [XML Job Definition File Syntax](#)

# XML Job Definition File Syntax

## Overview

We need a description of the section.

Request Message: PRQ\_SCHEDULE\_REQ  
 Process Distribution Option Elements  
 Process Output Option Elements  
 Process Email Option Elements  
 Job Item Elements  
 Job Item Distribution Option Elements  
 Job Item Output Option Elements  
 Job Item Email Option Elements  
 RunTime Parameter Elements

See the PRCS\_SCHEDULE section on this Oracle page:

[https://docs.oracle.com/cd/E57990\\_01/pt853pbh2/eng/pt/trws/task\\_SchedulingaRequest-1b7f37.html#u9a638ba5-3f8e-4a51-8d01-8cc9d25b5095](https://docs.oracle.com/cd/E57990_01/pt853pbh2/eng/pt/trws/task_SchedulingaRequest-1b7f37.html#u9a638ba5-3f8e-4a51-8d01-8cc9d25b5095)

The XML format is below:

```
<prq:Schedule><RunControlId>?</RunControlId><ProcessType>?</ProcessType><!--Optional:--><ProcessName>?</ProcessName><!--Optional:--><JobName>?</JobName><!--Optional:--><ServerName>?</ServerName><!--Optional:--><RunDateTime>?</RunDateTime><!--Optional:--><TimeZone>?</TimeZone><!--Optional:--><RecurrenceName>?</RecurrenceName><!--Optional:--><OutputDestinationType>?</OutputDestinationType><!--Optional:--><OutputDestinationFormat>?</OutputDestinationFormat><!--Optional:--><OutputDestinationString>?</OutputDestinationString><!--Optional:--><ReportFolderName>?</ReportFolderName><!--Optional:--><ProcessFileName>?</ProcessFileName><!--Optional:--><RetentionDays>?</RetentionDays><!--Zero or more repetitions:--><PrcsDistributionOption><PrcsDistributionIdType>?</PrcsDistributionIdType><PrcsDistributionId>?</PrcsDistributionId><PrcsDistributionOption><!--Optional:--><PrcsOutputOption><PrcsOutputDestinationType>?</PrcsOutputDestinationType><PrcsOutputDestinationFormat>?</PrcsOutputDestinationFormat><!--Optional:--><PrcsOutputDestinationString>?</PrcsOutputDestinationString><PrcsOutputOption><!--Optional:--><PrcsEmailOption><!--Optional:--><PrcsEmailSubject>?</PrcsEmailSubject><!--Optional:--><PrcsEmailText>?</PrcsEmailText><PrcsEmailAddresses>?</PrcsEmailAddresses><PrcsEmailAttachLog>false</PrcsEmailAttachLog><PrcsEmailWebReport>false</PrcsEmailWebReport><PrcsEmailOption><!--Zero or more repetitions:--><JobItem><JobName>?</JobName><!--Optional:--><ProcessItemLevel>?</ProcessItemLevel><!--Optional:--><JobSequenceNumber>?</JobSequenceNumber><!--Optional:--><SeqNoInItemLevel>?</SeqNoInItemLevel><!--Optional:--><DistributionOption><DistributionIdType>?</DistributionIdType><DistributionId>?</DistributionId></DistributionOption><!--Optional:--><OutputOption><OutputDestinationType>?</OutputDestinationType><OutputDestinationFormat>?</OutputDestinationFormat><!--Optional:--><OutputDestinationString>?</OutputDestinationString></OutputOption><!--Optional:--><EmailOption><!--Optional:--><EmailSubject>?</EmailSubject><!--Optional:--><EmailText>?</EmailText><EmailAddresses>?</EmailAddresses><EmailAttachLog>false</EmailAttachLog><EmailWebReport>false</EmailWebReport></EmailOption><!--Optional:--><ReportFolderName>?</ReportFolderName><!--Optional:--><RetentionDays>?</RetentionDays></JobItem><!--Zero or more repetitions:--><RunTimeParameter><ProcessName>?</ProcessName><ProcessType>?</ProcessType><ParameterName>?</ParameterName><ParameterValue>?</ParameterValue></RunTimeParameter></prq:Schedule>
```