



# Stonebranch Solutions

Version 4.2.0

Universal Enterprise Controller  
Client Applications

User Guide

uec-ca-4200



---

# Universal Enterprise Controller Client Applications User Guide

Stonebranch Solutions 4.2.0

---

<b>Document Name</b>	<b>Universal Enterprise Controller 4.2.0 Client Applications User Guide</b>				
<b>Document ID</b>	<b>uec-ca-4200</b>				
<b>Components</b>	<b>z/OS</b>	<b>UNIX</b>	<b>Windows</b>	<b>IBM i</b>	<b>HP NonStop</b>
I-Administrator			✓		
I-Activity Monitor			✓		
I-Management Console			✓		

---

# Stonebranch Documentation Policy

---

This document contains proprietary information that is protected by copyright. All rights reserved. No part of this publication may be reproduced, transmitted or translated in any form or language or by any means, electronic or mechanical, including photocopy, recording, or any information storage and retrieval system, without permission, in writing, from the publisher. Requests for permission to make copies of any part of this publication should be mailed to:

Stonebranch, Inc.  
950 North Point Parkway, Suite 200  
Alpharetta, GA 30005 USA  
Tel: (678) 366-7887  
Fax: (678) 366-7717

Stonebranch, Inc.<sup>®</sup> makes no warranty, express or implied, of any kind whatsoever, including any warranty of merchantability or fitness for a particular purpose or use.

The information in this documentation is subject to change without notice.

Stonebranch shall not be liable for any errors contained herein or for incidental or consequential damages in connection with the furnishing, performance or use of this document.

All products mentioned herein are or may be trademarks of their respective owners.

© 2003-2010 by Stonebranch, Inc.

All rights reserved.



---

# Summary of Changes

---

Changes for Universal Enterprise Controller 4.2.0  
Client Applications User Guide  
(uec-ca-4200)  
August 6, 2010

## **Universal Enterprise Controller Client Applications 4.2.0.0**

- No changes were required for this version of the document.

Changes for Universal Enterprise Controller 4.1.0  
Client Applications User Guide  
(uec-ca-4100)  
February 10, 2010

## **Universal Enterprise Controller Client Applications 4.1.0.0**

- Renamed Universal Activity Monitor as I-Activity Monitor.
- Renamed Universal Management Console as I-Management Console.
- Renamed UEC Administrator as I-Administrator.

Changes for Universal Enterprise Controller 3.2.0 Client Applications  
User Guide (uec-ca-3202)  
September 8, 2009

## **Universal Activity Monitor 3.2.0.2**

- Added [Tool Tips](#) in Section [4.7.1 Data Table Icons](#).
- Added [Table 4.7 Filter Matching Types](#) in Section [4.7.2 Data Table Filter Tool](#).

Changes for Universal Enterprise Controller 3.2.0 Client Applications  
User Guide (uec-ca-3201)  
September 5, 2008

- Added toll-free telephone number for North America in Appendix [A Customer Support](#).

**Universal Activity Monitor 3.2.0.1**

- Added job views (for Universal Command and Universal Data Mover) and file views in Chapter [4 I-Activity Monitor](#).

Changes for Universal Enterprise Controller 3.2.0 Client Applications  
User Guide (uec-ca-320)  
May 16, 2008

- This is the first version of the Universal Enterprise Controller 3.2.0 Client Applications document.

---

# Contents

---

Summary of Changes .....	5
Contents .....	7
List of Figures .....	12
List of Tables .....	15
Preface .....	16
Document Structure .....	16
Cross-Reference Links .....	16
Conventions .....	17
Vendor References .....	18
Terminology .....	19
Document Organization .....	21
1 Universal Enterprise Controller Client Applications Overview.....	22
1.1 Overview .....	22
1.1.1 I-Administrator .....	22
1.1.2 I-Activity Monitor .....	23
1.1.3 I-Management Console .....	23
2 Accessing UEC Client Applications .....	24
2.1 Overview .....	24
2.2 Connecting to UEC .....	25

2.2.1	Adding a Connection	26
2.2.2	UEC Connection Information	27
2.3	Logging In to a UEC Client Application	28
3	I-Administrator	29
3.1	Overview	29
3.1.1	Tasks Enabled via I-Administrator	29
3.2	Using I-Administrator	30
3.2.1	I-Administrator Screen Information	30
3.3	Menu Bar	32
3.3.1	Changing a Password	32
3.3.2	Logging Off I-Administrator	34
3.3.3	Viewing Information About I-Administrator	35
3.4	Tool Bar	36
3.5	Adding a User	38
3.5.1	Assigning User Permissions	40
3.5.2	Assigning Agent Groups to a User	42
3.5.3	Assigning Configuration Access to a User	43
3.6	Editing a User	45
3.7	Deleting a User	46
3.8	Adding a Group	47
3.9	Editing a Group	49
3.10	Deleting a Group	51
3.11	Adding an Agent	52
3.12	Editing an Agent	55
3.13	Deleting an Agent	57
3.14	Adding an SAP System	58
3.15	Editing an SAP System	61
3.16	Deleting an SAP System	63
4	I-Activity Monitor	64
4.1	Overview	64
4.1.1	I-Activity Monitor Tasks	64
4.2	Using I-Activity Monitor	65
4.2.1	I-Activity Monitor Screen Information	66
4.3	Menu Bar	67



4.4	Tool Bar	68
4.5	Filter Group Panel	70
4.6	Filter Tree	71
4.6.1	Filter Tree Icons	71
4.6.2	Alerts Category	72
	Alert Types	72
4.6.3	Jobs Category	73
4.6.4	Files Category	74
4.6.5	Systems Category	75
4.7	Data Table	76
	NA Values	76
4.7.1	Data Table Icons	77
	Tool Tips	78
4.7.2	Data Table Filter Tool	79
4.7.3	Sorting Data in the Data Table	81
4.7.4	Customizing Layout of the Data Table	82
	Saving a Data Table Layout	82
	Resetting the Default Data Table Layout	82
4.7.5	Updating Data Table Information	83
4.7.6	Displaying a Properties Table	83
4.7.7	Displaying a Jobs Table	83
4.8	Data Details Table	84
	NA Values	84
4.8.1	Properties Table	84
4.8.2	Jobs Table	85
4.9	User-Specific Tasks	86
4.9.1	Changing a Password	86
4.9.2	Saving a Data Table Layout	87
4.9.3	Resetting the Default Data Table Layout	87
4.9.4	Setting a Filter Group as Default Display	87
4.9.5	Logging Off I-Activity Monitor	88
	I-Activity Monitor Screen Size	89
4.9.6	Viewing Information About I-Activity Monitor	90
4.10	Stopping a Component	91
	Example	92
5	I-Management Console	93
5.1	Overview	93
5.1.1	I-Management Console Applications	93

5.2	Using I-Management Console	94
5.2.1	I-Management Console Screen Information	95
5.3	Menu Bar	96
5.4	Tool Bar	98
5.5	User Tasks	100
5.5.1	Accessing I-Management Console Applications	100
5.5.2	Logging Off I-Management Console	100
5.5.3	Displaying Information about I-Management Console	101
5.6	Agent Update	102
5.6.1	Accessing Agent Update	102
	Agent Tree	103
	Configuration Tree	104
	Configuration Options Table	105
5.6.2	Modifying Agent Configurations	107
	Undoing / Redoing Table Actions	108
5.6.3	Modifying Universal Access Control Lists	109
	UACL Configuration Actions	109
	Adding a UACL Entry	110
	Editing a UACL Entry	111
	Deleting a UACL Entry	112
	Moving Up a UACL Entry	112
	Moving Down a UACL Entry	112
5.6.4	Committing Agent Configurations	113
5.6.5	Validating Agent Configurations (Without Committing)	115
5.6.6	Correcting Invalid Agent Configuration Values	116
5.6.7	Saving Agent Configurations as a Profile	117
5.7	Mass Update	118
5.7.1	Accessing Mass Update	119
	Profile Tree	120
	Profile Configurations Tree	121
	Profile Agents Tree	122
	Profile Configurations Options Table	123
5.7.2	Creating a Profile	125
5.7.3	Adding / Removing Configurations in a Profile	126
5.7.4	Adding / Removing Agents in a Profile	128
5.7.5	Modifying Profile Configurations	130
	Undoing / Redoing Table Actions	131
5.7.6	Modifying Universal Access Control Lists	132
	Modifying a UACL Configuration	132

Adding a UACL Entry .....	133
Editing a UACL Entry .....	134
Deleting a UACL Entry .....	135
Moving Up a UACL Entry .....	135
Moving Down a UACL Entry .....	135
5.7.7 Saving Profile Configurations .....	136
5.7.8 Saving Profile Configurations As Another Profile .....	137
5.7.9 Validating Profile Configurations (Without Saving) .....	138
5.7.10 Committing Profile Configurations .....	139
Profile not Saved .....	140
5.7.11 Correcting Invalid Profile Configuration Values .....	141
5.7.12 Closing a Profile .....	142
Invalid Values in a Profile .....	142
5.7.13 Deleting a Profile .....	143
5.8 Commit Queue .....	144
5.8.1 Accessing Commit Queue .....	144
5.8.2 Commit Summary .....	145
5.8.3 Commit Detail .....	145
5.8.4 Canceling a Commit .....	146
A Customer Support .....	147
Index .....	148

---

# List of Figures

---

2	Accessing UEC Client Applications .....	24
	Figure 2.1 Connect To Universal Enterprise Controller dialog .....	25
	Figure 2.2 Add Connection dialog .....	26
	Figure 2.3 User Login dialog .....	28
3	I-Administrator .....	29
	Figure 3.4 I-Administrator screen .....	30
	Figure 3.5 I-Administrator - Change Password Dialog .....	32
	Figure 3.6 Connect To Universal Enterprise Controller dialog .....	34
	Figure 3.7 I-Administrator - Close Monitor dialog .....	34
	Figure 3.8 UEC - About I-Administrator dialog .....	35
	Figure 3.9 I-Administrator - Add User Dialog .....	38
	Figure 3.10 I-Administrator - User Access Dialog .....	40
	Figure 3.11 I-Administrator - Agent Group Access List .....	42
	Figure 3.12 I-Administrator - Configuration Access List .....	43
	Figure 3.13 I-Administrator - Edit User Dialog .....	45
	Figure 3.14 I-Administrator - Delete User Dialog .....	46
	Figure 3.15 I-Administrator - Add Group Dialog .....	47
	Figure 3.16 I-Administrator - Edit Group Dialog .....	49
	Figure 3.17 I-Administrator - Delete Group Dialog .....	51
	Figure 3.18 I-Administrator - Add Agent Dialog .....	52
	Figure 3.19 I-Administrator - Add Group dialog .....	54
	Figure 3.20 I-Administrator - Edit Agent Dialog .....	55
	Figure 3.21 I-Administrator - Delete Agent Dialog .....	57
	Figure 3.22 I-Administrator - Add SAP System Dialog .....	58
	Figure 3.23 I-Administrator - Add Group Dialog .....	60
	Figure 3.24 I-Administrator - Edit SAP System Dialog .....	61
	Figure 3.25 I-Administrator - Delete SAP System Dialog .....	63
4	I-Activity Monitor .....	64
	Figure 4.26 I-Activity Monitor screen .....	65
	Figure 4.27 I-Activity Monitor - Filter Group Panel .....	70

Figure 4.28	I-Activity Monitor - Filter Tree .....	71
Figure 4.29	I-Activity Monitor - Filter Tree / Alerts Category Filters .....	72
Figure 4.30	I-Activity Monitor - Filter Tree / Jobs Category Filters .....	73
Figure 4.31	I-Activity Monitor - Filter Tree / Files Category Filters .....	74
Figure 4.32	I-Activity Monitor - Filter Tree / Systems Category Filters .....	75
Figure 4.33	I-Activity Monitor - Data Table .....	76
Figure 4.34	I-Activity Monitor - Data Table / Filter Tool .....	79
Figure 4.35	I-Activity Monitor - Properties Table .....	84
Figure 4.36	I-Activity Monitor - Jobs Table .....	85
Figure 4.37	I-Activity Monitor - Change Password dialog .....	86
Figure 4.38	Connect To Universal Enterprise Controller dialog .....	88
Figure 4.39	I-Activity Monitor - Close Monitor dialog .....	88
Figure 4.40	I-Activity Monitor - About I-Activity Monitor dialog .....	90
Figure 4.41	I-Activity Monitor - Stop Component dialog .....	91
5	I-Management Console .....	93
Figure 5.42	I-Management Console screen (Initial Display) .....	94
Figure 5.43	Connect To Universal Enterprise Controller dialog .....	100
Figure 5.44	I-Management Console - Close Remote Configuration dialog .....	101
Figure 5.45	I-Management Console - About I-Management Console dialog .....	101
Figure 5.46	I-Management Console - Agent Update screen .....	102
Figure 5.47	I-Management Console - Agent Update screen / Agent Tree .....	103
Figure 5.48	I-Management Console - Agent Update screen / Configuration Tree .....	104
Figure 5.49	I-Management Console - Agent Update screen / Configuration Options table .....	105
Figure 5.50	I-Management Console - Agent Update / Configuration Option Selected .....	107
Figure 5.51	I-Management Console - Agent Update / Universal Access Control List Options .....	109
Figure 5.52	I-Management Console - Agent Update / Universal Access Control List Option - Add Row .....	110
Figure 5.53	I-Management Console - Agent Update / Universal Access Control List Option - Edit Row .....	111
Figure 5.54	I-Management Console - Agent Update / Commit dialog .....	113
Figure 5.55	I-Management Console - Agent Update / Commit Status dialog .....	114
Figure 5.56	I-Management Console - Agent Update / Validate dialog .....	116
Figure 5.57	Profile Save As... dialog .....	117
Figure 5.58	I-Management Console - Mass Update screen .....	119
Figure 5.59	I-Management Console - Mass Update screen / Profile Tree .....	120
Figure 5.60	I-Management Console - Mass Update screen / Profile Configurations tree .....	121
Figure 5.61	I-Management Console - Mass Update screen / Profile Agents tree .....	122
Figure 5.62	I-Management Console - Mass Update screen / Profile Configurations Options table .....	123
Figure 5.63	I-Management Console - Mass Update / New Profile dialog .....	125
Figure 5.64	I-Management Console - Mass Update / Edit Configuration List dialog .....	126
Figure 5.65	I-Management Console - Mass Update / Edit Agent List dialog .....	128
Figure 5.66	I-Management Console - Mass Update / Option Selected .....	130
Figure 5.67	I-Management Console - Mass Update / Universal Access Control List Options .....	132
Figure 5.68	I-Management Console - Mass Update / Universal Access Control List Option - Add Row .....	133
Figure 5.69	I-Management Console - Mass Update / Universal Access Control List Option - Edit Row .....	134
Figure 5.70	I-Management Console - Mass Update / Save As... dialog .....	137

---

Figure 5.71	I-Management Console - Mass Update / Commit dialog .....	139
Figure 5.72	I-Management Console - Mass Update / Commit Status dialog .....	140
Figure 5.73	I-Management Console - Mass Update / Validate dialog .....	141
Figure 5.74	I-Management Console - Mass Update / Delete Profile dialog .....	143
Figure 5.75	I-Management Console - Commit Queue screen .....	144

---

# List of Tables

---

3	I-Administrator .....	29
	Table 3.1 I-Administrator - Menu Selections .....	32
	Table 3.2 I-Administrator - Tool Bar Icons .....	37
4	I-Activity Monitor .....	64
	Table 4.3 I-Activity Monitor - Menu Selections .....	67
	Table 4.4 I-Activity Monitor - Tool Bar Icons .....	69
	Table 4.5 I-Activity Monitor - Filter Tree / Icons .....	71
	Table 4.6 I-Activity Monitor - Data Table / Icons .....	78
	Table 4.7 Filter Matching Types .....	80
5	I-Management Console .....	93
	Table 5.8 I-Management Console screen - Menu Selections .....	97
	Table 5.9 I-Management Console - Tool Bar Icons .....	99
	Table 5.10 I-Management Console - Commit Queue / Commit Summary Information .....	145
	Table 5.11 I-Management Console - Commit Queue / Commit Detail Information .....	145

---

# Preface

---

## Document Structure

This document is written using specific conventions for text formatting and according to a specific document structure in order to make it as useful as possible for the largest audience. The following sections describe the document formatting conventions and organization.

## Cross-Reference Links

---

This document contains cross-reference links to and from other Stonebranch Solutions documentation.

In order for the links to work correctly:

- Place the documents in the same folder.
- In Adobe Reader / Adobe Acrobat, de-select **Open cross-document link in same window** in the **General** category of your **Preferences** dialog (selected from the **Edit** menu).



## Conventions

---

Specific text formatting conventions are used within this document to represent different information. The following conventions are used.

### Typeface and Fonts

This document provides tables that identify how information is used. These tables identify values and/or rules that are either pre-defined or user-defined:

- *Italics* denotes user-supplied information.
- **Boldface** indicates pre-defined information.

Elsewhere in this document, **This Font** identifies specific names of different types of information, such as file names or directories (for example, `\abc\123\he1p.txt`).

### Operating System-Specific Text

Most of this document describes the product in the context of all supported operating systems. At times, it is necessary to refer to operating system-specific information. This information is introduced with a special header, which is followed by the operating system-specific text in a different font size from the normal text.

**z/OS**

This text pertains specifically to the z/OS line of operating systems.

This text resumes the information pertaining to all operating systems.

### Tips from the Stoneman



Look to the Stoneman for suggestions  
or for any other information  
that requires special attention.

**Stoneman's Tip**

---

## Vendor References

---

References are made throughout this document to a variety of vendor operating systems. We attempt to use the most current product names when referencing vendor software.

The following names are used within this document:

- **z/OS** is synonymous with IBM z/OS and IBM OS/390 line of operating systems.
- **Windows** is synonymous with Microsoft's Windows 2000 / 2003 / 2008, Windows XP, Windows Vista, and Windows 7 lines of operating systems. Any differences between the different systems will be noted.
- **UNIX** is synonymous with operating systems based on AT&T and BSD origins and the Linux operating system.
- **IBM i** is synonymous with IBM i/5, IBM OS/400, and OS/400 operating systems.
- **IBM System i** is synonymous with IBM i Power Systems, IBM iSeries, IBM AS/400, and AS/400 systems.

Note: These names do not imply software support in any manner. For a detailed list of supported operating systems, see the Stonebranch Solutions 4.2.0 Installation Guide.

---

# Terminology

---

The following terminology is used in this user guide:

## Agent

Single Indesca or Infitran installation, as defined in I-Administrator, comprised of one Universal Broker and one or more other Indesca or Infitran components.

## Commit

Commit configuration changes to a single Agent or multiple Agents assigned to a profile.

## Configuration

Set of options for an Indesca or Infitran component or component definition, or a set of rules for a Universal Access Control List (UACL) entry.

## Group

One or more Agents and/or SAP systems assigned to one or more users. Groups are used to control a user's access to agents and SAP systems.

By default, two groups are pre-defined in the UEC database:

- **A11 Agents** group – all Agents defined in the UEC database.
- **A11 SAP Systems** group – all SAP systems defined in the UEC database.

## Option

Configuration option of an Indesca or Infitran component or component definition, or a UACL entry.

## Profile

Set of configurations to which one or more Agents are assigned so that multiple Agents can be configured simultaneously.

## SAP System

In order for UEC to gain access to and retrieve information from an SAP system, it must first be defined – via I-Administrator – in the UEC database.

## Save

Save (and validate) modified configuration option values for a Profile.

## User

User of UEC Client Applications, as defined in I-Administrator. Each user is given a name, password, and permissions that identify and control access to UEC Client Applications.

## Validate

Determine if modified configuration option values are valid.

---

# Document Organization

The document is organized into the following chapters:

- [Universal Enterprise Controller Client Applications Overview](#) (Chapter 1)  
Overview of the Universal Enterprise Controller Client Applications.
- [Accessing UEC Client Applications](#) (Chapter 2)  
Information about accessing the Universal Enterprise Controller Client Applications.
- [I-Administrator](#) (Chapter 3)  
Information about the I-Administrator client application.
- [I-Activity Monitor](#) (Chapter 4)  
Information about the I-Activity Monitor client application.
- [I-Management Console](#) (Chapter 5)  
Information about the I-Management Console client application.
- [Customer Support](#) (Appendix A)  
Customer support contact information for Universal Enterprise Controller Client Applications.

---

# Universal Enterprise Controller Client Applications Overview

---

## 1.1 Overview

This chapter provides general information on the Universal Enterprise Controller (UEC) Client Applications:

- I-Administrator
- I-Activity Monitor
- I-Management Console

### 1.1.1 I-Administrator

---

The I-Administrator utility is used to identify the Agents that UEC will monitor and the SAP systems to which UEC will have access.

I-Administrator also is used to administer UEC users and their permissions.

With I-Administrator, a user can:

- Add, modify, and delete users, SAP systems, and Agents.
- Assign groups (of Agents and/or SAP systems) to users.

**Note:** A user must have UEC administrative rights in order to use I-Administrator.

Upon installation of UEC, a default user ID (**admin**) and password (**admin**) are created having UEC administrative rights. It is recommended that another user with administrative rights is created and the default administrative login (**admin**) is deleted.

---

## 1.1.2 I-Activity Monitor

---

The I-Activity Monitor displays information about the current status, posted alerts, and job and file activity for all Agents being monitored by UEC throughout an enterprise.

When an Agent or SAP system is added to (UEC), via the [I-Administrator](#) application, UEC is able to collect information about that Agent or system.

Authorized users are able to use the I-Activity Monitor interface to stop running any Indesca or Infitran component (if it is a component of an Agent being polled by UEC).

---

## 1.1.3 I-Management Console

---

The I-Management Console provides a graphical user interface for remotely configuring Agents.

- View and modify the configurations of Agents being monitored by UEC.
- Modify the configurations of multiple Agents simultaneously through the use of Agent profiles.
- View the status of modified configurations committed to Agents.

# Accessing UEC Client Applications

---

## 2.1 Overview

Currently, the UEC Client Applications can be run only as Windows applications.

To run a client application as a Windows application, you must first:

1. Connect to the UEC server on which client applications resides.
2. Log in to the client application.



## 2.2 Connecting to UEC

From the Windows **Start** menu, select the UEC Client Application that you want to run. The Connect to Universal Enterprise Controller dialog displays (Figure 2.1, below), which lets you connect to a Universal Enterprise Controller server.




Figure 2.1 Connect To Universal Enterprise Controller dialog

Select a connection in the UEC Connections window and click the **Connect** button. The User Login dialog then displays (Figure 2.3).

If there are no connections listed, you can create one (see Section 2.2.1 [Adding a Connection](#)).

**Note:** The Connect to Universal Enterprise Controller dialog also lets you **Edit** and **Delete** the user-defined UEC connections.

## 2.2.1 Adding a Connection

Click the **Add** button on the Connect to Universal Enterprise Controller dialog (Figure 2.1) to display the following dialog, which lets you add a connection.




Figure 2.2 Add Connection dialog

1. Enter the following information:
  - **Name** to be associated with the connection
  - **IP Address** (or hostname)
  - **Port** (UEC port)
2. Check **Default Connection** if you want this connection to be selected automatically the next time that you run the selected UEC Client Application.
3. Click **Save** to save the connection permanently and redisplay the Connect to Universal Enterprise Controller dialog (Figure 2.1), which displays this new connection.

**Note:** The I-Administrator utility and the I-Management Console utility keep separate controller lists.

## 2.2.2 UEC Connection Information

---

The UEC Client Applications create a file, **uechosts.txt**, that contains the UEC connection information, including the user-defined Agent name and the IP address on which UEC is installed. This file is shared by all client applications on UEC.

This file is located in the **%appdata%\Universa1** directory.

### Windows 2000, Windows XP, Windows Server 2003

**%appdata%** resolves to **C:\Documents and Settings\userid\Application Data**.

### Windows Vista, Windows 7, Windows Server 2008 / 2008 R2

**%appdata%** resolves to **C:\Users\userid\AppData\Roaming**.

For all Windows systems, **userid** is the ID of the user currently logged into Windows.

## 2.3 Logging In to a UEC Client Application

After you connect to Universal Enterprise Controller ([Figure 2.1](#)), the following dialog displays, which lets you log in to the selected client application.




Figure 2.3 User Login dialog

Enter your User Name and Password, and then click the **OK** button. The default screen for the selected client application then displays.

# I-Administrator

## 3.1 Overview

The I-Administrator utility is used to identify the Agents that UEC will monitor and the SAP systems to which UEC will have access. It also is used to administer UEC users and their permissions.

With I-Administrator, a user can:

- Add, modify, and delete users, SAP systems, and Agents.
- Assign groups (of Agents and/or SAP systems) to users.

### 3.1.1 Tasks Enabled via I-Administrator

By defining users, Agents, SAP systems, and groups in I-Administrator, you enable UEC to perform the following tasks:

- Poll status and events of Agents.
- Poll information from SAP systems.
- Propagate information to and from the UEC Client Applications:
  - I-Activity Monitor
  - I-Management Console

Additionally, it allows you, as a UEC user, to:

- Configure Agents and their applications through I-Management Console.
- Govern user permissions.

## 3.2 Using I-Administrator

When you log in to I-Administrator, (see Chapter 2 [Accessing UEC Client Applications](#)), the I-Administrator screen displays.




Figure 3.4 I-Administrator screen

### 3.2.1 I-Administrator Screen Information

The I-Administrator screen contains five regions:

- **Menu Bar (1)**  
The menu bar lets you change your UEC Client Applications password and log off I-Administrator (see Section 3.3 [Menu Bar](#)).
- **Tool Bar (2)**  
The tool bar lets you add, edit, and delete the four types of UEC database items (users, groups, Agents, and SAP systems) in the UEC database (see Section 3.4 [Tool Bar](#)).
- **UEC Navigation Tree (3)**  
The Navigation tree identifies the four types of UEC database items: Users, Groups, Agents, and SAP Systems.  
Clicking the + icon next to an item type displays a list, under that item type, of all currently defined items for that type.  
Clicking the name of an item type in the Navigation tree displays all currently defined items for that type in the Summary table.

- **Summary table (4)**  
The Summary table displays summary information of all items for a selected type. Clicking on an item in the Summary table displays detailed information about that item in the Detail view.
- **Detail View (5)**  
The Detail view displays detailed information about an item selected in the Summary table. It appears only when an item has been selected.

**Note:** The initial I-Administrator screen that displays when you log in provides a list of all currently defined UEC users. It does not pre-select a specific user and, therefore, does not display the Detail View (5).

The following sections in this chapter identify the information contained in these regions and how these regions are used to perform I-Administrator tasks.

## 3.3 Menu Bar

[Table 3.1](#), below, identifies the items on each menu of the menu bar at the top of the I-Administrator screen (see [Figure 3.4](#)).

The table provides a link to the task associated with each item.

Menu / Item	Description
User / Change Password	Change UEC Client Applications log in password. (See <a href="#">Section 3.3.1 Changing a Password</a> .)
User / Logoff	Log off I-Administrator. (See <a href="#">Section 3.3.2 Logging Off I-Administrator</a> .)
Help / About	View information about I-Administrator. (See <a href="#">Section 3.3.3 Viewing Information About I-Administrator</a> .)

Table 3.1 I-Administrator - Menu Selections

### 3.3.1 Changing a Password

To change the password that you use to log in to UEC Client Applications, perform the following steps.

1. Click **Change Password** on the **User** menu. The Change Password dialog displays.




Figure 3.5 I-Administrator - Change Password Dialog

1. Enter your **Current Password**.
2. Enter a **New Password**.
3. Reenter your new password in **Confirm Password**.



4. Click the **OK** button.

If the change was successful, the following dialog displays.



5. Click the **OK** button.

You must use this new password the next time that you log in to any of the UEC Client Applications.

## 3.3.2 Logging Off I-Administrator

To log off I-Administrator, perform the following tasks.

1. Click **Logoff** on the **User** menu. The Connect to Universal Enterprise Controller dialog displays.




Figure 3.6 Connect To Universal Enterprise Controller dialog

2. Click the **x** icon in the top, right corner to disconnect from the Universal Enterprise Controller Server on which I-Activity Monitor resides. The Close Monitor dialog then displays.




Figure 3.7 I-Administrator - Close Monitor dialog

3. Click the **Yes** button to log off I-Administrator.

### 3.3.3 Viewing Information About I-Administrator

To view information about the version of I-Administrator to which you have logged in, click **About** on the **Help** menu. The About I-Administrator dialog then displays.



Figure 3.8 UEC - About I-Administrator dialog

## 3.4 Tool Bar

The I-Administrator tool bar provides a set of 12 icons that let you select the I-Administrator functions. [Table 3.2](#), below, identifies these icons.

Icon	Description
 Add User	Add a UEC user. (See <a href="#">Section 3.5 Adding a User.</a> )
 Edit User	Edit a UEC user. (See <a href="#">Section 3.6 Editing a User.</a> )
 Delete User	Delete a UEC user. (See <a href="#">Section 3.7 Deleting a User.</a> )
 Add Group	Add a group of UEC Agents or SAP systems. (See <a href="#">Section 3.8 Adding a Group.</a> )
 Edit Group	Edit a group of UEC Agents or SAP systems. (See <a href="#">Section 3.9 Editing a Group.</a> )
 Delete Group	Delete a group of UEC gents or SAP systems. (See <a href="#">Section 3.10 Deleting a Group.</a> )
 Add Agent	Add an Agent. (See <a href="#">Section 3.11 Adding an Agent.</a> )
 Edit Agent	Edit an Agent. (See <a href="#">Section 3.12 Editing an Agent.</a> )





Icon	Description
 Delete Agent	Delete an Agent. (See Section <a href="#">3.13 Deleting an Agent.</a> )
 Add SAP System	Add an SAP system. (See Section <a href="#">3.14 Adding an SAP System.</a> )
 Edit SAP System	Edit an SAP system. (See Section <a href="#">3.15 Editing an SAP System.</a> )
 Delete SAP System	Delete an SAP system. (See Section <a href="#">3.16 Deleting an SAP System.</a> )

Table 3.2 I-Administrator - Tool Bar Icons

**Note:** The **Edit** and **Delete** icons for a database item (user, group, Agent, or SAP system) are enabled only when a specific item of that type is selected in the Navigation tree or Summary table.

## 3.5 Adding a User

Perform the following steps to add a UEC user.

1. Display the **Add User** dialog (Figure 3.9, below) either by:
  - Clicking **Add User** icon on the I-Administrator tool bar.
  - Clicking on **Users** in the UEC Navigation tree and then clicking on the **Add** button that displays when you right-click anywhere in the Navigation tree.



Figure 3.9 I-Administrator - Add User Dialog

2. Enter a **Name** to identify the user in the UEC database. The user must use this name to log in to any of the UEC Client Applications.  
Note: User names and passwords are case-sensitive.  
Duplicate user names are not allowed.
3. Select a method of **Authentication**: UEC or OS.
  - If you select **OS**, the **Name** and **Password** must be the same as those defined on the operating system where UEC is installed.
  - If you select **UEC**, the login requires the password as defined for the user in the UEC database.

4. If you selected UEC, enter a **Password** and then, at **Verify**, reenter the password. If you selected **OS** in Step 3, **Password** is disabled. The OS method provides authentication on the operating system where UEC is executing. Therefore, the password entry is unnecessary.
5. If you want to select permissions for the user, click the **User Access** button. The User Access dialog displays (see Section [3.5.1 Assigning User Permissions](#)).  
After you select permissions for this user, you are returned to the Add User dialog.
6. If you want to assign one or more Agent groups to the user, click the **Agent Group Access List** button. The Agent Group Access List dialog displays (see Section [3.5.2 Assigning Agent Groups to a User](#)).  
After you assign Agent groups to this user, you are returned to the Add User dialog.
7. If you want to assign the user I-Management Console access to the one or more Agent configurations, click the **Configuration Access List** button. The Configuration Access List dialog displays (see Section [3.5.3 Assigning Configuration Access to a User](#)).  
After you assign configurations to this user, you are returned to the Add User dialog.  
**Note:** The **Configuration Access List** button is enabled only if you have selected **Manage Configurations** in the User Access dialog ([Figure 3.10](#)).
8. Click the **Save** button to add the new user in the UEC database (or click the **Cancel** button to exit the Add User dialog without adding the user to the UEC database).

## 3.5.1 Assigning User Permissions

The User Access dialog (Figure 3.10, below) lets you assign permissions to a user.

To display the User Access dialog, click the **User Access** button on the Add User dialog (Figure 3.9) or the Edit User dialog (Figure 3.13).




Figure 3.10 I-Administrator - User Access Dialog

1. Select **Administer UEC** to permit the user to access I-Administrator.
2. Select **Monitor Activity** to permit the user to access I-Activity Monitor.
3. Select **Stop Components** to permit the user to stop a component using I-Activity Monitor.
4. Select **Manage Configuration** to permit the user to access the I-Management Console.
5. Select **Commit Configuration** to permit the user to commit configuration values and profiles to Agents in I-Management Console.
6. Select **Configurations**, and then either of the following, to permit the user access to Agent configurations and profiles in I-Management Console:
  - **Read Only**: User can view configurations and profile values.
  - **Edit**: User can alter configuration and profile values.
7. Select **View Commit Summary** to permit the user to view the Commit Summary table in I-Management Console.
8. Select **View Commit Detail** to permit the user to view the detail of a selected commit in I-Management Console.



9. Select **Cancel Commit** to permit the user to cancel a commit in I-Management Console.
10. Click the **OK** button to accept the selections on this dialog and return to the previous dialog (or click the **Cancel** button to exit the dialog without accepting the selections). Only when you click the **Save** button on the Add User or Edit User dialog are the selections saved.

## 3.5.2 Assigning Agent Groups to a User

The Agent Group Access List dialog lets you assign groups of Agents and/or SAP systems to a user.

To display the Agent Group Access List dialog (Figure 3.11, below) click the **Agent Group Access List** button on the Add User dialog (Figure 3.9) or the Edit User dialog (Figure 3.13).




Figure 3.11 I-Administrator - Agent Group Access List

The **Available Groups** window identifies all currently defined groups that have not been assigned to the user.

The **Assigned Groups** window identifies all currently defined groups that have been assigned to the user.

1. Double-click a group to move it from one window to another — OR:
  - a. Click on a group (or use the **Ctrl** key to click on more than one group).
  - b. Click the **Assign** button to move the selected group(s) to the Assigned Groups window; click the **Remove** button to move the selected group(s) to the Available Groups window.
2. Click the **Assign All** button to move all Available Groups to the Assigned Groups window.
3. Click the **Remove All** button to move all Assigned Groups to the Available Groups window.
4. Click the **OK** button to save the selected assignments and returns you to the previous dialog (or click the **Cancel** button to exit the dialog without saving the selections).

### 3.5.3 Assigning Configuration Access to a User

The Configuration Access List dialog lets you assign user access to one or more Indesca or Infitran configurations.

To display the Configuration Access List dialog (Figure 3.12, below), click the **Configuration Access List** button on the Add User dialog (Figure 3.9) or the Edit User dialog (Figure 3.13).

Note: The **Configuration Access List** button is enabled only if you have selected **Manage Configurations** in the User Access dialog (Figure 3.10).




Figure 3.12 I-Administrator - Configuration Access List

The Available Configurations window identifies all currently available configurations.

The Accessible Groups window identifies all configurations that have been assigned access to the user.

(Click the + icon next to each configurations group in the window to see its list of configurations. Configurations can be added or removed from each list individually or by group.)

1. Click on an Available or Accessible configuration group or individual configuration (or use the **Ctrl** key to click on more than one configuration group and/or individual configuration).
2. Click the **Assign** button to add selected Available Configurations to the Accessible Configurations window; click the **Remove** button to remove selected Accessible Configurations from that window.

3. Click the **Assign All** button to add all configurations to the Accessible Configurations window.
4. Click the **Remove All** button to remove all configurations from the Accessible Configurations window.
5. Click the **OK** button to save the selected assignments and returns you to the previous dialog (or click the **Cancel** button to exit the dialog without saving the selections).

## 3.6 Editing a User

Perform the following steps to edit a UEC user.

1. Select a UEC user to edit either by:
  - a. Double-clicking on a user name in the Navigation tree or the Summary table.
  - b. Clicking on a user name in the Navigation tree or the Summary table and then clicking the **Edit User** icon on the I-Administrator tool bar.
  - c. Clicking on a user name in the Navigation tree and then clicking on the **Edit** button that displays when you right-click anywhere in the Navigation tree.

The **Edit User** dialog displays.



Figure 3.13 I-Administrator - Edit User Dialog

2. Enter and/or edit information as instructed via the Add User Dialog (see Section [3.5 Adding a User](#)).
3. Click the **Save** button to save the changes to the selected user (or click the **Cancel** button to exit the Edit User dialog without editing the user in the UEC database).

## 3.7 Deleting a User

Perform the following steps to delete a UEC user.

1. Select a UEC user to delete either by:
  - a. Clicking on a user name in the Navigation tree or the Summary table and then clicking the **Delete User** icon on the I-Administrator tool bar.
  - b. Clicking on a user name in the Navigation tree and then clicking the **Delete** button that displays when you right-click anywhere in the Navigation tree.

The **Delete User** dialog displays.




Figure 3.14 I-Administrator - Delete User Dialog

2. Click the **Yes** button to delete the selected user (or click the **No** button to retain the user).

## 3.8 Adding a Group

Perform the following steps to add a UEC group.

1. Display the **Add Group** dialog either by:
  - a. Clicking the **Add Group** icon on the I-Administrator tool bar.
  - b. Clicking on **Groups** in the Navigation tree and then clicking on the **Add** button that displays when you right-click anywhere in the Navigation tree.




Figure 3.15 I-Administrator - Add Group Dialog

The **Available Agents** window identifies all currently defined Agents that are available to be assigned to the group. The **Assigned Agents** window identifies all currently defined Agents that have been assigned to the group.

The **Available SAP Systems** window identifies all currently defined SAP systems that are available to be assigned to the group. The **Assigned SAP Systems** window identifies all currently defined SAP systems that have been assigned to the group.

2. Enter a **Name** for the group.  
Note: Group names are case-sensitive.  
Duplicate group names are not allowed.
3. Enter a **Description** of the group.
4. Assign Agents to the group by moving them to the **Assigned Agents** window. Either:
  - a. Double-click on an Agent in the **Available Agents** window.
  - b. Click on an Agent in the **Available Agents** window (or use the **Ctrl** key to click on more than one Agent) and then click the **Assign** button.
  - c. Click the **Assign All** button.
5. Remove Agents from the group by moving them to the **Available Agents** window. Either:
  - a. Double-click on an Agent in the **Assigned Agents** window.
  - b. Click on an Agent in the **Assigned Agents** window (or use the **Ctrl** key to click on more than one Agent) and then click the **Remove** button.
  - c. Click the **Remove All** button.
6. Assign SAP systems to the group by moving them to the **Assigned SAP Systems** window. Either:
  - a. Double-click on an SAP system in the **Available SAP Systems** window.
  - b. Click on an SAP system in the **Available SAP Systems** window (or use the **Ctrl** key to click on more than one SAP system) and then click the **Assign** button.
  - c. Click the **Assign All** button.
7. Remove SAP systems from the group by moving them to the **Available SAP Systems** window. Either:
  - a. Double-click on an SAP system in the **Assigned SAP Systems** window.
  - b. Click on an SAP system in the **Assigned SAP Systems** window (or use the **Ctrl** key to click on more than one SAP system) and then click the **Remove** button.
  - c. Click the **Remove All** button.
8. Click the **Save** button to add the new group and return you to the previous dialog (or click the **Cancel** button to cancel the addition of this new group).



## 3.9 Editing a Group

Perform the following steps to edit a UEC group.

1. Select a UEC group either by:
  - a. Double-clicking on a group name in the Navigation tree or the Summary table.
  - b. Clicking on a group name in the Navigation tree or the Summary table and then clicking the **Edit Group** icon on the I-Administrator tool bar.
  - c. Clicking on a group name in the Navigation tree and then clicking on the **Edit** button that displays when you right-click anywhere in the Navigation tree.

The **Edit Group** dialog displays.




Figure 3.16 I-Administrator - Edit Group Dialog

2. Enter and/or edit information for the group in the same way as instructed for adding a group (see Section [3.8 Adding a Group](#)).
3. Click the **Save** button to save the changes to the selected group (or click the **Cancel** button to exit the dialog without editing the group in the UEC database).

## 3.10 Deleting a Group

Perform the following steps to delete a UEC group.

1. Select a UEC group to delete either by:
  - a. Clicking on a group name in the Navigation tree or the Summary table and then clicking the **Delete Group** icon on the I-Administrator tool bar.
  - b. Clicking on a group name in the Navigation tree and then clicking the **Delete** button that displays when you right-click anywhere in the Navigation tree.

The **Delete Group** dialog displays.




Figure 3.17 I-Administrator - Delete Group Dialog

2. Click the **Yes** button to delete the selected group (or click **No** to retain the group).

## 3.1.1 Adding an Agent

Perform the following steps to add a UEC Agent.

1. Display the **Add Agent** dialog (Figure 3.18, below) either by:
  - a. Clicking **Add Agent** icon on the I-Administrator tool bar.
  - b. Clicking on **Agents** in the Navigation tree and then clicking on the **Add** button that displays when you right-click anywhere in the Navigation tree.

The screenshot shows the 'Add Agent' dialog box with the following fields and options:

- Name: [Text Field]
- Description: [Text Field]
- Address: [Text Field]
- Port: [Text Field] (7887)
- Polling Interval:  Use Default [Text Field] seconds
- Save Persistent Events:  Yes  No
- Delete Events:  Use Default  Yes  No
- Post Alerts:  Yes  No
- Set Managed Mode:  Managed Mode:  Yes  No
- Available Groups: [List Box] (Secret Agents)
- Assigned Groups: [List Box] (All Agents)
- Buttons: Assign, Assign All, Remove, Remove All, Add Group, Save, Save & New, Cancel

Figure 3.18 I-Administrator - Add Agent Dialog

The **Available Groups** window identifies all currently defined groups to which the Agent can be assigned.

The **Assigned Groups** window identifies all currently defined groups to which the Agent currently is assigned. (Every Agent automatically is assigned to the **All Agents** group.)

2. Enter a **Name** for the Agent.  
Note: Agent names are case-sensitive.  
Duplicate Agent names are not allowed.
3. Enter a **Description** of the Agent.
4. Enter the **Address** of the Agent (the host name or IP address where the Agent is running).
5. Enter the **Port** (listening port) of the Agent.
6. Select a **Polling Interval** for the Agent (the interval of time that UEC will use to poll that Agent). Either:
  - a. Select **Use Default** for UEC to poll the Agent at the interval specified by the UEC **POLLING\_INTERVAL** configuration option.
  - b. De-select **Use Default** and enter the number of seconds at which to poll the Agent.
7. For **Save Persistent Events**, select whether or not you want UEC to save persistent events of the Agent to the event database (**Yes** or **No**).
8. For **Delete Events**, specify whether or not UEC is to notify the Agent to delete its events. Either:
  - a. Select **Use Default** for UEC to use the UEC **DELETE\_EVENTS\_ON\_BROKER** configuration option to determine if events are to be deleted on the Agent.
  - b. Select **Yes** to delete events on an Agent.
  - c. Select **No** to not delete events on an Agent.
9. For **Post Alerts**, select whether or not you want to send alerts to the system console for this Agent (**Yes** or **No**).
10. For **Set Managed Mode**, select whether or not you want changes to the configuration options for that Agent and its applications only to be applied through I-Management Console (**Yes** or **No**).
11. Assign the Agent to one or more groups by moving those groups from the **Available Groups** window to the **Assigned Groups** window. Either:
  - a. Double-click on a group in the **Available Groups** window.
  - b. Click on a group in the **Available Groups** window (or use the **Ctrl** key to click on more than one group) and then click the **Assign** button.
  - c. Click the **Assign All** button.
12. Remove the Agent from one or more groups by moving those groups from the **Assigned Groups** window to the **Available Groups** window. Either:
  - a. Double-click on a group in the **Assigned Groups** window.
  - b. Click on a group in the **Assigned Groups** window (or use the **Ctrl** key to click on more than one group) and then click the **Remove** button.
  - c. Click the **Remove All** button.

13. If you want to add a new group (to which this new Agent automatically will be added), click the **Add Group** button. The Add Group dialog displays.




Figure 3.19 I-Administrator - Add Group dialog

- Enter a name and (optionally) a description for the group, and then click the **OK** button.
14. Click the **Save** button to add the new Agent and return you to the previous dialog (or click the **Cancel** button to exit the Add Agent dialog without adding the Agent to the UEC database).
- Note:** If you want to add the new Agent and immediately add another Agent, click the **Save & New** button. The Add Agent dialog remains displayed.

## 3.12 Editing an Agent

Perform the following steps to edit a UEC Agent.

1. Select a UEC Agent to edit either by:
  - a. Double-clicking on an Agent name in the Navigation tree or the Summary table.
  - b. Clicking on an Agent name in the Navigation tree or the Summary table and then clicking the **Edit Agent** icon on the I-Administrator tool bar.
  - c. Clicking on an Agent name in the Navigation tree and then clicking on the **Edit** button that displays when you right-click anywhere in the Navigation tree.

The **Edit Agent** dialog displays.

The **Edit Agent** dialog box contains the following fields and controls:

- Name: localhost
- Description: (empty)
- Address: localhost
- Port: 7887
- Polling Interval:  Use Default  seconds
- Save Persistent Events:  Yes  No
- Delete Events:  Use Default  Yes  No
- Post Alerts:  Yes  No
- Set Managed Mode:  Managed Mode:  Yes  No
- Available Groups: (empty list)
- Assigned Groups: All Agents, Secret Agents
- Buttons: Assign, Assign All, Remove, Remove All, Add Group (highlighted), Save, Cancel

Figure 3.20 I-Administrator - Edit Agent Dialog

2. Enter and/or edit information for the Agent in the same way as instructed for adding an Agent (see Section [3.11 Adding an Agent](#)).
3. Click the **Save** button to save the changes to the selected Agent (or click the **Cancel** button to exit the dialog without editing the Agent in the UEC database).



## 3.13 Deleting an Agent

Perform the following steps to delete a UEC Agent.

1. Select a UEC Agent to delete either by:
  - a. Clicking on an Agent name in the Navigation tree or the Summary table and then clicking the **Delete Agent** icon on the I-Administrator tool bar.
  - b. Clicking on an Agent name in the Navigation tree and then clicking the **Delete** button that displays when you right-click anywhere in the Navigation tree.

The **Delete Agent** dialog displays.




Figure 3.21 I-Administrator - Delete Agent Dialog

2. Click the **Yes** button to delete the selected Agent.

## 3.14 Adding an SAP System

Perform the following steps to add an SAP system.

1. Display the **Add SAP System** dialog (Figure 3.22, below) either by:
  - a. Clicking **Add SAP System** icon on the I-Administrator tool bar.
  - b. Clicking on **SAP Systems** in the Navigation tree and then clicking on the **Add** button that displays when you right-click anywhere in the Navigation tree.

The screenshot shows the 'Add SAP System' dialog box with the following fields and controls:

- Name: [Text Field]
- Description: [Text Field]
- ASHOST: [Text Field]
- Client: [Text Field] SapLang: [Text Field]
- SysNR: [Text Field] XMI Audit Level: [Text Field]
- User ID: [Text Field]
- Password: [Text Field]
- Verify: [Text Field]
- Post Alerts:  Yes  No
- Available Groups: [List Box containing 'Secret Agents']
- Assigned Groups: [List Box containing 'All SAP Systems']
- Buttons: Assign, Assign All, Remove, Remove All, Add Group, Save, Save & New, Cancel

Figure 3.22 I-Administrator - Add SAP System Dialog

The Available Groups window identifies all currently defined groups to which the SAP system can be assigned.

The Assigned Groups window identifies all currently defined groups to which the SAP system currently is assigned. (Every SAP system automatically is assigned to the All SAP Systems group.)

2. Enter a **Name** for the SAP system.

Note: SAP system names are case-sensitive.

Duplicate SAP system names are not allowed.

3. Enter a **Description** of the SAP system.
4. For **ASHOST**, specify the host name of a specific SAP application server.
5. For **Client**, specify the SAP logon client for the connection (for example, 850).
6. For **SapLang**, specify a SAP logon language. (Messages coming from the SAP system will be in this language, whenever possible.)
7. For **SysNR**, specify the SAP system number of the SAP system to connect to.
8. Specify the **XMI Audit Level** to be used for the execution of SAP function modules on the SAP system.  
Valid values are 0, 1, 2, and 3. The amount of information logged in the XMI log (on the SAP system) increases with higher audit level values.
9. For **User ID**, specify the SAP logon user for this connection.
10. For **Password**, specify the SAP logon password for this connection.
11. For **Verify**, reenter the SAP logon password.
12. For **Post Alerts**, specify whether or not alerts associated with this SAP connection will be posted to the system console (**Yes** or **No**).
13. Assign the SAP system to one or more groups by moving those groups from the **Available Groups** window to the **Assigned Groups** window.  
Either:
  - a. Double-click on a group in the **Available Groups** window.
  - b. Click on a group in the **Available Groups** window (or use the **Ctrl** key to click on more than one group) and then click the **Assign** button.
  - c. Click the **Assign All** button.
14. Remove the SAP system from one or more groups by moving those groups from the **Assigned Groups** window to the **Available Groups** window.  
Either:
  - a. Double-click on a group in the **Assigned Groups** window.
  - b. Click on a group in the **Assigned Groups** window (or use the **Ctrl** key to click on more than one group) and then click the **Remove** button.
  - c. Click the **Remove All** button.

15. If you want to add a new group (to which this new SAP system automatically will be added), click the **Add Group** button. The Add Group dialog (Figure 3.23, below) displays.




Figure 3.23 I-Administrator - Add Group Dialog

Enter a name and (optionally) a description for the group, and then click the **OK** button.

16. Click the **Save** button to add the new SAP system and return you to the previous dialog (or click the **Cancel** button to exit the Add SAP system dialog without adding the SAP system to the UEC database).

**Note:** If you want to add the new SAP system and immediately add another SAP system, click the **Save & New** button. The Add SAP System dialog remains displayed.

## 3.15 Editing an SAP System

Perform the following steps to edit an SAP system.

1. Select an SAP system either by:
  - a. Double-clicking on an SAP system name in the Navigation tree or the Summary table.
  - b. Clicking on an SAP system name in the Navigation tree or the Summary table and then clicking the **Edit SAP System** icon on the I-Administrator tool bar.
  - c. Clicking on an SAP system name in the Navigation tree and then clicking on the **Edit** button that displays when you right-click anywhere in the Navigation tree.

The **Edit SAP System** dialog displays.

The screenshot shows the 'Edit SAP System' dialog box with the following fields and values:

- Name: #1 SAP system
- Description: first SAP system
- ASHOST: host
- Client: 800
- SapLang: en
- SysNR: 88
- XMI Audit Level: 3
- User ID: 5
- Password: \*\*\*
- Verify: \*\*\*
- Post Alerts:  Yes  No

Below the 'Post Alerts' section are two list boxes:

- Available Groups: (empty)
- Assigned Groups: All SAP Systems, big group

At the bottom of the dialog are the following buttons:

- Assign
- Assign All
- Remove
- Remove All
- Add Group
- Save
- Cancel

Figure 3.24 I-Administrator - Edit SAP System Dialog

2. Enter and/or edit information for an SAP system in the same way as instructed for adding an SAP system (see Section [3.14 Adding an SAP System](#)).
3. Click the **Save** button to save the changes to the selected SAP system (or click the **Cancel** button to exit the dialog without editing the SAP system in the UEC database).

## 3.16 Deleting an SAP System

Perform the following steps to delete an SAP system.

1. Select an SAP system either by:
  - a. Clicking on an SAP system name in the Navigation tree or the Summary table and then clicking the **Delete SAP System** icon on the I-Administrator tool bar.
  - b. Clicking on an SAP system name in the Navigation tree and then clicking the **Delete** button that displays when you right-click anywhere in the Navigation tree.The **Delete SAP System** dialog displays.




Figure 3.25 I-Administrator - Delete SAP System Dialog

2. Click the **Yes** button to delete the selected SAP system.

# I-Activity Monitor

## 4.1 Overview

When an Agent or SAP system is added to Universal Enterprise Controller (UEC), via the [I-Administrator](#) application, UEC is able to collect information about that Agent or SAP system.

The I-Activity Monitor connects to UEC. It displays information about the current status, posted alerts, and job and file activity for all Agents, and the current status and posted alerts for all SAP systems, being monitored by UEC throughout an enterprise.

This chapter provides information on using I-Activity Monitor.

### 4.1.1 I-Activity Monitor Tasks

I-Activity Monitor lets you perform the following tasks:

- Monitor the status and detailed job and file activity of Agents throughout an enterprise.
- Monitor SAP server status for SAP systems throughout an enterprise.
- View alerts posted for Agents and SAP systems.
- Stop any Indesca or Infitran component from running (if it is a component of an Agent being polled by UEC).

**Note:** You must have agent-monitoring permission with UEC in order to log in using I-Activity Monitor and, optionally, to stop running components through I-Activity Monitor.



## 4.2 Using I-Activity Monitor

When you log in to I-Activity Monitor, (see Chapter 2 [Accessing UEC Client Applications](#)) the I-Activity Monitor screen displays ([Figure 4.26](#), below).

The screenshot shows the I-Activity Monitor application window. The interface is divided into several sections:

- Region 1:** The menu bar at the top, containing 'User', 'View', and 'Help'.
- Region 2:** A toolbar below the menu bar with several icons for file operations and system management.
- Region 3:** A vertical navigation pane on the left with buttons for 'Alerts', 'Jobs', 'Files', and 'Systems'.
- Region 4:** A tree view in the left pane showing a hierarchy of 'Systems', 'Agents', 'SAP Systems', and 'System Groups'.
- Region 5:** The main 'Agents' table, which lists various agents with columns for Agent Name, Description, Version, IP Address, and TC. The agent 'qa-aix51' is selected.
- Region 6:** The 'Agent Properties' table below the main table, showing detailed information for the selected agent 'qa-aix51', such as its version (3.1.1 Level 8 Release Build 143), host name, IP address, and status.

At the bottom of the window, a status bar indicates: 'Connected to qa-zos15. Logged on as admin.'

Figure 4.26 I-Activity Monitor screen

See Section 4.2.1 [I-Activity Monitor Screen Information](#) for a description of the six regions identified in [Figure 4.26](#).

## 4.2.1 I-Activity Monitor Screen Information

---

The I-Activity Monitor screen ([Figure 4.26](#)) contains the following regions:

- **Menu Bar (1)**  
The menu bar lets you perform tasks common to all I-Activity Monitor activities (see [Section 4.3 Menu Bar](#)).
- **Tool Bar (2)**  
The tool bar lets you perform tasks common to all I-Activity Monitor activities and tasks specific to individual activities (see [Section 4.4 Tool Bar](#)).
- **Filter Group Panel (3)**  
The Filter Group panel contains buttons that let you select a category of UEC activity (see [Section 4.5 Filter Group Panel](#)).
- **Filter Tree (4)**  
The Filter tree displays the types of activities for the activity category selected in the Filter Group panel (see [Section 4.6 Filter Tree](#)).
- **Data Table (5)**  
The Data table displays a list of all activities for the activity type selected in the Filter tree (see [Section 4.7 Data Table](#)).
- **Data Details Table (6)**  
The Data Details table displays detailed information about an item select in the Data table. There are two types of Data Details table:
  - Properties table displays a list of all fields, and their values, for an item selected in the Data table (see [Section 4.8.1 Properties Table](#))
  - Jobs table displays a list of all current jobs for an Agent selected in the Data table (see [Section 4.8.2 Jobs Table](#)).

**Note:** In the I-Activity Monitor screen that displays when you log in:

- **Agents** is pre-selected in the Filter tree.
- **Systems** is pre-selected in the Filter Group panel.
- Data Details table does not display.

## 4.3 Menu Bar

[Table 4.3](#), below, identifies the items on each menu of the menu bar at the top of the I-Activity Monitor screen (see [Figure 4.26](#)).

The table provides a link to the task associated with each item.

Menu / Item	Description
User / Change Password	Change UEC Client Applications log in password. (See Section <a href="#">4.9.1 Changing a Password</a> .)
User / Save Layout	Save layout of currently displayed Data table. (See Section <a href="#">Saving a Data Table Layout</a> .)
User / Reset Default Layout	Reset layout of currently displayed Data table to its default layout. (See Section <a href="#">Resetting the Default Data Table Layout</a> .)
User / Set Initial Filter Group	Set the currently selected Filter group as the default display upon log in. (See Section <a href="#">4.9.4 Setting a Filter Group as Default Display</a> .)
User / Logoff	Log off I-Activity Monitor. (See Section <a href="#">4.9.5 Logging Off I-Activity Monitor</a> .)
View / Object Properties	Display the Properties table for an item selected in the Data table. (See Section <a href="#">4.7.6 Displaying a Properties Table</a> .)
Help / About	View information about I-Activity Monitor. (See Section <a href="#">4.9.6 Viewing Information About I-Activity Monitor</a> .)

Table 4.3 I-Activity Monitor - Menu Selections








## 4.4 Tool Bar

The tool bar at the top of the I-Activity Monitor screen (see [Figure 4.26](#)) provides icons that let you select tasks for the four filter groups listed in the [Filter Group Panel](#).

Some icons display for all filter groups and some icons display only for one or more specific filter groups.

[Table 4.4](#), below, identifies the icons that display for the different filter groups and provides a link to the task associated with each item.

Most of the icons are enabled only as appropriate for the region being accessed.

Icon	Description
<b>Alerts, Jobs, Files, and Systems</b>	
	<b>Save Layout</b> Save layout of currently displayed Data table. (See <a href="#">Saving a Data Table Layout</a> .)
	<b>Properties</b> Display the Properties table for a selected entry in the Data table. (See <a href="#">Section 4.7.6 Displaying a Properties Table</a> .)
<b>Jobs</b>	
	<b>Refresh Job Data</b> Update displayed information for the job currently selected in the Data table. (See <a href="#">Section 4.7.5 Updating Data Table Information</a> .)
	<b>Stop Component</b> Stop an active or restarted component. (See <a href="#">Section 4.10 Stopping a Component</a> .)
<b>Jobs / Indesca Jobs</b>	
	<b>Show Restart History</b> Display the history of restarts for the select job.
<b>Jobs / Infitran Jobs</b>	
	<b>Show File Transfers</b> Display the file transfers.
	<b>Show Commands</b> Display the commands.





Icon	Description
<b>Systems / Agents</b>	
	<p><b>Update Agent Info</b>                      Update displayed information for the Agent currently selected in the Data table.                      (See Section <a href="#">4.7.5 Updating Data Table Information.</a>)</p>
	<p><b>Show Indesca Jobs</b>                      Display Indesca jobs for the Agent currently selected in the Data table.                      (See Section <a href="#">4.8.2 Jobs Table.</a>)</p>
	<p><b>Show Infitran Jobs</b>                      Display Infitran jobs for the Agent currently selected in the Data table.                      (See Section <a href="#">4.8.2 Jobs Table.</a>)</p>
<b>Systems / SAP Systems</b>	
	<p><b>Update SAP System Info</b>                      Update the information for the currently selected SAP system in the Data table.                      (See Section <a href="#">4.7.5 Updating Data Table Information.</a>)</p>

Table 4.4 I-Activity Monitor - Tool Bar Icons

## 4.5 Filter Group Panel

The Filter Group panel ([Figure 4.27](#)) is a group of four buttons. Each button represents a category of Indesca and Infitran information that is available for viewing.



Figure 4.27 I-Activity Monitor - Filter Group Panel

Click on a button in the Filter Group panel to populate the [Filter Group Panel](#) with filters for that category:

Section [4.5 Filter Group Panel](#) provides a description of the information that displays for each category:

- [Alerts Category](#)
- [Jobs Category](#)
- [Files Category](#)
- [Systems Category](#)

## 4.6 Filter Tree

The Filter tree (Figure 4.28, below) displays a list of filters (that is, types of filtered information) for the category of Indesca or Infitran information currently selected in the Filter Group Panel.




Figure 4.28 I-Activity Monitor - Filter Tree

In this example, the Filter tree displays filters for the Systems category, indicating that the **Systems** button was clicked in the Filter Group Panel.

When you click a filter in the Filter tree, the entry is highlighted — Agent(s), in this example — and information for that filter displays in the Data Table.

### 4.6.1 Filter Tree Icons

Table 4.5, below, identifies the icons that are used in the Filter Group Panel.




Icon	Description
	Icon that represents a filter group. It is not a selectable filter option.
	Icon that represents a sub-group of a filter group. It is not a selectable filter group.
	Icon that represents a selectable filter. Selecting an item in the filter tree with this icon populates the Data table with data that matches the filter criteria.

Table 4.5 I-Activity Monitor - Filter Tree / Icons

## 4.6.2 Alerts Category

Clicking the **Alerts** button in the **Filter Group Panel** populates the **Filter Tree** with the filters shown in **Figure 4.29**, below.

Clicking on an option in the **Filter Tree** populates the **Data Table** with the information described in **Figure 4.29** for that filter.




Figure 4.29 I-Activity Monitor - Filter Tree / Alerts Category Filters

## Alert Types

UEC creates three types of alerts:

- **Agent Down**  
UEC was unable to establish a connection with the broker on the last poll attempt.
- **Component Disconnected**  
Server is not connected to the Manager. This occurs when a network error has occurred, the manager halted, or the manager host halted. The server is executing with either the network fault tolerant protocol, is restartable, or both.  
  
Note: The Server cannot determine whether or not the Manager is still executing because it cannot communicate with it.
- **Component Orphaned**  
Manager has terminated. The manager sends a termination message to the server to notify it of its termination prior to terminating. This state only occurs if the server is restartable.



## 4.6.3 Jobs Category

Clicking the **Jobs** button in the **Filter Group Panel** populates the **Filter Tree** with the filters shown in **Figure 4.30**, below.

Clicking on an option in the **Filter Tree** populates the **Data Table** with the information described in **Figure 4.30** for that filter.



	<p><b>Jobs</b></p> <p><b>Indesca Jobs - All</b> Indesca jobs monitored by UEC.</p> <p><b>Active</b> All Indesca jobs monitored by UEC that are currently in an active state.</p> <p><b>Restarted</b> All Indesca jobs monitored by UEC that have been restarted and completed.</p> <p><b>Completed</b> All Indesca jobs being monitored by UEC that have completed successfully.</p> <p><b>Failed</b> All Indesca jobs being monitored by UEC that have completed with an error status.</p> <p><b>Infitran Jobs - All</b> Infitran jobs monitored by UEC.</p> <p><b>Active</b> All Infitran jobs monitored by UEC that are currently in an active state.</p> <p><b>Completed</b> All Infitran jobs being monitored by UEC that have completed successfully.</p> <p><b>Failed</b> All Infitran jobs being monitored by UEC that have completed with an error status.</p>
--	---

Figure 4.30 I-Activity Monitor - Filter Tree / Jobs Category Filters

## 4.6.4 Files Category

Clicking the **Files** button in the **Filter Group Panel** populates the **Filter Tree** with the filters shown in **Figure 4.31**, below.

Clicking on an option in the **Filter Tree** populates the **Data Table** with the information described in **Figure 4.31** for that filter.



**Files**

- File Transfers - All
  - Active
  - Completed
  - Failed

**Alerts**

**Jobs**

**Files**

**Systems**

**Files – All**  
All files monitored by UEC.

**Active**  
All files monitored by UEC that are currently in an active state (for example: file being transferred, script being executed).

**Completed**  
All files being monitored by UEC that have completed successfully (script, file transfer).

**Failed**  
All files being monitored by UEC that have completed with an error status (script, file transfer).

Figure 4.31 I-Activity Monitor - Filter Tree / Files Category Filters

## 4.6.5 Systems Category

Clicking the **Systems** button in the **Filter Group Panel** populates the **Filter Tree** with the filters shown in **Figure 4.32**, below.

Clicking on an option in the **Filter Tree** populates the **Data Table** with the information described in **Figure 4.32** for that filter.






	<p><b>Systems</b></p> <p><b>Agents</b> All Agents assigned to UEC.</p> <p><b>SAP Systems</b> All SAP Systems assigned to UEC.</p> <p><b>System Groups</b> All groups defined to UEC via I-Administrator. Two groups are pre-defined to UEC and, therefore, always available:</p> <p><b>All Agents</b></p> <p><b>All SAP Systems</b> Any number of user-defined groups can be displayed here. Selecting a group under System Groups will further populate the filter tree with the systems (Agent and/or SAP) that have been defined to that group.</p>
<p> Alerts</p> <p> Jobs</p> <p> Files</p> <p> Systems</p>	

Figure 4.32 I-Activity Monitor - Filter Tree / Systems Category Filters

## 4.7 Data Table

The Data table displays data returned from UEC that meets the criteria of the currently selected filter in the [Filter Tree](#). The data is presented in near real-time. As UEC receives new information that meets the filter criteria, it is passed on to I-Activity Monitor and displayed in the Data table.

For example, in [Figure 4.33](#), below, the Data table contains an entry for all Agents currently assigned to UEC, since **Agents** had been selected in the [Filter Tree](#).

Agents							Count: 63
Agent Name		Contains					
Agent Name	Description	Version	IP Address	TCP Port	Status		
Full10		NA	Full10	7887	Unavailable	▲	
Full10-311		NA	Full10	7887	Unavailable		
os390new		NA	os390new	4311	Unavailable		
os390new-311		NA	os390new	4311	Unavailable		
qa-aix42		NA	qa-aix42	7887	Unavailable		
qa-aix43		3.1.1 Level 8 Release Build ...	qa-aix43	7887	Available		
qa-aix51		3.1.1 Level 8 Release Build ...	qa-aix51	7887	Available		
qa-aix53		3.2.0 Level 6 Release Build ...	qa-aix53	7887	Available		

Figure 4.33 I-Activity Monitor - Data Table

The Data table header identifies the currently selected filter and the number of matches in the table for that filter. (In [Figure 4.33](#), **Agents** was the selected filter, and the table lists three matches.)

### NA Values














In the Data table, a value of **NA** (Not Available) displays in any field that has not been populated with event data. That is, UEC has not received the information (a UES event) required to supply a value for that field.

The reason for this could be:

- Lack of visibility to a Broker (for example, Broker may be down).
- Component's `ACTIVITY_MONITORING` option may be set to `no`.

## 4.7.1 Data Table Icons

Each item in the Data table is preceded by an icon that indicates the status of that item. [Table 4.6](#), below, identifies and describes these icons.

Icon	Description
<b>Alerts</b>	
	Alert An alert has occurred on the system specified in the item.
<b>Jobs / Universal Jobs</b>	
	Active Job has not yet completed; all visible components (manager and servers) of the job are running.
	Completed At least one component of the job has completed without error.
	Failed Job has been cancelled or it has completed with an error status (return code is not 0).
	Active Restart Restarted job has not yet completed; all visible components (manager and servers) of the job are running.
	Completed Restart Restarted job has completed without error.
	Failed Restart Restarted job has been cancelled or it has completed with an error status (return code is not 0).
<b>Files</b>	
	Active Infitran file transfers that are active.
	Completed Infitran file transfers that have completed.
	Failed Infitran file transfers that have failed.
<b>Systems / Agents</b>	
	Agent Running Agent is up and responding.
	Agent Unreachable Agent cannot be reached by UEC.
	Agent Not Initialized Agent has not yet been polled by UEC.




Icon	Description
<b>Systems / SAP Systems</b>	
	System Running SAP system is up and responding.
	SAP System Unreachable SAP system cannot be reached by UEC.
	SAP System Not Initialized SAP system has not yet been polled by UEC.

Table 4.6 I-Activity Monitor - Data Table / Icons

## Tool Tips

Hold your cursor over any Data table icon to display a tool tip that describes the status represented by that icon.

## 4.7.2 Data Table Filter Tool

The Data table filter tool ([Figure 4.34](#), below), located just below the table header, provides an additional level of filtering that is performed locally.

The filter tool allows you to select specific data for any column of data listed in the table. Any filter that does not contain the specified data is removed from view.




Figure 4.34 I-Activity Monitor - Data Table / Filter Tool

To use the filter tool, perform the following steps:

1. From the first (left-most) drop-down list field, select a column header – for example, **Mgr Agent Name** – from the list of currently displayed columns (see [Section 4.7.4 Customizing Layout of the Data Table](#) for information on displaying columns).
2. From the second drop-down list field, select a filter matching types.
3. In the field on the right, enter any data to be displayed in the selected column. Any item in the Data table that does not contain this filter data in that column is removed from view — immediately and automatically.  
Note: Data entered in this field is case-sensitive.
4. To re-display the original list of matches, delete the data in the field on the right.

[Table 4.7](#), below, identifies the available filter matching types.

Filter Type	Description
==	Displays entries whose data in the selected column is equal to the filter data.
!=	Displays entries whose data in the selected column is not equal to the filter data.
>	Displays entries whose data in the selected column is greater than the filter data.
>=	Displays entries whose data in the selected column is greater than or equal to the filter data.
<	Displays entries whose data in the selected column is less than the filter data.
<=	Displays entries whose data in the selected column is less than or equal to the filter data.

Filter Type	Description
Date Offset	<p>Note: This filter matching type is available only when the column being filtered contains date information.</p> <p>Displays entries whose data in the selected column meets the user-supplied date offset. Date offsets can be back or forward in time in time some number of days, hours, minutes, or seconds.</p> <p>The syntax for the date offset specification is: <code>{- +}n{d h m s}</code></p> <ul style="list-style-type: none"> <li>• "-" indicates an offset in the past. Matches will be made for filtered column values that have a date value greater than "now-offset". The value of "now" is recalculated for each filter operation. Therefore, the filtered contents of the table will always match the user specified offset. In other words, as time changes, items in the table that once matched may no longer match and be removed from the table.</li> <li>• "n" is a user specified number.</li> <li>• "d" (or "D") is used to indicate that the "n" should be calculated as days.</li> <li>• "h" (or "H") is used to indicate that the "n" should be calculated as hours.</li> <li>• "m" (or "M") is used to indicate that the "n" should be calculated as minutes.</li> <li>• "s" (or "S") is used to indicate that the "n" should be calculated as seconds.</li> </ul> <p>For example, a user supplied value of "-5h" will match table items who's filter column date value is 5 hours or less in the past.</p> <p>If the user enters invalid syntax, the background color of the filter text box will turn red and an unfiltered table will be displayed. When the syntax is corrected, the background will return to it's normal color (white).</p>
Contains	<p>Displays entries whose data in the selected column contains the filter data. For example, if the filter data is <b>system</b>, entries containing both <b>test system</b> and <b>demo system</b> in the selected column would display. Similarly, if the filter data is <b>0</b>, entries containing both <b>0</b> and <b>100</b> in the selected column would display.</p>
Wild Cards	<p>Displays entries whose data in the selected column is equal to the filter data, taking into account the special characteristics of wild card characters.</p> <p>Valid wild card characters are * and ? .</p> <ul style="list-style-type: none"> <li>• * (asterisk) will match any character any number of times. So, a filter value of * will match everything. A filter of <b>T*e</b> will match <b>Te</b>, <b>Three</b>, and <b>This is one of three</b>.</li> <li>• ? (question mark) will match any character one time. So, a filter of <b>JOB ? TEST</b> will match <b>JOB A TEST</b>, <b>JOB B TEST</b>, and <b>JOB C TEST</b>.</li> </ul> <p>If a literal interpretation of the wild card characters is required, the characters must be escaped. Wild card characters are escaped by prefixing them with the backslash character ( \ ). So, a filter value of <b>This is ok\?</b> would match <b>This is ok?</b> but would NOT match <b>This is ok. .</b></p>
REGEX	<p>This matching type is for power users. It allows the user to specify a regular expression for the filter value. Regular expressions allow you to create very complex matching criteria. For documentation on the specifics of the regular expression engine used in I-Activity Monitor, refer to the Java documentation at <a href="http://java.sun.com/j2se/1.5.0/docs/api/java/util/regex/Pattern.html">http://java.sun.com/j2se/1.5.0/docs/api/java/util/regex/Pattern.html</a>.</p> <p>If the user enters invalid syntax for the regular expression, the background color of the filter text box will turn red and table will continue to use the last valid filter. When the syntax is corrected, the background will return to it's normal color (white).</p>
BLANK	<p>Displays entries whose selected column is blank. Selecting this filter type will disable and grey out the filter text box (since no user input is required).</p>
NA	<p>Displays entries whose selected column greyed-out <b>NA</b> used to designate fields that have not yet been seeded with a value (value is "Not Available"). Note that the grayed-out <b>NA</b> indicates a lack of value and is different from a blank field and different from a field that actually has a real value of <b>NA</b>.</p>

Table 4.7 Filter Matching Types



---

### 4.7.3 *Sorting Data in the Data Table*

---

Click on a column header in the Data table to sort the data in that column in ascending, descending, or arrival order. Additional clicks let you cycle through the sorting options.

An arrow icon on the column header indicates the sort option currently in effect (no arrow indicates that no sorting is being performed).

Hold down the **Ctrl** key to apply sorts to multiple columns.

The first column clicked is the primary sorting column. Additional sorts are performed within the context of the previously sorted column.

**Note:** The sort indicator icon displayed in the column header gets increasingly smaller with each additional sort. Therefore, the primary sorting column always will have the largest sort indicator icon.

---

## 4.7.4 Customizing Layout of the Data Table

---

You can customize the layout of the Data table for each type of filter.

**Note:** The customization applies only to the logged in user.

- **Reposition a column**  
Click on the column header and drag the column left or right, as desired.
- **Hide a column**  
Place the cursor in between column headers and drag the cursor to the left.
- **Expand a column**  
Place the cursor in between column headers and drag the cursor to the right.
- **Remove a column**  
Right-click on the column header of the column to be removed. On the dialog menu that displays, select **Remove** <column name>.
- **Add a column**  
Right-click on any column header. On the dialog menu that displays, select **Add** <column name>.

### *Saving a Data Table Layout*

To save the layout of the currently displayed Data table, either:

- Click **Save Layout** on the I-Activity Monitor **User** menu.
- Click the **Save Layout** icon on the I-Activity Monitor tool bar.

The customized layout of the Data table will display when the current user logs in to any I-Activity Monitor client application that connects to a common UEC.

### *Resetting the Default Data Table Layout*

To reset the currently displayed Data table to its default layout, click **Reset Default Layout** on the I-Activity Monitor **User** menu. The Data table immediately redisplay in its default layout.

---

## 4.7.5 Updating Data Table Information

---

To update the displayed information for items in the Data table, either:

### Jobs

- Click on the entry and then click the **Refresh job data** icon on the I-Activity Monitor tool bar.
- Right-click on the entry and then click **Refresh job data** on the displayed pop-up.

### Systems

- Click on the entry and then click the **Update <activity> Info** icon on the I-Activity Monitor tool bar.
- Right-click on the entry and then click **Update <activity> Info** on the displayed pop-up.

(Since UEC relies on polling its agent list periodically to get the state of the Agents, the information displayed in I-Activity Monitor may not be timely enough for some situations.)

---

## 4.7.6 Displaying a Properties Table

---

To display the Properties table for an item in the Data table, either:

- Right-click on the item and then, from the displayed dialog, click **<Filter Name> Properties**.
- Click on the item and then either:
  - Click the **Properties** icon on the I-Activity Monitor tool bar.
  - Select **Object Properties** from the View menu on the I-Activity Monitor menu bar.

The Properties table then displays for that item (see Section [4.8.1 Properties Table](#)).

---

## 4.7.7 Displaying a Jobs Table

---

To display the Jobs table for an Agent listed in the Data table, either:

- Click on the agent and then click the **Show <job type> Jobs** icon on the I-Activity Monitor tool bar.
- Right-click on the agent and then click **Show <job type> Jobs** on the displayed pop-up.

The Jobs table then displays (see Section [4.8.2 Jobs Table](#)).

## 4.8 Data Details Table

The Data Details table displays below the Data table. It contains detailed information for an item selected in the [Data Table](#).

There are two types of Data Details tables:

- [Properties Table](#)
- [Jobs Table](#)


### NA Values

As in the Data table, a value of **NA** (Not Available) displays in any field of the Properties table and Jobs table that has not been populated with event data. (See [NA Values](#) in [Section 4.7 Data Table](#).)

### 4.8.1 Properties Table

The Properties table identifies the parameters, and their values, of an item selected in the [Data Table](#) (see [Section 4.7.6 Displaying a Properties Table](#)).

In [Figure 4.35](#), below, the Properties table identifies parameters and values for Agent **qa-hp1123**.



Parameter	Value
Agent Name	qa-hp1123
Description	
Version	4.1.0 Level 0 Development Build 102
Host Name	qa-hp1123
IP Address	qa-hp1123
TCP Port	7887
Status	Available
Start Date/Time	NA
Component Total	1

Figure 4.35 I-Activity Monitor - Properties Table

**Note:** The Properties table lists all parameters / values for a selected filter, including any parameters / values that are not displayed in the Data table.

## 4.8.2 Jobs Table

The Jobs table displays information on jobs for an Agent selected in the [Data Table](#) (see [Section 4.7.7 Displaying a Jobs Table](#)).

You can select to display either:

- Indesca jobs
- Infitran jobs

Note: The Jobs table displays the same type of job information for a single Agent that displays in the Data table for all jobs.

In [Figure 4.36](#), below, the Jobs table displays Indesca jobs.

All Indesca jobs							Count: 264
	Mgr Work ID		Contains				
	Mgr Work ID	Mgr Agent Name	Srv Agent Name	Srv IP Address	Comment	Mgr Exit Code	
	U050105, JOB05224	qa-zos15-320	qa-mpras302	qa-mpras302		0	▲
	U050105, JOB05224	qa-zos15-320	qa-mpras302	qa-mpras302		2	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		2	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U050102, JOB05223	qa-zos15-320	qa-mpras302	qa-mpras302		2	
	PID65641	qa-zos15-320	qa-zos15-320	qa-zos15		0	
	QAMEMLST, STC05144	qa-zos15-320	NA	NA		0	
	QAMEMLST, STC05144	qa-zos15-320	qa-zos15-320	qa-zos15		1023	
	QAMEMLST, STC05144	qa-zos15-320	NA	NA		0	
	QAMEMLST, STC05144	qa-zos15-320	NA	NA		0	
	QAMEMLST, STC05144	qa-zos15-320	NA	NA		0	
	QAMEMLST, STC05144	qa-zos15-320	NA	NA		1	
	PID16842872	qa-zos15-320	qa-zos15-320	qa-zos15		255	
	PID65636	qa-zos15-320	qa-zos15-320	qa-zos15		8	
	U040101, JOB04938	qa-zos15-320	qa-zos15-320	qa-zos15		0	
	U010602, JOB04937	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U010602, JOB04937	qa-zos15-320	qa-mpras302	qa-mpras302		0	
	U010602, JOB04937	qa-zos15-320	qa-mpras302	qa-mpras302		0	▼

Figure 4.36 I-Activity Monitor - Jobs Table

## 4.9 User-Specific Tasks

The User menu on the I-Activity Monitor **Menu Bar** provides the following tasks that are specific to the logged in user.

- [Changing a Password](#)
- [Saving a Data Table Layout](#)
- [Resetting the Default Data Table Layout](#)
- [Setting a Filter Group as Default Display](#)
- [Logging Off I-Activity Monitor](#)
- [Viewing Information About I-Activity Monitor](#)

### 4.9.1 Changing a Password

To change the password that you use to log in to any of the UEC Client Applications, perform the following steps.

1. Select **Change Password** on the I-Activity Monitor **User** menu. The Change Password dialog displays.




Figure 4.37 I-Activity Monitor - Change Password dialog

2. Enter your **Current Password**.
3. Enter a **New Password**.
4. Reenter your new password in **Confirm Password**.
5. Click the **OK** button.

You must use this new password the next time that you log in to any of the UEC Client applications.

---

## 4.9.2 Saving a Data Table Layout

---

For information on setting the currently displayed Data table layout as the default Data table layout for the logged in user, see [Saving a Data Table Layout](#) in Section 4.7.4 [Customizing Layout of the Data Table](#).

---

## 4.9.3 Resetting the Default Data Table Layout

---

For information on resetting the currently displayed Data table layout to the default Data table layout for the logged in user, see [Resetting the Default Data Table Layout](#) in Section 4.7.4 [Customizing Layout of the Data Table](#).

---

## 4.9.4 Setting a Filter Group as Default Display

---

To set the currently selected filter group (Alerts, Jobs, Files, or Systems) as the initial filter group displayed when you log in to I-Activity Monitor, click **Set Initial Filter Group** on the I-Activity Monitor **User** menu.

When you next log in to I-Activity Monitor, the button for the currently displayed filter group will be pre-selected in the [Filter Group Panel](#) and the [Filter Group Panel](#) will be populated with the filters in that filter group.

## 4.9.5 Logging Off I-Activity Monitor

To log off I-Activity Monitor, perform the following steps.

1. Click **Logoff** on the **User** menu. The Connect to Universal Enterprise Controller dialog displays.




Figure 4.38 Connect To Universal Enterprise Controller dialog

2. Click the **x** icon in the top, right corner to disconnect from the Universal Enterprise Controller Server on which I-Activity Monitor resides. The Close Monitor dialog then displays.




Figure 4.39 I-Activity Monitor - Close Monitor dialog

3. Click the **Yes** button to log off I-Activity Monitor.



## I-Activity Monitor Screen Size

When you log off I-Activity Monitor, the currently displayed size of the I-Activity Monitor screen is saved in the `uec1o.txt` file. The next time that I-Activity Monitor is logged into on this UEC server, the I-Activity Monitor screen is displayed in this same size.

This file is located in the `%appdata%\Universal` directory.

### Windows 2000, Windows XP, Windows Server 2003

`%appdata%` resolves to `C:\Documents and Settings\userid\Application Data`.

### Windows Vista, Windows 7, Windows Server 2008 / 2008 R2

`%appdata%` resolves to `C:\Users\userid\AppData\Roaming`.

For all Windows systems, `userid` is the ID of the user currently logged into Windows.

## 4.9.6 Viewing Information About I-Activity Monitor

To view information about the version of I-Activity Monitor to which you have logged in, click **About** on the **Help** menu. The About I-Activity Monitor dialog then displays.




Figure 4.40 I-Activity Monitor - About I-Activity Monitor dialog

## 4.10 Stopping a Component

To stop an active or restarted component, perform the following steps:

1. In the Filter Group panel, click the **Jobs** button.
2. In the Jobs table, select the component to be stopped.
3. On the I-Activity Monitor tool bar, click the **Stop Component** icon.

If you have permission to stop components running under the selected Agent, UEC will attempt to stop the component using a remote user name in the following format:

**UEC\_USER:LOGGED\_IN\_USER**

- **UEC\_USER** is the user ID under which UEC itself is executing.
- **LOGGED\_IN\_USER** is the user ID of the I-Activity Monitor user.

Unless the user ID was changed at installation:

- UEC for z/OS will execute as user **STCUSER**.
- UEC for Windows will execute as **NT AUTHORITY\SYSTEM**.

If the Universal Access Control List (UACL) on the remote machine for Universal Control allows this remote user to stop components, the component should be stopped.

4. If the UACL does not allow components to be stopped with this remote user ID, I-Activity Monitor displays the Stop Component dialog (Figure 4.41, below).




Figure 4.41 I-Activity Monitor - Stop Component dialog

Enter the **User Name** and **Password** used to execute the job, and then click **OK**.

UEC then will re-attempt to stop the component with this information. If UEC cannot stop the component, you will be notified by UEC.

## Example

The following is an example entry in the UACL configuration of the remote agent for Universal Control **stop** access:

```
# User connecting to MVS UEC
uctl_access ALL,STCUSER:user1,*,allow,noauth
# User connecting to windows UEC
uctl_access "ALL,NT AUTHORITY\SYSTEM:user1,*,allow,noauth"
```

(For a complete description of UCTL\_ACCESS, see the chapter on Universal Control UACL Entries in the Stonebranch Solutions Utilities 4.2.0 Reference Guide.)

Note: You cannot stop a component in the pending state. Instead, the manager must be executed with either:

- RESTART option value of **auto** or **yes**, in order to pick up its output and exit status.
- FORCE\_COMPLETE option in order to clean up the spool.

Also, stopping a component that is running under the control of Universal Broker version 1.2 is not supported.

---

# I-Management Console

---

## 5.1 Overview

The I-Management Console application provides a graphical user interface for remotely configuring Agents.

### 5.1.1 I-Management Console Applications

---

I-Management Console is comprised of three applications:

- [Agent Update](#)  
The Agent Update application lets you:
  - View and modify the configurations of Agents being monitored by the Universal Enterprise Controller (UEC).
  - Save the configuration of an Agent as an Agent profile.
- [Mass Update](#)  
The Mass Update application lets you:
  - Modify the configurations of multiple agents simultaneously through the use of Agent profiles.
- [Commit Queue](#)  
The Commit Queue application lets you:
  - View the status of modified configurations committed to Agents.
  - Cancel a commit that is pending.

Note: To specify the Agents to be monitored by UEC, use the I-Administrator application (see Chapter [3 I-Administrator](#)).

## 5.2 Using I-Management Console

When you log in to I-Management Console, (see Chapter 2 [Accessing UEC Client Applications](#)), the I-Management Console screen displays (Figure 5.42, below).

Note: The screen for the Agent Update application is the initial display.




Figure 5.42 I-Management Console screen (Initial Display)

## 5.2.1 I-Management Console Screen Information

---

The I-Management Console screen ([Figure 5.42](#)) contains the following regions:

- **Menu Bar (1)**  
The menu bar lets you perform tasks common to all I-Management Console applications and tasks specific to individual applications (see [Section 5.3 Menu Bar](#)).
- **Tool Bar (2)**  
The tool bar lets you perform tasks common to all I-Management Console applications and tasks specific to individual applications (see [Section 5.4 Tool Bar](#)).
- **Filter Tree (3)**  
The Filter tree identifies the currently defined list of agents (see [Figure 5.46 I-Management Console - Agent Update screen](#)) or profiles (see [Figure 5.58 I-Management Console - Mass Update screen](#)).
- **Applications Panel (4)**  
The Applications panel contains buttons that provide access to each I-Management Console application:
  - [Agent Update](#)
  - [Mass Update](#)
  - [Commit Queue](#)
- **Data Panel (5)**  
The Data panel contains different information for each I-Management Console application. See:
  - [Figure 5.46 I-Management Console - Agent Update screen](#)
  - [Figure 5.58 I-Management Console - Mass Update screen](#)
  - [Figure 5.75 I-Management Console - Commit Queue screen](#)

## 5.3 Menu Bar

Most of the menu items on the I-Management Console menu bar (see [Figure 5.42](#)) are enabled only as appropriate for the task being performed. The tasks in this chapter identify when these items are enabled and available for selection.

[Table 5.8](#), below, identifies the items on each menu of the menu bar and provides a link to the task associated with each item.

Menu / Item	Description
File / New	Create a new Profile. (See <a href="#">Section 5.7.2 Creating a Profile.</a> )
File / Close	Close a displayed Profile. (See <a href="#">Section 5.7.12 Closing a Profile.</a> )
File / Save	Save modified Profile configurations. (See <a href="#">Section 5.7.7 Saving Profile Configurations.</a> )
File / Save As	Copy and save a modified Profile as another Profile. (See <a href="#">Section 5.7.8 Saving Profile Configurations As Another Profile.</a> )
File / Edit Configuration List	Add and/or remove configuration in a Profile. (See <a href="#">Section 5.7.3 Adding / Removing Configurations in a Profile.</a> )
File / Edit Agent List	Add and/or remove Agents in a Profile. (See <a href="#">Section 5.7.4 Adding / Removing Agents in a Profile.</a> )
File / Delete	Delete a Profile. (See <a href="#">Section 5.7.13 Deleting a Profile.</a> )
File / Log Off	Log off I-Management Console. (See <a href="#">Section 5.5.2 Logging Off I-Management Console.</a> )
Edit / Undo	Undo one or more entries in a table. (See <a href="#">Section 5.6.2 Modifying Agent Configurations</a> and <a href="#">Section 5.7.5 Modifying Profile Configurations.</a> )
Edit / Redo	Redo one or more entries in a table. (See <a href="#">Section 5.6.2 Modifying Agent Configurations</a> and <a href="#">Section 5.7.5 Modifying Profile Configurations.</a> )
Edit / Load Value	Load actual or default value into an Agent configuration option field. (See <a href="#">Section 5.6.2 Modifying Agent Configurations.</a> )
View / Agent Update	Display the Agent Update screen. (See <a href="#">Section 5.6 Agent Update.</a> )
View / Mass Update	Display the Mass Update screen. (See <a href="#">Section 5.7 Mass Update.</a> )
View / Commit Queue	Display the Commit Queue screen. (See <a href="#">Section 5.8 Commit Queue.</a> )
UACL / Add	Add rules for a new UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table.</a>
UACL / Edit	Edit rules of a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table.</a>













Menu / Item	Description
UACL / Delete	Delete a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
UACL / Move Up	Move up a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
UACL / Move Down	Move down a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
Actions / Commit	Commit a modified configuration. (See Sections <a href="#">5.6.4 Committing Agent Configurations</a> and <a href="#">5.7.10 Committing Profile Configurations</a> .)
Actions / Validate	Validate a modified configuration. (See Sections <a href="#">5.6.5 Validating Agent Configurations (Without Committing)</a> and <a href="#">5.7.9 Validating Profile Configurations (Without Saving)</a> .)
Actions / Cancel Commit	Cancel a committed (by not yet competed) configuration. (See Section <a href="#">5.8.4 Canceling a Commit</a> .)
Help / About	Display information about the logged in version of I-Management Console. (See Section <a href="#">5.5.3 Displaying Information about I-Management Console</a> .)

Table 5.8 I-Management Console screen - Menu Selections

## 5.4 Tool Bar

The I-Management Console tool bar provides icons that let you select functions for the three I-Management Console applications. As [Table 5.9](#), below, illustrates, some icons are shared by applications and some are unique to a specific application.

Most of the icons are enabled only as appropriate for the region being accessed in a specific I-Management Console application.

Icon	Description
<b>Agent Update and Mass Update</b>	
	<b>Add a Row</b> Add rules for a new UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
	<b>Edit a Row</b> Edit rules of a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
	<b>Delete a Row</b> Delete a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
	<b>Move Up a Row</b> Move up a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
	<b>Move Down a Row</b> Move down a UACL entry in a <a href="#">Configuration Options Table</a> or <a href="#">Profile Configurations Options Table</a> .
	<b>Commit Configuration</b> Commit agent or profile configurations (see <a href="#">Section 5.6.4 Committing Agent Configurations</a> and <a href="#">5.7.10 Committing Profile Configurations</a> )
<b>Agent Update</b>	
	<b>Save Actual Values to Profile</b> Save the configurations of an agent as a profile (see <a href="#">Section 5.6.7 Saving Agent Configurations as a Profile</a> ).
<b>Mass Update</b>	
	<b>New Profile</b> Create a new profile of configurations (see <a href="#">Section 5.7.2 Creating a Profile</a> ).
	<b>Save Profile</b> Save a profile of configurations (see <a href="#">Section 5.7.7 Saving Profile Configurations</a> ).
	<b>Save Profile As</b> Save a profile of configurations as another profile (see <a href="#">Section 5.7.8 Saving Profile Configurations As Another Profile</a> ).





Icon	Description
	<b>Close Profile</b> Close a Profile (without saving changes to its configurations (see Section <a href="#">5.7.12 Closing a Profile</a> )).
	<b>Edit Configuration List</b> Add and/or remove configurations in a profile (see Section <a href="#">5.7.3 Adding / Removing Configurations in a Profile</a> ).
	<b>Edit Agent List</b> Add and/or remove agents in a profile (see Section <a href="#">5.7.4 Adding / Removing Agents in a Profile</a> ).
<b>Commit Queue</b>	
	<b>Cancel Commit</b> Cancel a commit that has not yet completed (see Section <a href="#">5.8.4 Canceling a Commit</a> ).

Table 5.9 I-Management Console - Tool Bar Icons

## 5.5 User Tasks

The user tasks are common for all I-Management Console applications.

### 5.5.1 Accessing I-Management Console Applications

In addition to accessing a I-Management Console application by clicking the appropriate panel in the I-Management Console screen Applications Panel, you also can access them via the **View** menu on the I-Management Console menu bar (see [Figure 5.42](#)). There is a separate menu item for each application.

### 5.5.2 Logging Off I-Management Console

To log off I-Management Console, perform the following steps.

1. Click **Log Off** on the **File** menu. The Connect to Universal Enterprise Controller dialog displays.




Figure 5.43 Connect To Universal Enterprise Controller dialog

2. Click the **x** icon in the top, right corner to disconnect from the Universal Enterprise Controller Server on which I-Management Console resides. The Close Remote Configuration dialog then displays.




Figure 5.44 I-Management Console - Close Remote Configuration dialog

3. Click the **Yes** button to log off I-Management Console.

### 5.5.3 Displaying Information about I-Management Console

---

To view information about the version of I-Management Console to which you have logged in, click **About** on the **He1p** menu.

The About I-Management Console dialog then displays.




Figure 5.45 I-Management Console - About I-Management Console dialog

## 5.6 Agent Update

The Agent Update application lets you perform the following tasks:

1. View installed configurations, and their options, for all Agents.
2. Modify configuration option values and commit them to an Agent.
3. Save an Agent's configurations and option values to a profile.

### 5.6.1 Accessing Agent Update

To access the Agent Update application, click the **Agent Update** button in the I-Management Console screen Applications panel. The Agent Update screen (Figure 5.46) then displays.

Note: When you log in to I-Management Console, this is the default display.




Figure 5.46 I-Management Console - Agent Update screen

In addition to the **Menu Bar** and **Tool Bar**, the Agent Update screen is comprised of three regions:

- **Agent Tree (1)**
- **Configuration Tree (2)**
- **Configuration Options Table (3)**

## Agent Tree

The Agent tree section of the Agent Update screen ([Figure 5.47](#), below) identifies all of the agents and groups assigned to the current user.






Figure 5.47 I-Management Console - Agent Update screen / Agent Tree

Each agent in the Agent tree is identified by one of the following icons:

-  Agent has been polled by UEC. This icon displays even if the Agent currently, for whatever reason, cannot be polled by UEC.
-  Agent has not been polled by UEC: UEC may be unable to poll the Agent, or the Agent was defined to the Broker being polled prior to version 4.1.0.

When you click on an agent in the Agent tree, the [Configuration Tree](#) is populated with all configurations installed on that agent.

Note: Groups and agents, and the users to which they are assigned, are created in the I-Administrator utility (see [Chapter 3 I-Administrator](#)).

## Configuration Tree

The Configuration tree section of the Agent Update screen ([Figure 5.48](#), below) identifies all of the Indesca or Infitran components installed on the Agent currently selected in the [Agent Tree](#).




Figure 5.48 I-Management Console - Agent Update screen / Configuration Tree

The following configuration groups can appear in the Configuration tree:

- Universal Command
- Universal Data Mover
- Universal Event Monitor
- Universal Infrastructure
- Universal Utilities

When you click on a configuration in the Configuration tree, the [Configuration Options Table](#) is populated with all of the options, and their values, included in that configuration.



## Configuration Options Table

The Configuration Options table of the Agent Update screen (Figure 5.49, below) identifies all of the options included in the configuration currently selected in the Configuration Tree.

(The top, left corner of the table identifies the selected configuration.)

Manager			
1	Option 2	Value 3	Actual 4
<input type="checkbox"/>	Message Level		Warn
<input checked="" type="checkbox"/>	Display Time		NO
<input type="checkbox"/>	Message Language		ENGLISH
<input type="checkbox"/>	Trace File Lines		100000
<input type="checkbox"/>	Trace Table Size		0
<input checked="" type="checkbox"/>	Trace Table Unit		Bytes
<input checked="" type="checkbox"/>	Trace Print Condition		Never
<input type="checkbox"/>	Connect Timeout		0
<input type="checkbox"/>	Data Authentication		NO
<input type="checkbox"/>	Data Compression		NO
<input checked="" type="checkbox"/>	Data Compression Method		ZLIB
<input type="checkbox"/>	Data Encryption		NO
<input type="checkbox"/>	DNS Expand		NO
<input type="checkbox"/>	Host Selection Method		SEQUENTIAL
<input type="checkbox"/>	Hostname Retry Count		1
<input type="checkbox"/>	Job Retention		

Figure 5.49 I-Management Console - Agent Update screen / Configuration Options table

The Configuration Options table consists of four columns:

- **(1)** Check box that lets you select an option to modify.
- **(2) Option** Name of each option whose value can be changed.
- **(3) Value** Field that lets you create or modify an option value.  
Depending on the option, **Value** has the following form:
  - Text field
  - Drop-down list
  - Custom field (for example, the SSL Cipher List fields)
- **(4) Actual** Current value of each option.

### *Navigating in the Configuration Options Table*

After selecting a option in the Configuration Options table, you can navigate in the table and modify values solely from the keyboard by using the following keys:

- Space Bar           Toggles the Commit check box (inserts / removes check mark).
- Down Arrow        Moves to the next option.
- Up Arrow            Moves to the previous option.
- Esc                 Exits the edit mode.
- Enter                Enters the edit mode.

### *Rules for Creating and Modifying Configuration Values*

The following rules apply for creating and modifying configuration values in the Configuration Options table:

- Configuration values can contain spaces and/or tabs, but if they do, they must be enclosed in single ( ' ) or double ( " ) quotation marks. Repeat the enclosing characters to include them as part of the value.
- Configuration values that are not pre-defined, such as directory names and file names, are case sensitive.

## 5.6.2 Modifying Agent Configurations

To modify agent configurations — that is, to modify the configuration option values of an agent — perform the following steps:

1. Select an agent from the Agent tree. The Configuration tree then lists all configurations of that Agent.
2. Select a configuration from the Configuration tree. The Configuration Options table then lists all options, and their current values, for that configuration.
3. In the Configuration Options table, click the Commit check box of an option whose value you want to modify (see [Figure 5.50](#), below).

**Note:** An option with a gray Commit check box (such as **Display Time** in [Figure 5.50](#)) is a dependent option. It can be selected for modification only if the independent option (with a white Commit check box) immediately preceding it has been selected.

Consecutively listed dependent options all are dependent on the independent option immediately preceding them.




Figure 5.50 I-Management Console - Agent Update / Configuration Option Selected

This causes the following to occur:

- (a) Check mark is inserted in the Commit check box for that option.
- (b) Row for that option is highlighted.
- (c) Value field for that option is enabled.
- (d) Configuration tree displays a green check mark (✓) for the group and configuration in which the option resides. This allows you to keep track of all your selections.

4. In the **Value** field, enter a modified value for the option (that is, a different value than **Actual** value) either by:
  - Typing a value (in a text field).
  - Selecting a value (from a drop-down list).
  - Loading a value by selecting either of the following from the **Edit** menu.
    - Select **Load Value / Actual** to enter the **Actual** value in the **Value** field.
    - Select **Load Value / Default** to enter the default value in the **Value** field.
5. Press the **Enter** key, or click the mouse anywhere outside that **Value** field, to validate the modified value.

If the modified value is valid, it is accepted and displayed in the **Value** field.
6. If the modified value is invalid, a warning message displays.

Exit the warning message and either:

  - Enter another value in that **Value** field and press the **Enter** key (or click the mouse anywhere outside that **Value** field).
  - Cancel the modification either by:
    - Clicking on the Commit check box
    - Pressing the **Esc** key.

This removes the check mark from the Commit check box.
7. Select and modify other values, as desired.

## Undoing / Redoing Table Actions

You can undo multiple actions, and redo multiple undone actions, performed in the Configuration Options table.

- To undo an action, either select **Undo** from the I-Management Console **Edit** menu or press **Ctrl+Z**.
- To redo an undone action, either select **Undo** from the I-Management Console **Edit** menu or press **Ctrl+Y**.

## 5.6.3 Modifying Universal Access Control Lists

Universal Access Control List (UACL) configurations (as shown in [Figure 5.51](#), below) are used to define Access Control Lists (ACLs) and certificates.




Figure 5.51 I-Management Console - Agent Update / Universal Access Control List Options

Each Universal Access Control configuration in the Configuration tree (1) represents a type of UACL entry for a specific component.

A UACL entry type selected in the Configuration tree is identified at the top of the Configuration Options table (2). The column headers identify the fields that comprise the rule for that entry type. Each row in the table represents the rule for a single entry.

There is no limit to the number of UACL entries that can exist for an entry type.

[Figure 5.51](#), for example, illustrates a single entry of Broker Access Rules for the Universal Broker. The rule is comprised of two fields: Host (value=abc) and Access (value=Allow).

### UACL Configuration Actions


You can perform the following actions for a UACL configuration:

- [Adding a UACL Entry](#)
- [Editing a UACL Entry](#)
- [Deleting a UACL Entry](#)
- [Moving Up a UACL Entry](#)
- [Moving Down a UACL Entry](#)

## Adding a UACL Entry

To add a UACL entry for a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Configuration tree. The Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click **Add Row** from either the UACL menu or the I-Management Console tool bar. The Add Row dialog (Figure 5.52, below) displays.



Column	Value
Host	
Access	

Figure 5.52 I-Management Console - Agent Update / Universal Access Control List Option - Add Row

3. For each field, click the **Value** column and enter/ select a value.
4. Click the **Save** button to add that new UACL entry, which then displays in the Configuration Options table below any already defined entries.

## Editing a UACL Entry

To edit a UACL entry of a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Configuration tree. The Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Display the Edit Row dialog (Figure 5.53, below) for a row either by:
  - Clicking on that row and selecting **Edit Row** from the UACL menu or I-Management Console tool bar.
  - Double-clicking that row.





Figure 5.53 I-Management Console - Agent Update / Universal Access Control List Option - Edit Row

3. For each field that you want to edit, click the **Value** column and enter/select a value.
4. Click the **Save** button. The Configuration Options table displays the edited values for that entry.

## Deleting a UACL Entry

To delete a UACL entry of a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Configuration tree. The Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click on a row and select either **Delete Row** from either the UACL menu or the I-Management Console tool bar. The Delete Row dialog displays.



3. Click the **Yes** button to delete UACL entry; the row is removed from the Configuration Options table.

## Moving Up a UACL Entry

To move up an entry in a UACL, perform the following steps.

1. Click on a UACL entry type of a specific component in the Configuration tree. The Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
1. Click on a row.
2. Click **Move Up** from the UACL menu or tool bar.  
Each time that you click **Move Up**, the row moves up one position.

## Moving Down a UACL Entry

To move down an entry in a UACL, perform the following steps.

1. Click on a UACL entry type of a specific component in the Configuration tree. The Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click on a row.
3. Click **Move Down** from the UACL menu or tool bar.  
Each time that you click **Move Down**, the row moves down one position.



## 5.6.4 Committing Agent Configurations

You must commit any modified option values of an Agent configuration in order for UEC to send those values to the Agent. When you commit a configuration, a validation automatically is performed on all of its modified option values.

Committed configurations are placed in a Commit queue. Whenever UEC polls an Agent, the Commit queue is scanned for any pending commits (committed configurations) to that agent. If a pending commit is found, it is sent to the Agent, where the Universal Broker automatically is refreshed.

Only one pending commit is sent to an Agent per poll. For example, if a user commits five times to an agent, five Agent polls are required to process the pending commits.

Note: The frequency with which UEC polls an Agent is defined in the UEC [POLLING\\_INTERVAL](#) configuration option. This polling interval also can be defined for individual agents through the I-Administrator client application (see [Chapter 3 I-Administrator](#)).

To track the status of commits, access the Commit Queue application (see [Section 5.8 Commit Queue](#)).

To commit a configuration, perform the following steps.

1. In the Configuration tree, click the configuration to be committed.
2. Commit the selected configuration either by:
  - Clicking **Commit** in the Actions menu on the I-Management Console menu bar.
  - Clicking the **Commit Configuration** icon on the I-Management Console tool bar.

Note: Only values for options with the Commit check box checked in the Configuration Options table can be committed. (If you modify an option value, but remove the check mark before submitting that value for validation, the modification is removed from the value field and will not be made.)

3. If validation is successful – that is, all option values are successfully validated – the Commit dialog displays.




Figure 5.54 I-Management Console - Agent Update / Commit dialog

Enter a description for the commit.

(The following default description is provided: **Commit to agent: <agent name>**.)

4. Click the **Commit** button to commit the changes to the agent.
5. The commit is placed on the I-Management Console Commit queue and the following dialog displays.




Figure 5.55 I-Management Console - Agent Update / Commit Status dialog


Click **OK**.

## 5.6.5 Validating Agent Configurations (Without Committing)

When you commit a configuration, a validation automatically is performed on all of its modified option values (see Section [5.6.4 Committing Agent Configurations](#)).

However, If you want to validate the modified values without committing the configuration, perform the following steps.


1. Click **Validate** in the I-Management Console Actions menu.  
If the validation is successful, the following dialog displays.



2. Click **OK**.

## 5.6.6 Correcting Invalid Agent Configuration Values

If validation is unsuccessful when you attempt to commit a configuration – that is, the configuration contains one or more invalid option values – the following dialog displays.



Click **OK**. The Validate dialog (Figure 5.56, below) displays. (The Validate dialog displays immediately if you attempt to validate, without committing, an agent configuration.)




Figure 5.56 I-Management Console - Agent Update / Validate dialog

For each invalid option value, the Validate dialog provides the following information:

- **Application** of the option containing the invalid value.
- **Option** for which there is an invalid value.
- **Value** that is invalid.
- **Warning Message** indicating why the value is invalid.

To modify a value, perform the following steps:

1. Click on the row of the invalid value.
2. Click the **Goto** button. The Validate dialog closes and the corresponding Configuration tree and Configuration Options table display for that option.
3. Modify the value and re-validate or re-commit the option values.

## 5.6.7 Saving Agent Configurations as a Profile

To save agent configurations as a profile, perform the following steps:

1. Click an agent in the Agent tree.
2. Click either:
  - **Save As** from the I-Management Console File menu.
  - **Save Actual Values to Profile** icon on the I-Management Console tool bar.The Profile Save As... dialog then displays.




Figure 5.57 Profile Save As... dialog

3. Enter a name for the profile. (A default name that includes the name of the agent is provided.)
4. Click the **Save** button to save the profile; it displays in the Profile tree of the Mass Update application. You assign one or more agents to this profile.  
The agent from which the profile was created automatically is assigned to the profile and displays in the Profile Agent tree of Mass Update.

## 5.7 Mass Update

The Mass Update application lets you modify configurations for multiple agents simultaneously through the use of agent profiles.

Each profile is a set of one, more than one, or all configurations. A profile is available to a user only if the user has been given access, via I-Administrator, to all configurations included in that profile.

Mass Update lets you perform the following tasks:

1. Create profiles.
2. Select profile configurations for the created profiles.
3. Assign agents to profiles.
4. Define configuration option values for the profile configurations.
5. Commit the profiles to Universal Enterprise Controller (UEC).

The following sections of this document tells you how to perform these tasks.

## 5.7.1 Accessing Mass Update

To access the Mass Update application, click the **Mass Update** panel on the bottom left corner of the I-Management Console screen. The Mass Update screen (Figure 5.58, below) then displays.




Figure 5.58 I-Management Console - Mass Update screen

In addition to the **Menu Bar** and **Tool Bar**, the Mass Update screen (Figure 5.58) is comprised of four regions:

- **Profile Tree (1)**
- **Profile Configurations Tree (2)**
- **Profile Agents Tree (3)**
- **Profile Configurations Options Table (4)**

## Profile Tree

The Profile tree section of the Mass Update screen ([Figure 5.59](#), below) identifies all of the profiles for which the current user (resident on UEC) has configuration access.




Figure 5.59 I-Management Console - Mass Update screen / Profile Tree

When you click on a profile in the Profile tree, the [Profile Configurations Tree](#) is populated with all configurations defined for that profile.

**Note:** When you select Mass Update for the first time, the Profile tree may be empty.



## Profile Configurations Tree

The Profile Configurations tree section of the Mass Update screen (Figure 5.60, below) identifies all of the configurations included in the profile selected in the [Profile Tree](#).




Figure 5.60 I-Management Console - Mass Update screen / Profile Configurations tree

The Profile Configuration tree organizes the configurations under groups that provide a logical hierarchy.

The following configuration groups can appear in the Profile Configuration tree:

- Universal Command
- Universal Data Mover
- Universal Event Monitor
- Universal Infrastructure
- Universal Utilities

The [Edit Configuration List](#) link at the bottom of the tree lets you add or remove configurations for this profile (see Section [5.7.3 Adding / Removing Configurations in a Profile](#)).

## Profile Agents Tree

The Profile Agents tree section of the Mass Update screen (Figure 5.61, below) identifies all of the agents that have been assigned to the profile selected in the Profile Tree.




Figure 5.61 I-Management Console - Mass Update screen / Profile Agents tree

The [Edit Agent List](#) link at the bottom of the tree lets you add or remove agents assigned to this profile (see Section 5.7.4 Adding / Removing Agents in a Profile).

## Profile Configurations Options Table

The Profile Configurations Options table section of the Mass Update screen (Figure 5.62, below) identifies all of the options for a profile configuration selected in the [Profile Configurations Tree](#).

(The top, left corner of the table identifies the selected profile configuration.)

Manager		
1	Option 2	Value 3
<input checked="" type="checkbox"/>	Message Level	Warn
<input type="checkbox"/>	Display Time	NO
<input checked="" type="checkbox"/>	Message Language	ENGLISH
<input checked="" type="checkbox"/>	Trace File Lines	100000
<input checked="" type="checkbox"/>	Trace Table Size	0
<input type="checkbox"/>	Trace Table Unit	Bytes
<input type="checkbox"/>	Trace Print Condition	Never
<input checked="" type="checkbox"/>	Connect Timeout	0
<input checked="" type="checkbox"/>	Data Authentication	NO
<input checked="" type="checkbox"/>	Data Compression	NO
<input type="checkbox"/>	Data Compression Method	ZLIB
<input checked="" type="checkbox"/>	Data Encryption	NO
<input checked="" type="checkbox"/>	DNS Expand	NO
<input checked="" type="checkbox"/>	Host Selection Method	SEQUENTIAL
<input checked="" type="checkbox"/>	Hostname Retry Count	1
<input checked="" type="checkbox"/>	Job Retention	
<input checked="" type="checkbox"/>	Local Code Page	iso8859-1

Figure 5.62 I-Management Console - Mass Update screen / Profile Configurations Options table

The Profile Configurations Options table consists of three columns:

- **(1)** Check box that lets you select an option to modify.
- **(2) Option** Options in the selected configuration whose value can be defined.
- **(3) Value** Fields that lets you create or modify option values.  
Depending on the option, **Value** has the following form:
  - Text field
  - Drop-down list
  - Custom field (for example, the SSL Cipher List fields)

### Navigating in the Profile Configurations Options Table

After selecting an option in the Profile Configurations Options table, you can navigate in the table and modify values solely from the keyboard by using the following keys:

- Space Bar           Toggles the Commit check box (inserts / removes check mark).
- Down Arrow        Moves to the next option.
- Up Arrow            Moves to the previous option.
- Esc                 Exits the edit mode.
- Enter                Enters the edit mode.

### Rules for Creating and Modifying Configuration Values

The following rules apply for creating and modifying configuration values in the Profile Configurations Options table:

- Configuration values can contain spaces and/or tabs, but if they do, they must be enclosed in single ( ' ) or double ( " ) quotation marks. Repeat the enclosing characters to include them as part of the value.
- Configuration values that are not pre-defined, such as directory names and file names, are case sensitive.

## 5.7.2 Creating a Profile

To create a new profile, perform the following steps:

1. Display the New Profile dialog either by:
  - a. Clicking **New . . .** on the I-Management Console File menu.
  - b. Click the **New Profile** icon on the Mass Update toolbar.




Figure 5.63 I-Management Console - Mass Update / New Profile dialog

2. Enter a **Profile Name**.
3. Click the **Create** button.

The Profile tree then displays this profile.

You now can:

- Add configurations to a profile (see Section [5.7.3 Adding / Removing Configurations in a Profile](#)).
- Assign agents to this profile (see Section [5.7.4 Adding / Removing Agents in a Profile](#)).

## 5.7.3 Adding / Removing Configurations in a Profile

To add and/or remove configurations in a Profile, perform the following steps.

1. Select a profile in the Profile tree.
2. Display the Edit Configurations dialog (Figure 5.64, below) either by:
  - Clicking the [Edit Configuration List](#) link at the bottom of the Profile Configurations tree.
  - Clicking **Edit Configuration List** on the I-Management Console File menu.




Figure 5.64 I-Management Console - Mass Update / Edit Configuration List dialog

The **Available Configurations** window lists all configurations that are assigned to the current user. To display the list of available configurations, click **+** next to **Configurations** and each configuration group.

The **Include in Profile** window lists all of the configurations that currently are included in this profile. To display the list of all configurations currently in the profile, click **+** next to **Configurations** and each configuration group.

3. To add a configuration to the profile:
    - a. Click on that configuration in the **Available Configurations** window.
    - b. Click the **Assign->** button.The configuration then is listed in the **Include in Profile** window.
  4. To add all configurations to the profile, click the **Assign All->** button.  
All of the configurations are listed in the **Include in Profile** window.
  5. To remove a configuration from the profile:
    - a. Click on that configuration in the **Include in Profile** window.
    - b. Click the **<-Remove** button.The configuration is removed from the **Include in Profile** window.
  6. To remove all configurations from the profile, click the **<-Remove All** button.  
All of the configurations are removed from the **Include in Profile** window.
  7. Click the **Save** button at the bottom of the Edit Configurations dialog to save your edits.
- Note: Adding configurations to the **Include in Profile** window does not remove them from the **Available Configurations** window.

## 5.7.4 Adding / Removing Agents in a Profile

To add and/or remove agents in a Profile, perform the following steps:

1. Select a profile in the Profile tree.
2. Display the Edit Agent List dialog (Figure 5.65, below), either by:
  - Clicking the [Edit Agent List](#) link at the bottom of the Profile Agents tree.
  - Clicking **Edit Agent List** on the I-Management Console File menu.




Figure 5.65 I-Management Console - Mass Update / Edit Agent List dialog

The **Available Agents** window lists all agents that are assigned to the current user. To display the list of available agents, click **+** next to **All Agents**.

The **Include in Profile** window lists all of the agents that currently are included in this profile. To see the list of all agents currently in the profile, click **+** next to **Agents**.

3. To add an agent to the profile:
  - a. Click on that agent in the **Available Agents** window.
  - b. Click the **Assign->** button.  
The agent is listed in the Include in Profile window.
4. To add all agents to the profile, click the **Assign All->** button.  
All of the agents are listed in the Include in Profile window.



5. To remove an agent from the profile:
  - a. Click on that agent.
  - b. Click the **<-Remove** button.  
The agent is removed from the Include in Profile window.
6. To remove all agents from the profile, click the **<-Remove All** button.  
All of the agents are removed from the Include in Profile window.
7. Click the **Save** button at the bottom of the Edit Agent List dialog to save your edits.

## 5.7.5 Modifying Profile Configurations

To modify profile configurations — that is, to modify the configuration option values of a profile — perform the following steps.

1. Select a profile from the Profile tree. This causes the following to occur:
  - Profile Configurations tree lists all configurations of that profile.
  - Profile Agents tree lists all of the agents assigned to that profile.
2. Select a configuration from the Profile Configurations tree. The Profile Configurations Options table then lists all options, and their current values, for that configuration.
3. In the Profile Configurations Options table, click the Commit check box of an option whose value you want to modify (see [Figure 5.66](#), below).

Note: An option with a gray Commit check box (such as **Display Time** in [Figure 5.66](#)) is a dependent option. It can be selected for modification only if the independent option (with a white Commit check box) immediately preceding it has been selected.

Consecutively listed dependent options all are dependent on the independent option immediately preceding them.




Figure 5.66 I-Management Console - Mass Update / Option Selected

This causes the following to occur:

- (a) Check mark is inserted in the Commit check box for that option.
  - (b) Row for that option is highlighted.
  - (c) **Va1ue** field for that option is enabled.
  - (d) Profile Configurations tree displays a green check mark (✓) for the group and configuration in which the option resides. This allows you to keep track of all your selections.
4. In the **Va1ue** field, enter a modified value for the option (that is, a different value than **Actua1** value).  
Depending on the option, the **Va1ue** field has the following form:
- Text field
  - Drop-down list
  - Custom field (for example, SSL Cipher List)
5. Press the **Enter** key, or click the mouse anywhere outside that **Va1ue** field, to validate the modified value.  
If the modified value is valid, it is accepted and displayed in the **Va1ue** field.
6. If the modified value is invalid, a warning message displays.  
Exit the warning message and either:
- Enter another value in that **Va1ue** field and press the **Enter** key (or click the mouse anywhere outside that **Va1ue** field).
  - Cancel the modification either by:
    - Clicking on the Commit check box
    - Pressing the **Esc** key.
- This removes the check mark from the Commit check box.
7. Select and modify other values, as desired.
8. You now can either:
- a. Save (and validate) the profile (see Section [5.7.7 Saving Profile Configurations](#)).
  - b. Save (and validate) the profile as another profile (see Section [5.7.8 Saving Profile Configurations As Another Profile](#)).
  - c. Validate (without saving) the profile (see Section [5.7.9 Validating Profile Configurations \(Without Saving\)](#)).

**Note:** You must save a profile before you can commit it. Saving a profile validates the profile, but validating a profile does not save it.

## Undoing / Redoing Table Actions

You can undo multiple actions, and redo multiple undone actions, performed in the Profile Configurations Options table.

- To undo an action, either select **Undo** from the I-Management Console **Edi t** menu or press **Ctrl+Z**.
- To redo an undone action, either select **Undo** from the I-Management Console **Edi t** menu or press **Ctrl+Y**.

## 5.7.6 Modifying Universal Access Control Lists

Universal Access Control List (UACL) configurations (as shown in [Figure 5.67](#), below) are used to define Access Control Lists (ACLs) and certificates.




Figure 5.67 I-Management Console - Mass Update / Universal Access Control List Options

Each Universal Access Control configuration in the Profile Configurations tree (1) represents a type of UACL entry for a specific component.

A UACL entry type selected in the Profile Configurations tree is identified at the top of the Profile Configurations Options table (2). The column headers identify the fields that comprise the rule for that entry type. Each row in the table represents the rule for a single entry.

There is no limit to the number of UACL entries that can exist for an entry type.

[Figure 5.67](#), for example, illustrates a single entry of Broker Access Rules for the Universal Broker. The rule is comprised of two fields: Host (value=`abc`) and Access (value=`Allow`).

### Modifying a UACL Configuration

You can perform the following actions on a UACL configuration:

- [Adding a UACL Entry](#)
- [Editing a UACL Entry](#)
- [Deleting a UACL Entry](#)
- [Moving Up a UACL Entry](#)
- [Moving Down a UACL Entry](#)

## Adding a UACL Entry

To add a UACL entry for a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Profile Configurations tree. The Profile Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click **Add Row** from either the UACL menu or the I-Management Console tool bar. The Add Row dialog (Figure 5.68, below) displays.

Column	Value
Host	
Access	


Figure 5.68 I-Management Console - Mass Update / Universal Access Control List Option - Add Row

3. For each field, click the **Value** column and enter/ select a value.
4. Click the **Save** button to add that new UACL entry, which then displays in the Profile Configuration Options table below any already defined entries.

## Editing a UACL Entry

To edit a UACL entry of a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Profile Configuration tree. The Profile Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Display the Edit Row dialog (Figure 5.69, below) for a row either by:
  - Clicking on that row and selecting **Edit Row** from the UACL menu or I-Management Console tool bar.
  - Double-clicking that row.



Column	Value
Host	abc
Access	Allow


Figure 5.69 I-Management Console - Mass Update / Universal Access Control List Option - Edit Row

3. Click in the **Value** field for each **Column** to enable that field.
4. Modify the data in that **Value** field.
5. Click the **Save** button. The Profile Configuration Options table displays the changed values.

## Deleting a UACL Entry

To delete a UACL entry of a component, perform the following steps.

1. Click on a UACL entry type of a specific component in the Profile Configurations tree. The Profile Configuration Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click on a row and select either **Delete Row** from either the UACL menu or the I-Management Console tool bar. The Delete Row dialog displays.



3. Click the **Yes** button to delete UACL entry; the row is removed from the Configuration Options table.

## Moving Up a UACL Entry

To move up an entry in a UACL, perform the following steps.

1. Click on a UACL entry type of a specific component in the Profile Configurations tree. The Profile Configurations Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click on a row.
3. Click **Move Up** from the UACL menu or tool bar.  
Each time that you click **Move Up**, the row moves up one position.

## Moving Down a UACL Entry

To move down an entry in a UACL, perform the following steps.

1. Click on a UACL entry type of a specific component in the Profile Configurations tree. The Profile Configurations Options table then displays a row for each UACL entry of that type currently defined for that component.
2. Click on a row.
3. Click **Move Down** from the UACL menu or tool bar.  
Each time that you click **Move Down**, the row moves down one position.

---

## 5.7.7 Saving Profile Configurations

---

You must save modified configurations of a profile before you can commit the profile.

**Note:** When you save a profile, a validation automatically is performed on all of its modified configuration option values. However, you can validate a profile without saving it (see Section [5.7.9 Validating Profile Configurations \(Without Saving\)](#)).

To save profile configurations, perform the following steps:

1. Select the profile on the Profile tree.
2. Save the profile either by:
  - Clicking **Save** on the I-Management Console File menu.
  - Clicking **Save Profile** on the Mass Update tool bar.



## 5.7.8 Saving Profile Configurations As Another Profile

To copy profile configurations and save it as another profile (that is, under a different name), perform the following steps.

1. Select a profile on the Profile tree.
2. Display the **Save As . . .** dialog either by:
  - Clicking **Save As . . .** on the I-Management Console **File** menu.
  - Click the **Save As** icon on the Mass Update toolbar.




Figure 5.70 I-Management Console - Mass Update / Save As... dialog


3. Enter a **Profile Name** for the profile.
4. Click **Save**. I-Management Console saves (and validates) the profile. When the save is complete, the profile resides in the UEC database and it displays in the Profile tree.

## 5.7.9 Validating Profile Configurations (Without Saving)

When you save a profile, a validation automatically is performed on all of its modified configuration option values (see Section [5.7.7 Saving Profile Configurations](#)). Only after a profile is saved, and its values successfully validated, can you commit the profile to be sent by UEC to all agents with that profile.

However, if you want to validate the configuration option values of a profile without saving the profile, perform the following steps.

1. Click **Validate** in the I-Management Console Actions menu.  
If the validation is successful, the following dialog displays.



2. Click **OK**.

**Note:** Validating a profile does not save it. You still must save the profile before committing it.

## 5.7.10 Committing Profile Configurations

You must commit a profile in order to have UEC send its modified configuration option values to all Agents with that profile. However, before you can commit a profile, you must save – and automatically validate – the profile (see Section [5.7.7 Saving Profile Configurations](#)).

Committed profiles are placed in a Commit queue. Whenever UEC polls an Agent, the Commit queue is scanned for a pending commit to Agents with that profile. If a pending commit is found, it is sent to the Agent, where the Universal Broker automatically is refreshed.

The frequency with which UEC polls an Agent is defined in the `POLLING_INTERVAL` configuration option of UEC. This polling interval also can be defined for individual Agents through the I-Administrator client application (see Chapter [3 I-Administrator](#)).

Only one pending commit is sent to an Agent per poll. For example, if a user commits five times to an Agent, five Agent polls are required to process the pending commits.

To track the status of commits, access the Commit Queue application (see Section [5.8 Commit Queue](#)).

To commit a profile, perform the following steps.

1. In the Profile tree, click the configuration to be committed.
2. Commit the selected profile either by:
  - Clicking **Commit** in the **Actions** menu on the I-Management Console menu bar.
  - Clicking the **Commit Configuration** icon on the I-Management Console tool bar.

**Note:** Only values for options with the Commit check box checked in the Profile Configurations Options table can be committed. (If you modify an option value, but remove the check mark before submitting that value for validation, the modification is removed from the value field and will not be made.)

3. The Commit dialog displays.




Figure 5.71 I-Management Console - Mass Update / Commit dialog

Enter a description for the commit.

(The following default description is provided: **Commit profile: <profiles name>**.)

- Click the **Commit** button to commit the changes to the agent.  
The commit is placed on the I-Management Console Commit queue and the following dialog displays.





Figure 5.72 I-Management Console - Mass Update / Commit Status dialog

- Click **OK**.

## Profile not Saved


If you try to commit a profile before it has been saved, the following dialog displays:



Click **OK**, and then save the profile (see [Section 5.7.7 Saving Profile Configurations](#)).

## 5.7.1.1 Correcting Invalid Profile Configuration Values

If you try to validate or save a Profile configuration that contains one or more invalid option values, the following dialog displays.



Click **OK**. The Validate dialog (Figure 5.73, below) displays.




Figure 5.73 I-Management Console - Mass Update / Validate dialog

For each invalid option value, the Validate dialog provides the following information:

- **Application** of the option containing the invalid value.
- **Option** for which there is an invalid value.
- **Value** that is invalid.
- **Warning Message** indicating why the value is invalid.

To modify a value, perform the following steps:


1. Click on the row of the invalid value.
2. Click the **Goto** button. The Validate dialog closes and the corresponding Profile Configurations tree and Profile Configurations Options table display for that option.
3. Modify the value and re-validate (or re-save) the option values.

## 5.7.12 Closing a Profile

Closing a profile de-selects it from the I-Management Console Profile tree and removes its information from the I-Management Console Profile Configurations tree, Profile Agents tree, and Profile Configurations Options table).

To close a selected profile, perform the following steps:


1. Close the profile either by:
  - Clicking **C**lose on the I-Management Console menu bar.
  - Clicking the **C**lose **P**rofile icon on the Mass Update tool bar.
  - Clicking on another profile in the Profile tree.
2. If you modified the profile that you want to close, but did not save it, the following dialog displays.



3. If you want to save (and close) the profile, click the **S**ave button.
4. If you want to close the profile without saving any of the changes made to it, click the **D**iscard button.
5. If you want to cancel the closing of the profile, click the **C**ancel button.

### Invalid Values in a Profile

If the profile contains one or more invalid option values, the following dialog displays when you attempt to save it.



Click **OK**. The Validation dialog then displays, which provides a means of correcting the invalid values (see Section [5.7.11 Correcting Invalid Profile Configuration Values](#)).

## 5.7.13 Deleting a Profile

To delete a profile, perform the following steps.

1. Select a profile from the Profile tree.
2. Click **Delete** on the **File** menu of the I-Management Console task bar. The Delete Profile dialog displays.




Figure 5.74 I-Management Console - Mass Update / Delete Profile dialog

3. Click **Yes** to delete the profile.

## 5.8 Commit Queue

The Commit Queue application lets you view the committed configurations.

It also lets you cancel any commit that has not yet completed (see Section 5.8.4 [Canceling a Commit](#)).

### 5.8.1 Accessing Commit Queue

To access the Commit Queue application, click the **Commit Queue** panel at the bottom left corner of the I-Management Console screen. The Commit Queue screen ([Figure 5.75](#), below) then displays.

Tracking	Status	User	Start	Completed	Success	Failed	Description
2	Completed	admin	Apr 25, 2008 ...	Apr 25, 2008 ...	0	1	Commit to ...
3	Completed	admin	9:54:15 AM	9:56:07 AM	0	1	Commit to ...
4	Completed	admin	10:27:43 AM	10:28:25 AM	0	1	Commit to ...
5	Completed	admin	10:28:21 AM	10:30:26 AM	0	1	Commit to ...

△ Agent	Status	Time	Message
test	Failed	Apr 25, 2008 5:58:1...	access denied

Figure 5.75 I-Management Console - Commit Queue screen

In addition to the [Menu Bar](#) and [Tool Bar](#), the Commit Queue screen is comprised of two regions:

- [Commit Summary](#) provides summary information about each commit (1).
- [Commit Detail](#) provides detail information about a commit selected in the Commit Summary (2).



## 5.8.2 Commit Summary

The Commit Summary region of the Commit Queue screen displays a row of summary information for each committed configuration.

Table 5.10, below, describes the information in each row.

Information	Description
Tracking	Tracking number of the commit.
Status	Pending, Hold, Cancelled, or Completed.
User	User that performed the commit.
Start	Start time of the commit.
Completed	Time that the commit was either Completed or Cancelled.
Profile	Profile name (if the commit was performed through Agent Update, this field contains the Agent name).
Description	Description of the profile provided by the user at the time of the commit.
Success	Number of Agents successfully completing the commit.
Failed	Number of Agents who failed to commit.

Table 5.10 I-Management Console - Commit Queue / Commit Summary Information

## 5.8.3 Commit Detail

The Commit Detail region of the Commit Queue screen displays detailed information for a configuration selected in the Commit Summary region.

Table 5.11, below, describes this information.

Information	Description
Agent	Agent that is the target of the commit.
Status	Pending, Success, Failed, or Cancelled.
Time	Time when the commit was performed on the Agent.
Message	Informational message for a failed commit to an Agent.

Table 5.11 I-Management Console - Commit Queue / Commit Detail Information

## 5.8.4 Canceling a Commit


You can cancel any commit that has not completed.

To permanently cancel a commit from completing, perform the following steps:

1. Click on a row in the Commit Summary region of the Commit Queue screen.
2. Select either:
  - **Cancel** icon from the I-Management Console tool bar.
  - **Cancel** from the I-Management Console menu bar / Actions menu.

The status of the commit in the Commit Summary region will change to **Cancelled**.

Note: If you try to cancel a commit that already has been completed, the following dialog displays.



# Customer Support

---

Stonebranch, Inc. provides customer support, via telephone and e-mail, for Universal Enterprise Controller Client Applications and all Stonebranch Solutions components.

## E-MAIL

---

### All Locations

[support@stonebranch.com](mailto:support@stonebranch.com)

Customer support contact via e-mail also can be made via the Stonebranch website:

[www.stonebranch.com](http://www.stonebranch.com)

## TELEPHONE

---

Customer support via telephone is available 24 hours per day, 7 days per week.

### North America

**(+1) 678 366-7887, extension 6**

**(+1) 877 366-7887, extension 6 [toll-free]**

### Europe

**+49 (0) 700 5566 7887**

---

# Index

---

## A

- About I-Activity Monitor *90*
  - About I-Administrator *35*
  - About I-Management Console *101*
  - accessing
    - Agent Update *102*
    - Commit Queue *144*
    - I-Management Console application *100*
    - Mass Update *119*
  - adding
    - Agent *52*
    - Agents in a profile *128*
    - configurations in a profile *126*
    - group *47, 54*
    - SAP system *58*
    - UACL entry *110, 133*
    - UEC connection *26*
    - user *38*
  - Agent
    - adding *52*
    - assigning to a group *53*
    - deleting *57*
    - editing *55*
    - installed components *104*
    - polling interval *53*
    - removing from a group *53*
  - Agent configurations
    - committing *113*
    - modifying *107*
    - saving as a profile *117*
    - validating (without committing) *115*
    - validation (automatically during commit) *113*
  - Agent Update *102*
    - accessing *102*
    - Agent tree *103*
    - Commit check box *107*
    - Configuration Options table *105*
    - Configuration tree *104*
  - Agents
    - assigning to a group *48*
    - removing from a group *48*
  - alert types in I-Activity Monitor Filter tree *72*
  - alerts
    - sending *53*
  - Alerts category in I-Activity Monitor *72*
  - assigning
    - Agent to a group *53*
    - Agents to a group *48*
    - configuration access to a user *43*
    - groups to a user *42*
    - SAP system to a group *59*
    - SAP systems to a group *48*
    - user permissions *40*
  - authentication of user *38*
- 
- ## C
  - cancelling a commit *146*
  - changing password for UEC Client Applications *32, 86*
  - closing a profile *142*
  - commit cancellation *146*

---

---

- Commit check box *107, 130*
- Commit Detail in Commit queue *145*
- Commit Queue
  - accessing *144*
  - Commit Detail *145*
  - Commit Summary *145*
- Commit Summary in Commit Queue *145*
- committing
  - Agent configurations *113*
  - profile *139*
- component stop *91*
- components installed on an Agent *104*
- configuration access
  - assigning to a user *43*
- Configuration Options table
  - Agent Update *105*
  - navigating *106*
  - redoing actions *108*
  - undoing actions *108*
- configuration rules *106, 124*
- Configuration tree in Agent Update *104*
- connecting to UEC *25*
- connection information (UEC) file *27*
- correcting an invalid value *116*
- creating a profile *125*
- customizing a I-Activity Monitor Data table *82*

## D

- Data table
  - customizing *82*
  - I-Activity Monitor *76*
  - resetting default layout *82*
  - saving layout *82*
  - sorting data *81*
  - updating information *83*
- deleting
  - Agent *57*
  - events *53*
  - group *51*
  - profile *143*
  - SAP system *63*
  - UACL entry *112, 135*
  - user *46*
- displaying
  - I-Activity Monitor Jobs table *83*
  - I-Activity Monitor Properties table *83*

## E

- editing

---

---

- Agent 55
- group 49
- SAP system 61
- UACL entry 111, 134
- user 45

events deletion 53

## F

- file types in I-Activity Monitor Filter tree 74
- files
  - I-Activity Monitor screen size 89
  - UEC connection information 27
- Files category in I-Activity Monitor 74
- filter group for I-Activity Monitor (default display) 87
- Filter Group panel
  - I-Activity Monitor 70
- filter tool in I-Activity Monitor Data table 79
- Filter tree icons 71
- Filter tree in I-Activity Monitor 71

## G

- group
  - adding 47, 54
  - assigning a SAP system 59
  - assigning Agents 48, 53
  - assigning SAP systems 48
  - assigning to a user 42
  - deleting 51
  - editing 49
  - removing a SAP system 59
  - removing Agents 48
  - removing an Agent 53
  - removing SAP systems 48

## I

- I-Activity Monitor
  - About 90
  - alert types in Filter tree 72
  - Data table 76
    - filter tool 79
    - icons 77
  - file types in Filter tree 74
  - Filter Group panel 70
  - Filter tree 71
  - job types in Filter tree 73
  - logging off 88
  - menu bar 67
  - screen size file 89

---

---

- setting initial filter group display 87
- stopping a component 91
- system types in Filter tree 75
- tool bar 68
- I-Activity Monitor screen 65
- I-Administrator
  - About 35
  - logging off 34
  - menu bar 32
  - tool bar 36
- I-Administrator screen 30
  - menu bar 32
- icons
  - I-Activity Monitor Data table 77
  - I-Activity Monitor Filter tree 71
  - I-Activity Monitor tool bar 68
- I-Management Console
  - About 101
  - accessing applications 100
  - logging off 100
  - menu bar 96
  - tool bar 98
- I-Management Console screen 94

## J

- job types in I-Activity Monitor Filter tree 73
- Jobs category in I-Activity Monitor 73
- Jobs table
  - displaying 83
  - information 85

## L

- layout
  - Data table default 82
  - I-Activity Monitor Data table 82
- logging in
  - UEC Client Applications 28
- logging off
  - I-Activity Monitor 88
  - I-Administrator 34
  - I-Management Console 100

## M

- managed mode 53
- Mass Update
  - accessing 119
  - Commit check box 130
  - Profile Agent tree 122

---

Profile Configurations Options table *123*  
Profile Configurations tree *121*  
Profile tree *120*  
menu bar  
  I-Activity Monitor *67*  
  I-Administrator *32*  
  I-Administrator screen *32*  
  I-Management Console *96*  
modifying  
  Agent configurations *107*  
  configurations for multiple Agents simultaneously *118*  
  profile configurations *130*  
  UACL entries *109, 132*  
moving down a UACL entry *112, 135*  
moving up a UACL entry *112, 135*

## N

NA values *76*  
navigating  
  in Configuration Options table *106*  
  in Profile Configurations Options table *124*

## P

password change for UEC Client Applications *32, 86*  
permissions assigned to a user *40*  
persistent events saving *53*  
polling interval  
  Agent *53*  
  commits *113*  
profile  
  adding Agents *128*  
  adding configurations *126*  
  as a saved Agent configurations *117*  
  closing *142*  
  committing *139*  
  configurations modification *130*  
  creating *125*  
  deleting *143*  
  removing Agents *128*  
  removing configurations *126*  
  saving *136*  
  saving as another profile *137*  
  validating (without saving) *138*  
  validation failure *141*  
Profile Agent tree in Mass Update *122*  
Profile Configurations Options table  
  Mass Update *123*  
  navigating *124*  
  redoing actions *131*



---

---

- undoing actions *131*
- Profile Configurations tree
  - Mass Update *121*
- Profile tree
  - Mass Update *120*
- Properties table
  - displaying *83*
  - information *84*

## R

- redoing
  - actions in Configuration Options table *108*
  - actions in Profile Configurations Options table *131*
- refreshing Universal Broker *113, 139*
- removing
  - Agent from a group *53*
  - Agents from a group *48*
  - Agents in a profile *128*
  - configurations in a profile *126*
  - SAP system from a group *59*
  - SAP systems from a group *48*
- resetting I-Activity Monitor Data table default layout *82*
- rules of configuration *106, 124*

## S

- SAP system
  - adding *58*
  - assigning to a group *59*
  - deleting *63*
  - editing *61*
  - removing from a group *59*
- SAP systems
  - assigning to a group *48*
  - removing from a group *48*
- saving
  - Agent configurations as a profile *117*
  - Data table layout *82*
  - persistent events *53*
  - profile as another profile *137*
  - profile configurations *136*
- screen size file (I-Activity Monitor) *89*
- sending alerts *53*
- setting
  - initial filter group display for I-Activity Monitor *87*
  - manage mode *53*
- sorting data in I-Activity Monitor Data table *81*
- stopping a UEC component *91*
- system types in I-Activity Monitor Filter tree *75*
- Systems category in I-Activity Monitor *75*

---

## T

### tool bar

- I-Activity Monitor *68*
- I-Administrator *36*
- I-Management Console *98*

## U

### UACL

- adding an entry *110, 133*
- modifying entries *109, 132*

### UACL entry

- deleting *112, 135*
- editing *111, 134*
- moving down *112, 135*
- moving up *112, 135*

### UEC

- connection information file *27*

### UEC Client Applications

- changing password *32, 86*
- logging in *28*
- running as Windows applications *24*

### UEC connection *25*

- adding *26*

### undoing

- actions in Configuration Options table *108*
- actions in Profile Configurations Options table *131*

### Universal Broker refresh *113, 139*

### updating I-Activity Monitor Data table information *83*

### user

- adding *38*
- assigned Agents and groups *103*
- assigning configuration access *43*
- assigning groups *42*
- assigning permissions *40*
- defined profiles *120*
- deleting *46*
- editing *45*
- method of authentication *38*

## V

### validating

- Agent configurations *115*
- profile (without saving) *138*

### validation failure

- profile *141*

### viewing committed configurations *144*





**950 North Point Parkway, Suite 200  
Alpharetta, Georgia 30005  
U.S.A.**

