



# Stonebranch Solutions

Version 4.2.0

## Universal Connector Reference Guide

usap-ref-4201



---

# Universal Connector

## Reference Guide

Stonebranch Solutions 4.2.0

---

<b>Document Name</b>	<b>Universal Connector 4.2.0 Reference Guide</b>				
<b>Document ID</b>	<b>usap-ref-4201</b>				
<b>Components</b>	<b>z/OS</b>	<b>UNIX</b>	<b>Windows</b>	<b>IBM i</b>	<b>HP NonStop</b>
Universal Connector	√	√			

---

# Stonebranch Documentation Policy

---

This document contains proprietary information that is protected by copyright. All rights reserved. No part of this publication may be reproduced, transmitted or translated in any form or language or by any means, electronic or mechanical, including photocopy, recording, or any information storage and retrieval system, without permission, in writing, from the publisher. Requests for permission to make copies of any part of this publication should be mailed to:

Stonebranch, Inc.  
950 North Point Parkway, Suite 200  
Alpharetta, GA 30005 USA  
Tel: (678) 366-7887  
Fax: (678) 366-7717

Stonebranch, Inc.<sup>®</sup> makes no warranty, express or implied, of any kind whatsoever, including any warranty of merchantability or fitness for a particular purpose or use.

The information in this documentation is subject to change without notice.

Stonebranch shall not be liable for any errors contained herein or for incidental or consequential damages in connection with the furnishing, performance or use of this document.

All products mentioned herein are or may be trademarks of their respective owners.

© 2003-2010 by Stonebranch, Inc.

All rights reserved.



---

# Summary of Changes

---

Changes for Universal Controller 4.2.0 Reference Guide  
(usap-ref-4201)  
October 29, 2010

- Changed configuration file keyword from **Client** to **client** in Section [5.13 CLIENT](#).
- Modified the configuration option description in:
  - Section [5.17 ENCRYPT\\_FILE](#)
  - Section [5.34 FILE\\_NAME](#)
- Added the USAPFROMTIME environment variable to Section [5.36 FROM\\_TIME](#).
- Add the USAPTOTIME environment variable to Section [5.104 TO\\_TIME](#).

Changes for Universal Connector 4.2.0 Reference Guide  
(usap-ref-4200)  
August 6, 2010

## **Universal Connector 4.2.0.0**

- Moved information from Universal Connector 4.1.0 User Guide into Universal Connector 4.2.0 Reference Guide. Information on component features and examples was moved to the Indesca 4.2.0 User Guide.
- Removed all information on the Universal Connector CM Interface.

---

Changes for Universal Connector 4.1.0 Reference Guide  
(usap-ref-4100)  
February 10, 2010

#### **Universal Connector 4.1.0.0**

- Added the following options in Chapter 5 [Universal Connector Configuration Options](#):
  - [MASS\\_ACTIVITY\\_WAIT](#)
  - [RETURN\\_APPLICATION\\_LOG](#)
  - [RETURN\\_APPLICATION\\_RC](#)
  - [USE\\_APPLICATION\\_RC](#)

Changes for Universal Controller 3.2.0 User Guide  
(usap-user-3204)  
September 8, 2009

#### **Universal Connector 3.2.0.2**

- Added [SPOOL\\_CODEPAGE](#) configuration option.

Changes for Universal Connector 3.2.0 Reference Guide  
(usap-ref-3203)  
April 1, 2009

#### **Universal Connector 3.2.0.1**

- Added " " as a value for the [LOGON\\_LANGUAGE](#) configuration option.
- Added audit as a value for the [MESSAGE\\_LEVEL](#) configuration option.
- Added the following configuration options:
  - [INSTALLATION\\_DIRECTORY](#)
  - [SERVER\\_STOP\\_CONDITIONS](#)
  - [TARGET\\_VARIANT](#)

Changes for Universal Connector 3.2.0 Reference Guide  
(usap-ref-3202)  
December 17, 2008

- Changed the name of the environment variable for the [SYSTEM\\_ID](#) configuration option from **USAPSYSTEM** to **USAPSYSTEMID**.

---

Changes for Universal Connector 3.2.0 Reference Guide  
(usap-ref-3201)  
September 5, 2008

- Added toll-free telephone number for North America in [Appendix A Customer Support](#).

Changes for Universal Connector 3.2.0 Reference Guide  
(usap-ref-320)  
May 16, 2008

### **Universal Connector 3.2.0.0**

- Added the following configuration options in [Chapter 5 Universal Connector Configuration Options](#):
  - [ACTIVITY\\_MONITORING](#)
  - [AS\\_HOST](#)
  - [BIF\\_DIRECTORY](#)
  - [DISPLAY\\_CLIENT](#)
  - [EVENT\\_GENERATION](#)
  - [MAX\\_XBP](#)
  - [PLF\\_DIRECTORY](#)
  - [SYSTEM\\_ID](#)
  - [SYSTEM\\_NUMBER](#)
  - [TRACE\\_FILE\\_LINES](#)
  - [TRACE\\_TABLE](#)
  - [VARIANT\\_LANGUAGE](#)
- Removed the following configuration options from [Chapter 5 Universal Connector Configuration Options](#):
  - [RETURN\\_CODE\\_PAIR\\_00](#)
  - [RETURN\\_CODE\\_PAIR\\_04](#)
  - [RETURN\\_CODE\\_PAIR\\_08](#)
  - [RETURN\\_CODE\\_PAIR\\_16](#)

---

# Contents

---

Summary of Changes .....	5
Contents .....	8
List of Figures .....	17
List of Tables .....	20
Preface .....	23
Document Structure .....	23
Document Information .....	26
1 Overview of Universal Connector .....	27
1.1 Introduction .....	27
1.1.1 Universal Connector Functionality .....	28
1.1.2 Universal Connector Communications .....	28
1.2 Supported SAP Versions .....	29
1.2.1 XBP 2.0 Support .....	29
1.2.2 XBP 3.0 Support .....	30
1.3 SAP User Authorization Requirements .....	31
2 Universal Connector for z/OS.....	32
2.1 Overview .....	32
2.2 Usage .....	33
2.2.1 JCL Procedure .....	33



2.2.2 DD Statements used in JCL Procedure	34
2.2.3 JCL	34
2.2.4 Command Line Syntax	35
2.3 Commands	36
2.3.1 Command Groups	36
2.3.2 RUN JOB Command	38
2.3.3 RUN FS JOB NETWORK Command	41
2.3.4 SUBMIT JOB Command	42
2.3.5 SUBMIT VARIANT Command	44
2.3.6 SUBMIT INTERCEPT CRITERIA TABLE Command	45
2.3.7 SUBMIT FS JOBNET Command	46
2.3.8 MODIFY JOB Command	47
2.3.9 MODIFY VARIANT Command	49
2.3.10 START JOB Command	50
2.3.11 START FS JOBNET Command	52
2.3.12 WAIT for JOB Command	53
2.3.13 MASS ACTIVITY WAIT Command	55
2.3.14 WAIT for FS JOB NETWORK Command	57
2.3.15 BDCWAIT Command	58
2.3.16 ABORT Command	60
2.3.17 PURGE JOB Command	61
2.3.18 PURGE FS JOB NETWORK Command	62
2.3.19 RAISE EVENT Command	63
2.3.20 SYNTAX Command	64
2.3.21 DISPLAY JOBLOG Command	65
2.3.22 DISPLAY SPOOLIST Command	66
2.3.23 DISPLAY STATUS Command	67
2.3.24 DISPLAY VARIANTS Command	69
2.3.25 DISPLAY VARIANT Command	70
2.3.26 DISPLAY JOBDEF Command	71
2.3.27 DISPLAY SELECT Command	72
2.3.28 DISPLAY SYSLOG Command	74
2.3.29 DISPLAY INTERCEPTED_JOBS Command	75
2.3.30 DISPLAY INTERCEPT_TABLE Command	76
2.3.31 DISPLAY QSTATE Command	77
2.3.32 DISPLAY REPORTS Command	78
2.3.33 DISPLAY COMMANDS Command	79
2.3.34 DISPLAY OUTPUT_DEVICES Command	80
2.3.35 DISPLAY PRINT_FORMATS Command	81
2.3.36 GENERATE JOB DEFINITION FILE Command	82

2.3.37	GENERATE VARIANT DEFINITION FILE Command	83
2.4	Configuration Options	84
2.4.1	Configuration Option Categories	84
2.4.2	HOST Options	85
2.4.3	USER Options	86
2.4.4	CFT Options	87
2.4.5	COMMAND FILE Options	88
2.4.6	EVENT Options	90
2.4.7	INFORMATIONAL Options	91
2.4.8	LOCAL Options	92
2.4.9	MESSAGE Options	93
2.4.10	RFC Options	94
2.5	Exit Codes	95
2.5.1	WAIT for JOB Exit Codes	95
2.5.2	WAIT for FS JOB NETWORK Exit Codes	95
2.5.3	DISPLAY STATUS Exit Codes	96
2.5.4	DISPLAY OSTATE Exit Codes	96
2.5.5	All Other Command Exit Codes	97
3	Universal Connector for UNIX	98
3.1	Overview	98
3.2	Usage	99
3.2.1	Command Line Syntax	99
3.3	Commands	100
3.3.1	Command Groups	100
3.3.2	RUN JOB Command	102
3.3.3	RUN FS JOB NETWORK Command	105
3.3.4	SUBMIT JOB Command	106
3.3.5	SUBMIT VARIANT Command	108
3.3.6	SUBMIT INTERCEPT CRITERIA TABLE Command	109
3.3.7	SUBMIT FS JOBNET Command	110
3.3.8	MODIFY JOB Command	111
3.3.9	MODIFY VARIANT Command	114
3.3.10	START JOB Command	115
3.3.11	START FS JOBNET Command	117
3.3.12	WAIT for JOB Command	118
3.3.13	MASS ACTIVITY WAIT Command	120
3.3.14	WAIT for FS JOB NETWORK Command	122
3.3.15	BDCWAIT Command	123

3.3.16	ABORT Command	125
3.3.17	PURGE JOB Command	126
3.3.18	PURGE FS JOB NETWORK Command	127
3.3.19	RAISE EVENT Command	128
3.3.20	SYNTAX Command	129
3.3.21	DISPLAY JOBLIST Command	130
3.3.22	DISPLAY SPOOLIST Command	131
3.3.23	DISPLAY STATUS Command	132
3.3.24	DISPLAY VARIANTS Command	134
3.3.25	DISPLAY VARIANT Command	135
3.3.26	DISPLAY JOBDEF Command	136
3.3.27	DISPLAY SELECT Command	137
3.3.28	DISPLAY SYSLOG Command	139
3.3.29	DISPLAY INTERCEPTED_JOBS Command	140
3.3.30	DISPLAY INTERCEPT_TABLE Command	141
3.3.31	DISPLAY OSTATE Command	142
3.3.32	DISPLAY REPORTS Command	143
3.3.33	DISPLAY COMMANDS Command	144
3.3.34	DISPLAY OUTPUT_DEVICES Command	145
3.3.35	DISPLAY PRINT_FORMATS Command	146
3.3.36	GENERATE JOB DEFINITION FILE Command	147
3.3.37	GENERATE VARIANT DEFINITION FILE Command	148
3.4	Configuration Options	149
3.4.1	Configuration Option Categories	149
3.4.2	HOST Options	150
3.4.3	USER Options	151
3.4.4	CFT Options	152
3.4.5	COMMAND FILE Options	153
3.4.6	EVENT Options	155
3.4.7	INFORMATIONAL Options	156
3.4.8	INSTALLATION Options	157
3.4.9	LOCAL Options	158
3.4.10	MESSAGE Options	159
3.4.11	RFC Options	160
3.5	Exit Codes	161
3.5.1	WAIT for JOB Exit Codes	161
3.5.2	WAIT for FS JOB NETWORK Exit Codes	161
3.5.3	DISPLAY STATUS Exit Codes	162
3.5.4	DISPLAY OSTATE Exit Codes	162
3.5.5	All Other Command Exit Codes	163

4	Universal Connector Job Definition Files .....	164
4.1	Overview .....	164
4.2	Standard USAP Job Definition File Syntax .....	165
4.2.1	Keywords .....	165
4.3	Keywords for Job Header Statement .....	166
4.4	Keywords for ABAP Step Statement .....	168
4.5	Keywords for External Step Statement .....	172
4.6	Keywords for External Command Step Statement .....	173
4.7	Sample USAP Job Definition File .....	174
4.8	Variant Definition File .....	175
4.8.1	Variant Definition File Syntax .....	175
4.8.2	Keywords .....	176
4.8.3	Sample Variant Definition File .....	178
4.9	Job Intercept Table Definition File .....	179
4.9.1	Job Intercept Table Definition File Syntax .....	179
4.9.2	Keywords .....	180
4.9.3	Sample Job Intercept Table Definition File .....	181
4.10	FS Job Network Definition File .....	182
4.10.1	FS Job Network Definition File Syntax .....	182
4.10.2	Keywords .....	183
4.11	Spoolist Translation Tables .....	187
4.11.1	Spoolist Translation Table File Format .....	187
5	Universal Connector Configuration Options .....	188
5.1	Overview .....	188
5.2	Configuration Options Information .....	189
5.3	Configuration Options List .....	191
5.4	ABAP_NAME .....	196
5.5	ACTIVITY_MONITORING .....	197
5.6	ALLOW_AUTO_RESTART .....	198
5.7	AS_HOST .....	199
5.8	BATCH_MONITOR .....	200
5.9	BIF_DIRECTORY .....	201
5.10	CFT_ABAP_PROGRAM .....	202
5.11	CFT_COMMAND_PREFIX .....	203

5.12 CFT_TARGET_HOST .....	204
5.13 CLIENT .....	205
5.14 COMMAND_ID .....	206
5.15 DESTINATION .....	207
5.16 DISPLAY_CLIENT .....	208
5.17 ENCRYPT_FILE .....	209
5.18 ENCRYPTION_KEY .....	210
5.19 EVENT_GENERATION .....	211
5.20 EVENT_ID .....	213
5.21 EVENT_PARAMETER .....	214
5.22 EXIT_JOB_ACTIVE .....	215
5.23 EXIT_JOB_FINISHED .....	216
5.24 EXIT_JOB_READY .....	217
5.25 EXIT_JOB_RELEASED .....	218
5.26 EXIT_JOB_SCHEDULED .....	219
5.27 EXIT_JOB_TERMINATED .....	220
5.28 EXIT_QUEUE_BACKGROUND .....	221
5.29 EXIT_QUEUE_CREATED .....	222
5.30 EXIT_QUEUE_ERROR .....	223
5.31 EXIT_QUEUE_FINISHED .....	224
5.32 EXIT_QUEUE_UNPROCESSED .....	225
5.33 EXTERNAL_COMMAND .....	226
5.34 FILE_NAME .....	227
5.35 FROM_DATE .....	228
5.36 FROM_TIME .....	229
5.37 HELP .....	230
5.38 IMMEDIATE_JOB .....	231
5.39 INSTALLATION_DIRECTORY .....	232
5.40 JOB_ID .....	233
5.41 JOB_ID_PATTERN .....	234
5.42 JOB_LOG_CHILD .....	235
5.43 JOB_NAME .....	236

5.44	JOB_NAME_PATTERN	237
5.45	JOB_NETWORK_ID	238
5.46	JOB_PROCESS_ID	239
5.47	LAYOUT_NAME	240
5.48	LISTEN_INTERVAL	241
5.49	LOGON_LANGUAGE	242
5.50	LOGON_RETRY_COUNT	243
5.51	LOGON_RETRY_INTERVAL	244
5.52	LONG_DEVICE_NAME	245
5.53	MASS_ACTIVITY_WAIT	246
5.54	MAX_CHILD_DEPTH	247
5.55	MAX_HIT_COUNT	248
5.56	MAX_JOB_LOG_SIZE	249
5.57	MAX_SPOOL_LIST_SIZE	250
5.58	MAX_XBP	251
5.59	MESSAGE_LANGUAGE	252
5.60	MESSAGE_LEVEL	253
5.61	NO_START_DATE	254
5.62	OPERATING_SYSTEM	255
5.63	OUTPUT_FIELD_LIST	256
5.64	PAGE_LIMIT	258
5.65	PASSWORD	259
5.66	PLF_DIRECTORY	260
5.67	PRINTER_NAME	261
5.68	PURGE_BDC_MAP	262
5.69	PURGE_CHILD_JOBS	263
5.70	PURGE_JOB	264
5.71	QUEUE_ID	265
5.72	QUEUE_ID_PATTERN	266
5.73	RESTART	267
5.74	RETRY_CALL_COUNT	269
5.75	RETRY_CALL_INTERVAL	270

5.76 RETURN_APPLICATION_LOG .....	271
5.77 RETURN_APPLICATION_RC .....	272
5.78 RETURN_JOB_LOG .....	273
5.79 RETURN_SPOOL_LIST .....	274
5.80 SECURE_CFT .....	275
5.81 SERVER_STOP_CONDITIONS .....	276
5.82 SPOOL_CODEPAGE .....	277
5.83 SPOOL_LIST_CHILD .....	278
5.84 START_JOB .....	279
5.85 STATUS_ABORTED .....	280
5.86 STATUS_CHECK_INTERVAL .....	281
5.87 STATUS_FINISHED .....	282
5.88 STATUS_READY .....	283
5.89 STATUS_RELEASED .....	284
5.90 STATUS_RUNNING .....	285
5.91 STATUS_SCHEDULED .....	286
5.92 STEP_NUMBER .....	287
5.93 SYSLOG .....	288
5.94 SYSLOG_POST_TIME .....	289
5.95 SYSLOG_PRE_TIME .....	290
5.96 SYSTEM_ID .....	291
5.97 SYSTEM_NUMBER .....	292
5.98 TARGET_JOB_NAME .....	293
5.99 TARGET_SERVER .....	294
5.100 TARGET_VARIANT .....	295
5.101 TECHNICAL_DEVICE_NAME .....	296
5.102 TIMEOUT_INTERVAL .....	297
5.103 TO_DATE .....	298
5.104 TO_TIME .....	299
5.105 TRACE_DIRECTORY .....	300
5.106 TRACE_FILE_LINES .....	301
5.107 TRACE_TABLE .....	302

5.108 TRANSLATION_TABLE .....	304
5.109 USAP_POLL .....	305
5.110 USE_APPLICATION_RC .....	306
5.111 USER_ID .....	307
5.112 USER_NAME .....	308
5.113 VARIANT .....	309
5.114 VARIANT_LANGUAGE .....	310
5.115 VARIANT_SELECTION .....	311
5.116 VERSION .....	312
5.117 WAIT .....	313
5.118 WAIT_FOR_CHILD_JOBS .....	314
5.119 WITH_PREDECESSOR .....	315
5.120 XMI_AUDIT_LEVEL .....	316
A Customer Support .....	317



---

# List of Figures

---

2	Universal Connector for z/OS .....	32
	Figure 2.1 Universal Connector for z/OS – JCL Procedure .....	33
	Figure 2.2 Universal Connector for z/OS – JCL .....	34
	Figure 2.3 Universal Connector for z/OS - Command Line Syntax .....	35
	Figure 2.4 RUN JOB Command Line Syntax .....	39
	Figure 2.5 RUN FS JOB NETWORK Command Line Syntax .....	41
	Figure 2.6 SUBMIT JOB Command Line Syntax .....	42
	Figure 2.7 SUBMIT VARIANT Command Line Syntax .....	44
	Figure 2.8 SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax .....	45
	Figure 2.9 SUBMIT FS JOBNET Command Line Syntax .....	46
	Figure 2.10 MODIFY JOB Command Line Syntax .....	47
	Figure 2.11 MODIFY VARIANT Command Line Syntax .....	49
	Figure 2.12 START JOB Command Line Syntax .....	50
	Figure 2.13 START FS JOBNET Command Line Syntax .....	52
	Figure 2.14 WAIT for JOB Command Line Syntax .....	53
	Figure 2.15 MASS ACTIVITY WAIT Command Line Syntax .....	55
	Figure 2.16 WAIT for FS JOB NETWORK Command Line Syntax .....	57
	Figure 2.17 BDCWAIT Command Line Syntax .....	58
	Figure 2.18 ABORT Command Line Syntax .....	60
	Figure 2.19 PURGE JOB Command Line Syntax .....	61
	Figure 2.20 PURGE FS JOB NETWORK Command Line Syntax .....	62
	Figure 2.21 RAISE EVENT Command Line Syntax .....	63
	Figure 2.22 SYNTAX Command Line Syntax .....	64
	Figure 2.23 DISPLAY JOBLOG Command Line Syntax .....	65
	Figure 2.24 DISPLAY SPOOLLIST Command Line Syntax .....	66
	Figure 2.25 DISPLAY STATUS Command Line Syntax .....	67
	Figure 2.26 DISPLAY VARIANTS Command Line Syntax .....	69
	Figure 2.27 DISPLAY VARIANT Command Line Syntax .....	70
	Figure 2.28 DISPLAY JOBDEF Command Line Syntax .....	71
	Figure 2.29 DISPLAY SELECT Command Line Syntax .....	72
	Figure 2.30 DISPLAY SYSLOG Command Line Syntax .....	74
	Figure 2.31 DISPLAY INTERCEPTED_JOBS Command Line Syntax .....	75
	Figure 2.32 DISPLAY INTERCEPT_TABLE Command Line Syntax .....	76

Figure 2.33	DISPLAY OSTATE Command Line Syntax .....	77
Figure 2.34	DISPLAY REPORTS Command Line Syntax .....	78
Figure 2.35	DISPLAY COMMANDS Command Line Syntax .....	79
Figure 2.36	DISPLAY OUTPUT_DEVICES Command Line Syntax .....	80
Figure 2.37	DISPLAY PRINT_FORMATS Command Line Syntax .....	81
Figure 2.38	GENERATE JOB DEFINITION FILE Command Line Syntax .....	82
Figure 2.39	GENERATE VARIANT DEFINITION FILE Command Line Syntax .....	83
Figure 2.40	HOST Options Syntax .....	85
Figure 2.41	USER Options Syntax .....	86
Figure 2.42	CFT Options Syntax .....	87
Figure 2.43	Command File (Plain Text) Options Syntax .....	88
Figure 2.44	Command File (Encrypted) Options Syntax .....	89
Figure 2.45	EVENT Options Syntax .....	90
Figure 2.46	INFORMATIONAL Options Syntax .....	91
Figure 2.47	LOCAL Options Syntax .....	92
Figure 2.48	MESSAGE Options Syntax .....	93
Figure 2.49	RFC Options Syntax .....	94
3	Universal Connector for UNIX .....	98
Figure 3.1	Universal Connector for UNIX - Command Line Syntax .....	99
Figure 3.2	RUN JOB Command Line Syntax .....	103
Figure 3.3	RUN FS JOB NETWORK Command Line Syntax .....	105
Figure 3.4	SUBMIT JOB Command Line Syntax .....	106
Figure 3.5	SUBMIT VARIANT Command Line Syntax .....	108
Figure 3.6	SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax .....	109
Figure 3.7	SUBMIT FS JOBNET Command Line Syntax .....	110
Figure 3.8	MODIFY JOB Command Line Syntax .....	112
Figure 3.9	MODIFY VARIANT Command Line Syntax .....	114
Figure 3.10	START JOB Command Line Syntax .....	115
Figure 3.11	START FS JOBNET Command Line Syntax .....	117
Figure 3.12	WAIT for JOB Command Line Syntax .....	118
Figure 3.13	MASS ACTIVITY WAIT Command Line Syntax .....	120
Figure 3.14	WAIT for FS JOB NETWORK Command Line Syntax .....	122
Figure 3.15	BDCWAIT Command Line Syntax .....	123
Figure 3.16	ABORT Command Line Syntax .....	125
Figure 3.17	PURGE JOB Command Line Syntax .....	126
Figure 3.18	PURGE FS JOB NETWORK Command Line Syntax .....	127
Figure 3.19	RAISE EVENT Command Line Syntax .....	128
Figure 3.20	SYNTAX Command Line Syntax .....	129
Figure 3.21	DISPLAY JOBLOG Command Line Syntax .....	130
Figure 3.22	DISPLAY SPOOLIST Command Line Syntax .....	131
Figure 3.23	DISPLAY STATUS Command Line Syntax .....	132
Figure 3.24	DISPLAY VARIANTS Command Line Syntax .....	134
Figure 3.25	DISPLAY VARIANT Command Line Syntax .....	135
Figure 3.26	DISPLAY JOBDEF Command Line Syntax .....	136
Figure 3.27	DISPLAY SELECT Command Line Syntax .....	137
Figure 3.28	DISPLAY SYSLOG Command Line Syntax .....	139
Figure 3.29	DISPLAY INTERCEPT_JOBS Command Line Syntax .....	140
Figure 3.30	DISPLAY INTERCEPT_TABLE Command Line Syntax .....	141

Figure 3.31	DISPLAY OSTATE Command Line Syntax .....	142
Figure 3.32	DISPLAY REPORTS Command Line Syntax .....	143
Figure 3.33	DISPLAY COMMANDS Command Line Syntax .....	144
Figure 3.34	DISPLAY OUTPUT_DEVICES Command Line Syntax .....	145
Figure 3.35	DISPLAY PRINT_FORMATS Command Line Syntax .....	146
Figure 3.36	GENERATE JOB DEFINITION FILE Command Line Syntax .....	147
Figure 3.37	GENERATE VARIANT DEFINITION FILE Command Line Syntax .....	148
Figure 3.38	HOST Options Syntax .....	150
Figure 3.39	USER Options Syntax .....	151
Figure 3.40	CFT Options Syntax .....	152
Figure 3.41	COMMAND FILE (Plain Text) Options Syntax .....	153
Figure 3.42	COMMAND FILE (Encrypted) Options Syntax .....	154
Figure 3.43	EVENT Options Syntax .....	155
Figure 3.44	INFORMATIONAL Options Syntax .....	156
Figure 3.45	INSTALLATION Options Syntax .....	157
Figure 3.46	LOCAL Options Syntax .....	158
Figure 3.47	MESSAGE Options Syntax .....	159
Figure 3.48	RFC Options Syntax .....	160
4	Universal Connector Job Definition Files .....	164
Figure 4.1	USAP Standard Job Definition Syntax .....	165
Figure 4.2	USAP Job Definition File .....	174
Figure 4.3	USAP Variant Definition Syntax .....	175
Figure 4.4	Variant Definition File (Sample) .....	178
Figure 4.5	USAP Job Intercept Table Definition Syntax .....	179
Figure 4.6	Job Intercept Table Definition File (Sample) .....	181
Figure 4.7	USAP FS Jobnet Definition Syntax .....	182
Figure 4.8	FS Job Network Definition File (Sample) .....	186

---

# List of Tables

---

Preface .....	23
Table P.1    Command Line Syntax .....	24
2    Universal Connector for z/OS .....	32
Table 2.1    Universal Connector for z/OS – DD Statements in JCL Procedure .....	34
Table 2.2    USAP for z/OS - Command Groups .....	37
Table 2.3    RUN JOB Command Options .....	40
Table 2.4    RUN FS JOB NETWORK Command Options .....	41
Table 2.5    SUBMIT JOB Command Options .....	43
Table 2.6    SUBMIT FS JOBNET Command Options .....	46
Table 2.7    MODIFY JOB Command Options .....	48
Table 2.8    START JOB Command Options .....	51
Table 2.9    START FS JOBNET Command Options .....	52
Table 2.10   WAIT for JOB Command Options .....	54
Table 2.11   MASS ACTIVITY WAIT Command Options .....	56
Table 2.12   WAIT for FS JOB NETWORK Command Options .....	57
Table 2.13   BDCWAIT Command Options .....	59
Table 2.14   ABORT Command Options .....	60
Table 2.15   PURGE JOB Command Options .....	61
Table 2.16   PURGE FS JOB NETWORK Command Options .....	62
Table 2.17   RAISE EVENT Command Options .....	63
Table 2.18   DISPLAY JOBLIST Command Options .....	65
Table 2.19   DISPLAY SPOOLIST Command Options .....	66
Table 2.20   DISPLAY STATUS Command Options .....	68
Table 2.21   DISPLAY VARIANTS Command Options .....	69
Table 2.22   DISPLAY VARIANT Command Options .....	70
Table 2.23   DISPLAY JOBDEF Command Options .....	71
Table 2.24   DISPLAY SELECT Command Options .....	73
Table 2.25   DISPLAY SYSLOG Command Options .....	74
Table 2.26   DISPLAY INTERCEPTED_JOBS Command Options .....	75
Table 2.27   DISPLAY QSTATE Command Options .....	77
Table 2.28   DISPLAY REPORTS Command Options .....	78

Table 2.29	DISPLAY COMMANDS Command Options .....	79
Table 2.30	DISPLAY OUTPUT_DEVICES Command Options .....	80
Table 2.31	DISPLAY PRINT_FORMATS Command Options .....	81
Table 2.32	GENERATE JOB DEFINITION FILE Command Options .....	82
Table 2.33	GENERATE VARIANT DEFINITION FILE Command Options .....	83
Table 2.34	Universal Connector for z/OS - Configuration Option Categories .....	84
Table 2.35	HOST Options .....	85
Table 2.36	USER Options .....	86
Table 2.37	CFT Options .....	87
Table 2.38	COMMAND FILE (Plain Text) Options .....	88
Table 2.39	COMMAND FILE (Encrypted) Options .....	89
Table 2.40	EVENT Options .....	90
Table 2.41	INFORMATIONAL Options .....	91
Table 2.42	LOCAL Options .....	92
Table 2.43	MESSAGE Options .....	93
Table 2.44	RFC Options .....	94
Table 2.45	z/OS Wait for Job Exit Codes .....	95
Table 2.46	z/OS Wait for FS Job Network Exit Codes .....	95
Table 2.47	z/OS DISPLAY STATUS Exit Codes .....	96
Table 2.48	z/OS Queue State Exit Codes .....	96
Table 2.49	USAP for z/OS - Exit Codes .....	97
3	Universal Connector for UNIX .....	98
Table 3.1	USAP for UNIX - Command Groups .....	101
Table 3.2	RUN JOB Command Options .....	104
Table 3.3	RUN FS JOB NETWORK Command Options .....	105
Table 3.4	SUBMIT JOB Command Options .....	107
Table 3.5	SUBMIT FS JOBNET Command Options .....	110
Table 3.6	MODIFY JOB Command Options .....	113
Table 3.7	START JOB Command Options .....	116
Table 3.8	START FS JOBNET Command Options .....	117
Table 3.9	WAIT for JOB Command Options .....	119
Table 3.10	MASS ACTIVITY WAIT Command Options .....	121
Table 3.11	WAIT for FS JOB NETWORK Command Options .....	122
Table 3.12	BDCWAIT Command Options .....	124
Table 3.13	ABORT Command Options .....	125
Table 3.14	PURGE JOB Command Options .....	126
Table 3.15	PURGE FS JOB NETWORK Command Options .....	127
Table 3.16	RAISE EVENT Command Options .....	128
Table 3.17	DISPLAY JOBLIST Command Options .....	130
Table 3.18	DISPLAY SPOOLLIST Command Options .....	131
Table 3.19	DISPLAY STATUS Command Options .....	133
Table 3.20	DISPLAY VARIANTS Command Options .....	134
Table 3.21	DISPLAY VARIANT Command Options .....	135
Table 3.22	DISPLAY JOBDEF Command Options .....	136
Table 3.23	DISPLAY SELECT Command Options .....	138
Table 3.24	DISPLAY SYSLOG Command Options .....	139
Table 3.25	DISPLAY INTERCEPTED_JOBS Command Options .....	140
Table 3.26	DISPLAY QSTATE Command Options .....	142

Table 3.27	DISPLAY REPORTS Command Options .....	143
Table 3.28	DISPLAY COMMANDS Command Options .....	144
Table 3.29	DISPLAY OUTPUT_DEVICES Command Options .....	145
Table 3.30	DISPLAY PRINT_FORMATS Command Options .....	146
Table 3.31	GENERATE JOB DEFINITION FILE Command Options .....	147
Table 3.32	GENERATE VARIANT DEFINITION FILE Command Options .....	148
Table 3.33	Universal Connector for UNIX - Configuration Option Categories .....	149
Table 3.34	HOST Options .....	150
Table 3.35	USER Options .....	151
Table 3.36	CFT Options .....	152
Table 3.37	COMMAND FILE (Plain Text) Options .....	153
Table 3.38	COMMAND FILE (Encrypted) Options .....	154
Table 3.39	EVENT Options .....	155
Table 3.40	INFORMATIONAL Options .....	156
Table 3.41	INSTALLATION Options .....	157
Table 3.42	LOCAL Options .....	158
Table 3.43	MESSAGE Options .....	159
Table 3.44	RFC Options .....	160
Table 3.45	UNIX Wait for Job Exit Codes .....	161
Table 3.46	UNIX Wait for FS Job Network Exit Codes .....	161
Table 3.47	UNIX DISPLAY STATUS Exit Codes .....	162
Table 3.48	UNIX Queue State Exit Codes .....	162
Table 3.49	USAP for UNIX - Exit Codes .....	163
4	Universal Connector Job Definition Files .....	164
Table 4.1	Job Header Keywords .....	167
Table 4.2	ABAP Step Keywords .....	171
Table 4.3	External Step Keywords .....	172
Table 4.4	External Command Step Keywords .....	173
Table 4.5	Variant Header Keywords .....	176
Table 4.6	Variant Text Step Keywords .....	176
Table 4.7	Variant Content Step Keywords .....	177
Table 4.8	Job Intercept Table Header Keywords .....	180
Table 4.9	Job Intercept Row Step Keywords .....	180
Table 4.10	FS Jobnet Header Keywords .....	183
Table 4.11	FS Jobnet Process Step Keywords .....	183
Table 4.12	FS Jobnet Process Relation Step Keywords .....	184
5	Universal Connector Configuration Options .....	188
Table 5.1	Universal Connector - Configuration Options .....	195
Table 5.2	BAPIXMJOB Structure Fields .....	257

---

# Preface

---

## Document Structure

This document is written using specific conventions for text formatting and according to a specific document structure in order to make it as useful as possible for the largest audience. The following sections describe the document formatting conventions and organization.

## Cross-Reference Links

---

This document contains cross-reference links to and from other Stonebranch Solutions documentation.

In order for the links to work correctly:

- Place the documents in the same folder.
- In Adobe Reader / Adobe Acrobat, de-select **Open cross-document link in same window** in the **General** category of your **Preferences** dialog (selected from the **Edit** menu).

## Conventions

Specific text formatting conventions are used within this document to represent different information. The following conventions are used.

### Typeface and Fonts

This document provides tables that identify how information is used. These tables identify values and/or rules that are either pre-defined or user-defined:

- *Italics* denotes user-supplied information.
- **Boldface** indicates pre-defined information.

Elsewhere in this document, **This Font** identifies specific names of different types of information, such as file names or directories (for example, `\abc\123\he1p.txt`).

### Command Line Syntax Diagrams

Command line syntax diagrams use the following conventions:

Convention	Description
<b>bold monospace font</b>	Specifies values to be typed verbatim, such as file / data set names.
<i>italic monospace font</i>	Specifies values to be supplied by the user.
[ ]	Encloses configuration options or values that are optional.
{ }	Encloses configuration options or values of which one must be chosen.
	Separates a list of possible choices.
...	Specifies that the previous item may be repeated one or more times.
<b>BOLD UPPER CASE</b>	Specifies a group of options or values that are defined elsewhere.

Table P.1 Command Line Syntax

### Operating System-Specific Text

Most of this document describes the product in the context of all supported operating systems. At times, it is necessary to refer to operating system-specific information. This information is introduced with a special header, which is followed by the operating system-specific text in a different font size from the normal text.

**z/OS**

This text pertains specifically to the z/OS line of operating systems.

This text resumes the information pertaining to all operating systems.



## Tips from the Stoneman



### Stoneman's Tip

Look to the Stoneman for suggestions or for any other information that requires special attention.

## Vendor References

References are made throughout this document to a variety of vendor operating systems. We attempt to use the most current product names when referencing vendor software.

The following names are used within this document:

- **z/OS** is synonymous with IBM z/OS and IBM OS/390 line of operating systems.
- **Windows** is synonymous with Microsoft's Windows 2000 / 2003 / 2008, Windows XP, Windows Vista, and Windows 7 lines of operating systems. Any differences between the different systems will be noted.
- **UNIX** is synonymous with operating systems based on AT&T and BSD origins and the Linux operating system.
- **IBM i** is synonymous with IBM i/5, IBM OS/400, and OS/400 operating systems.
- **IBM System i** is synonymous with IBM i Power Systems, IBM iSeries, IBM AS/400, and AS/400 systems.

Note: These names do not imply software support in any manner. For a detailed list of supported operating systems, see the Stonebranch Solutions 4.2.0 Installation Guide.

---

# Document Information

The document provides information organized into the following chapters:

- [Overview of Universal Connector](#) (Chapter 1)  
Overview of Universal Connector.
- [Universal Connector for z/OS](#) (Chapter 2)  
Detailed information on Universal Connector for z/OS.
- [Universal Connector for UNIX](#) (Chapter 3)  
Detailed information on Universal Connector for UNIX.
- [Universal Connector Job Definition Files](#) (Chapter 4)  
Information on Universal Connector job definition files, which contain statements that specify the attributes of jobs.
- [Universal Connector Configuration Options](#) (Chapter 5)  
Detailed information on all Universal Connector configuration options for all operating systems.
- [Customer Support](#) (Appendix A)  
Customer support contact information for Universal Connector.

---

# Overview of Universal Connector

---

## 1.1 Introduction

Universal Connector is a command line application that controls background processing within an SAP system. This allows any computer on the network to manage SAP background processing tasks via the local command line.

You indicate to Universal Connector which SAP system to connect to and what background processing tasks to perform. Universal Connector connects to the SAP system and processes your request.

On z/OS and UNIX, Universal Connector is part of Stonebranch Solutions, which provides command line interfaces to all of the major operating systems in your data center. That is, the remote operating system's command line interface is extended to the local operating system's command line interface. The remote and local systems can be running two different operating systems.

All of the Stonebranch Solutions components can interact with Universal Connector.

---

## 1.1.1 Universal Connector Functionality

---

Universal Connector provides the functionality to integrate SAP systems into both local administrative tools and enterprise system management infrastructures.

Specifically, Universal Connector allows you to:

- Define SAP jobs using a job definition file or by copying existing jobs.
- Modify SAP jobs using a job definition file.
- Start SAP jobs.
- Check the status of SAP jobs.
- Retrieve the joblog of SAP jobs.
- Retrieve the spoolists of SAP jobs.
- Delete SAP jobs and their associated output.
- Query jobs in the SAP system.
- Define SAP variants using a variant definition file.
- Modify SAP variants using a variant definition file.
- Query variants in the SAP system.
- Process/monitor Batch Input sessions.
- Retrieve the SAP syslog.
- Define SAP FS job networks to the SAP system using a definition file.
- Start SAP FS job networks.
- Check the status of SAP FS job networks.
- Delete SAP FS job networks from the SAP system.
- Interface with the MHP Communication Management product.

---

## 1.1.2 Universal Connector Communications

---

Universal Connector communicates with an SAP system using an SAP RFC connection. Through this RFC connection, Universal Connector utilizes SAP's external interfaces to perform background-processing tasks.

## 1.2 Supported SAP Versions

Universal Connector supports SAP 3.1G and above.

The following commands are not available when running USAP against SAP 3.1 and 4.0 systems:

- Purge.
- Display select.
- Target Server parameter for START and RUN commands.

### 1.2.1 XBP 2.0 Support

---

Universal Connector supports the SAP XBP 2.0 interface. The XBP 2.0 interface introduces important new feature sets and many enhancements to basic functionality.

The following features are the most notable additions to the XBP 2.0 interface:

#### Parent / Child Functionality

This feature allows Universal Connector to identify the parent/child relationship between jobs and work with them accordingly. For example, monitoring a submitted job can now take into account the activity of all child jobs.

#### Job Intercept Functionality

This feature allows Universal Connector to define and modify criteria used by the SAP system to intercept jobs (prevent jobs from starting).

#### Raise Events Externally

This feature allows Universal Connector to trigger SAP events.

**IMPORTANT:** Some features of the XBP 2.0 interface (parent/child and interception) may not be used by all SAP customers. Therefore, to prevent unnecessary use of resources, SAP provides a means to globally turn on and off these features. ABAP program `INITXBP2` performs this function.

Parent/child functionality and job interception functionality are turned off by default. The SAP ABAP program `INITXBP2` must be run before Universal Connector can use this functionality.

---

## 1.2.2 XBP 3.0 Support

---

USAP supports the SAP XBP 3.0 interface. All functionality will go through the XBP 3.0 interface if it is available.

Currently, Universal Connector supports only the following new feature set of XBP 3.0:

### *Application Information*

This feature set includes the ability to retrieve application logs and application return codes for jobs on the SAP system.

**Note:** Not all jobs will create this information. The availability is dependent upon the functionality of the programs that are executed within the job on the SAP system.

## 1.3 SAP User Authorization Requirements

USAP requires a user ID defined in the SAP system for RFC logon/user authentication. The user ID used with USAP requires certain SAP authorizations to perform tasks within the SAP system.

If the instance profile parameter `auth/rfc_authority_check` is set to 1, the system checks authorization for the function group of the RFC function module against the authorization object `S_RFC`. In this case, the following authorizations are required:

### SAP 3.1 - 4.0

User IDs that will run USAP should be assigned an authorization for the authorization object `S_RFC` with the following fields:

- Type of RFC object to be protected (RFC\_TYPE)=FUGR.
- Name of the RFC object (RFC\_NAME)=SXMI, SXJI, SQUE, STUS.
- Activity (RFC\_ACTVT)=16 (execute).

### SAP 4.5 (and Higher)

User IDs that will run USAP should be assigned an authorization for the authorization object `S_RFC` with the following fields:

- Type of RFC object to be protected (RFC\_TYPE)=FUGR.
- Name of the RFC object (RFC\_NAME)=SXMI, SXBP, SQUE, STUS.
- Activity (RFC\_ACTVT)=16 (execute).

# Universal Connector for z/OS

---

## 2.1 Overview

This chapter documents Universal Connector (USAP) at a detailed level, specific to the z/OS operating system.

It provides sections of the following information:

- [Usage](#)
- [Commands](#)
- [Configuration Options](#)
- [Exit Codes](#)



## 2.2 Usage

Universal Connector for z/OS executes as a batch job.

Each batch job contains:

1. JCL interface to the command line.
2. Configuration options associated with the specified command.
3. Configuration options (required and optional) not associated with any specific command.

Universal Connector performs an operation specified by the command. The configuration options describe the actions to take for that operation.

This section describes the JCL and command line syntax of Universal Connector for z/OS.

### 2.2.1 JCL Procedure

Figure 2.1, below, illustrates the Universal Connector for z/OS JCL procedure (**USPPRC**, located in the **SUSPSAMP** library) that is provided to simplify the execution JCL and future maintenance.

```
//USPPRC  PROC UPARM=,           -- USAP options
//                SAPRFC=USPRFC00,   -- SAP RFC member
//                USAPPRE=#SHLQ.UNV,
//                USAPPRD=#PHLQ.UNV
//*
//PS1     EXEC PGM=USAP, PARM='ENVAR(TZ=EST5EDT)/&UPARM'
//STEPLIB DD  DISP=SHR,DSN=&USAPPRE..SUNVLOAD
//*
//UNVNLS  DD  DISP=SHR,DSN=&USAPPRE..SUNVNLS
//UNVRFC  DD  DISP=SHR,DSN=&USAPPRD..UNVCONF(&SAPRFC)
//UNVTRACE DD  SYSOUT=*
//*
//SYSPRINT DD  SYSOUT=*
//SYSOUT  DD  SYSOUT=*
//CEEDUMP DD  SYSOUT=*
```

Figure 2.1 Universal Connector for z/OS – JCL Procedure

The parameter **UPARM** specifies EXEC PARM keyword values. The parameter **CONFIG** specifies the configuration member. The parameter **SAPRFC** specifies the SAP RFC configuration member. The parameter **USAPPRE** specifies the data set name prefix of USAP installation data sets.

## 2.2.2 DD Statements used in JCL Procedure

**Table 2.1**, below, describes the DD statements used in the Universal Connector for z/OS JCL illustrated in [Figure 2.1](#).

ddname	DCB Attributes *	Mode	Description
STEPLIB	DSORG=PO, RECFM=U	input	Load library containing the program being executed.
UNVNLS	DSORG=PO, RECFM=(F, FB, V, VB)	input	USAP national language support library. Contains message catalogs.
UNVRFC	DSORG=PS, RECFM=(F, FB, V, VB)	input	SAP Remote Function Call (RFC) configuration member.
UNVTRACE	DSORG=PS, RECFM=(F, FB, V, VB)	Output	USAP trace output.
SYSPRINT	DSORG=PS, RECFM=(F, FB, V, VB)	output	Standard output file for the USAP program.
SYSOUT	DSORG=PS, RECFM=(F, FB, V, VB)	output	Standard error file for the USAP program.

\* The C runtime library determines the default DCB attributes. Refer to the IBM manual *OS/390 C/C++ Programming Guide* for details on default DCB attributes for stream I/O

Table 2.1 Universal Connector for z/OS – DD Statements in JCL Procedure

## 2.2.3 JCL

**Figure 2.2**, below, illustrates the Universal Connector for z/OS JCL using the **USPPRC** procedure illustrated in [Figure 2.1](#).

```
//jobname JOB CLASS=A,MSGCLASS=X
//STEP1 EXEC USPPRC
//SYSIN DD *
  -dest BIN_45 -client 850 -userid user -pwd password
  -run
  -jobname SAMPLE1
  -jobid 13203001
  . . .
/*
```

Figure 2.2 Universal Connector for z/OS – JCL

Job step STEP1 executes the procedure **USAPPRC**.

The command options are specified on the SYSIN DD.

## 2.2.4 Command Line Syntax

Figure 2.3, below, illustrates the command line syntax of Universal Connector for z/OS.

```
usap {RUN | SUBMIT | MODIFY | START | WAIT | ABORT | DISPLAY | GENERATE |  
PURGE | SYNTAX | RAISE EVENT} HOST USER [CFT] [EVENT] [INFORMATIONAL]  
[LOCAL] [MESSAGE] [RFC] [COMMAND FILE]
```

Figure 2.3 Universal Connector for z/OS - Command Line Syntax

Names enclosed in {BRACES} identify command groups. For each execution, a single command is specified from one of these groups. One or more configuration options associated with each command also can be used to specify additional information / actions for the execution.

See Section [2.3 Commands](#) for detailed information on the commands, and their associated configuration options, in each command group.

Names not enclosed in {BRACES} or [BRACKETS] identify categories of configuration options that are not associated with specific commands but from which one or more options are required.

Names encoded in [BRACKETS] identify categories of configuration options that are not associated with specific commands and from which options are not required.

See Section [2.4 Configuration Options](#) for detailed information on configuration options not associated with one or more commands.

### Example

The following is an example of a command line syntax executing Universal Connector:

```
usap -sub file.usp -immediate -client 987 -dest -userid 123 -pwd ABC  
-lang english -level info
```

## 2.3 Commands

This section identifies all of the Universal Connector for z/OS commands.

Each command has configuration options associated with it that can be used to specify additional information / actions for an execution of that command.

(For detailed information on configuration options not associated with one or more specific commands, see Section [2.4 Configuration Options](#).)

### 2.3.1 Command Groups

Universal Connector groups commands into areas of common functionality, as shown in [Table 2.2](#), below. Each row identifies a command group, the commands in that group, and the type of operation performed by those commands.

The name of each command is a link to the following information in this section:

- **Command description** Description of the operation(s) performed by the command.
- **Command line syntax** Syntax of the command and its options on the command line.
- **Command argument** Command line expression (short and/or long form) and description of the command argument.
- **Command options** Description of the configuration options associated with the option and a link to detailed information about those options.

Command Groups	Description
RUN <ul style="list-style-type: none"> <li>• <a href="#">RUN JOB Command</a></li> <li>• <a href="#">RUN FS JOB NETWORK Command</a></li> </ul>	Performs the following actions: <ol style="list-style-type: none"> <li>1. Defines an SAP job.</li> <li>2. Starts the job.</li> <li>3. Waits for the job to complete.</li> <li>4. Writes the joblog and spoolists of the job.</li> <li>5. Purges the job from the SAP system.</li> </ol>
SUBMIT <ul style="list-style-type: none"> <li>• <a href="#">SUBMIT FS JOBNET Command</a></li> <li>• <a href="#">SUBMIT JOB Command</a></li> <li>• <a href="#">SUBMIT INTERCEPT CRITERIA TABLE Command</a></li> <li>• <a href="#">SUBMIT VARIANT Command</a></li> </ul>	Defines a job to the SAP system.
MODIFY <ul style="list-style-type: none"> <li>• <a href="#">MODIFY JOB Command</a></li> <li>• <a href="#">MODIFY VARIANT Command</a></li> </ul>	Modifies a job in an SAP job.
START <ul style="list-style-type: none"> <li>• <a href="#">START FS JOBNET Command</a></li> <li>• <a href="#">START JOB Command</a></li> </ul>	Starts a defined SAP job.

Command Groups	Description
WAIT <ul style="list-style-type: none"> <li>• <a href="#">WAIT for JOB Command</a></li> <li>• <a href="#">MASS ACTIVITY WAIT Command</a></li> <li>• <a href="#">WAIT for FS JOB NETWORK Command</a></li> <li>• <a href="#">BDCWAIT Command</a></li> </ul>	Allows USAP to reconnect to a started job and monitor it through completion.
ABORT <ul style="list-style-type: none"> <li>• <a href="#">ABORT Command</a></li> </ul>	Cancels a running SAP job.
DISPLAY <ul style="list-style-type: none"> <li>• <a href="#">DISPLAY COMMANDS Command</a></li> <li>• <a href="#">DISPLAY INTERCEPTED_JOBS Command</a></li> <li>• <a href="#">DISPLAY INTERCEPT_TABLE Command</a></li> <li>• <a href="#">DISPLAY JOBDEF Command</a></li> <li>• <a href="#">DISPLAY JOBLOG Command</a></li> <li>• <a href="#">DISPLAY OUTPUT_DEVICES Command</a></li> <li>• <a href="#">DISPLAY PRINT_FORMATS Command</a></li> <li>• <a href="#">DISPLAY QSTATE Command</a></li> <li>• <a href="#">DISPLAY REPORTS Command</a></li> <li>• <a href="#">DISPLAY SPOOLLIST Command</a></li> <li>• <a href="#">DISPLAY STATUS Command</a></li> <li>• <a href="#">DISPLAY VARIANT Command</a></li> <li>• <a href="#">DISPLAY VARIANTS Command</a></li> <li>• <a href="#">DISPLAY SELECT Command</a></li> <li>• <a href="#">DISPLAY SYSLOG Command</a></li> </ul>	Displays various SAP job data.
GENERATE <ul style="list-style-type: none"> <li>• <a href="#">GENERATE JOB DEFINITION FILE Command</a></li> <li>• <a href="#">GENERATE VARIANT DEFINITION FILE Command</a></li> </ul>	Generates USAP job or variant definitions based on model SAP jobs or variants.
PURGE <ul style="list-style-type: none"> <li>• <a href="#">PURGE JOB Command</a></li> <li>• <a href="#">PURGE FS JOB NETWORK Command</a></li> </ul>	Deletes SAP jobs.
<a href="#">RAISE EVENT Command</a>	Raises the specified SAP background processing event.
<a href="#">SYNTAX Command</a>	Checks the syntax of a job definition file.

Table 2.2 USAP for z/OS - Command Groups

---

## 2.3.2 RUN JOB Command

---

The RUN JOB command performs the following actions:

1. Defines a new SAP, job based on either a job definition specification or an existing SAP job definition.
2. Starts the defined job.
3. Waits for the job to complete.
4. Prints the job's joblog to standard error and the spoolists to standard output.
5. Purges the job from the SAP system.

The exit code of USAP will indicate the completion status of the SAP job.

See Section [2.5.1 WAIT for JOB Exit Codes](#) for a complete list of job status exit codes.

## RUN JOB Command Line Syntax

Figure 2.4, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RUN JOB command.

```
-run {ddname | -jobname jobname -jobid jobid}
    [-target_jobname jobname]
    [-poll seconds]
    [-job_stat_check_interval seconds]
    [-targetserver server]
    [-target_variant job step, variant name; job step, variant name; ...]
    [-immediate]
    [-activeec exitcode]
    [-readyec exitcode]
    [-scheduledec exitcode]
    [-releasedec exitcode]
    [-terminatedec exitcode]
    [-finishedec exitcode]
    [-max_log_size size]
    [-max_spool_size size]
    [-server_stop_conditions codes]
    [-spool_codepage codepage]
    [-bdcwait
        [-bdcjobnameptrn pattern]
        [-bdcjobidptrn pattern]
        [-bdcqidptrn pattern]
        [-qtobecreatedec exitcode]
        [-qunprocessedec exitcode]
        [-qinbackgroundec exitcode]
        [-qfinishedec exitcode]
        [-qerrorec exitcode]
    ]
```

Figure 2.4 RUN JOB Command Line Syntax

## RUN JOB Command Argument

The RUN JOB command can be expressed as either:

- -R           Short form
- -run         Long form

The RUN JOB command argument, *ddname*, specifies the name of the file that contains the job definition.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the job definition file.

## RUN JOB Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the started job.
EXIT_JOB_ACTIVE	USAP exit code for the SAP job active status.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_READY	USAP exit code for the SAP job ready status.
EXIT_JOB_RELEASED	USAP exit code for the SAP job released status.
EXIT_JOB_SCHEDULED	USAP exit code for the SAP job scheduled status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state <b>S</b> (in background).
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state <b>C</b> (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state <b>E</b> (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state <b>F</b> (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state [ ] (unprocessed).
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
JOB_NAME	Existing SAP job name to use as a model for the new job definition.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.
SERVER_STOP_CONDITIONS	Exit code(s) of the executing Universal Connector process that should trigger the locally running Universal Broker to cancel the corresponding SAP job.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
TARGET_JOB_NAME	Name to give the newly created job.
TARGET_SERVER	Server on which the job will run.
TARGET_VARIANT	One or more replacement variants for ABAP program job steps in an SAP job.
USAP_POLL	Length of time to wait between job status calls to the SAP system.

Table 2.3 RUN JOB Command Options



## 2.3.3 RUN FS JOB NETWORK Command

The RUN FS JOB NETWORK command performs the following actions:

1. Defines a new SAP FS job network based on a USAP FS Job Network definition file.
2. Starts the defined FS job network.
3. Waits for the started FS job network to complete.
4. Purges the FS job network from the SAP system.

The exit code of **usap** will indicate the completion status of the FS job network.

See Section [2.5.2 WAIT for FS JOB NETWORK Exit Codes](#) for a complete list of job status exit codes.

### RUN FS JOB NETWORK Command Line Syntax

[Figure 2.5](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RUN FS JOB NETWORK command.

```
-run {ddname | -jnetid jobnetid -jnetprcid processid}
```

Figure 2.5 RUN FS JOB NETWORK Command Line Syntax

### RUN FS JOB Command Argument

The RUN FS JOB command can be expressed as either:

- -R            Short form
- -run        Long form

The RUN FS JOB command argument, *ddname*, specifies the name of the file that contains the FS job network definition.

See Section [4.10 FS Job Network Definition File](#) for additional information on the FS job network definition file.

### RUN FS JOB NETWORK Command Options

Option Name	Description
<a href="#">JOB_NETWORK_ID</a>	Network identifier for the pre-existing SAP FS job network being started.
<a href="#">JOB_PROCESS_ID</a>	Process ID of an existing SAP FS job network process to start.

Table 2.4 RUN FS JOB NETWORK Command Options

## 2.3.4 SUBMIT JOB Command

The SUBMIT JOB command defines a new SAP job.

### SUBMIT JOB Command Line Syntax

Figure 2.6, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT JOB command.

```

-sub {ddname | -jobname jobname -jobid jobid}
  [-target_jobname jobname]
  [-start
    [-immediate]
    [-targetserver server]
    [-target_variant job step,variant name;job step,variant name;...]
    [-wait
      [-poll seconds]
      [-joblog {yes|no}]
      [-spoolist {yes|no}]
      [-purge]
      [-waitchild {yes|no}]
      [-max_child_depth depth]
      [-joblogchild {yes|no|error}]
      [-spoolistchild {yes|no}]
      [-purgechild {yes|no}]
    ]
  ]

```

Figure 2.6 SUBMIT JOB Command Line Syntax

### SUBMIT JOB Command Argument

The SUBMIT JOB command can be expressed as either:

- -U           Short form
- -sub         Long form

The SUBMIT JOB command argument, *ddname*, specifies the name of the file that contains the job definition.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the job definition file.

## SUBMIT JOB Command Options

Option Name	Description
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_CHILD_DEPTH	Controls the maximum relationship depth that will be monitored by USAP.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoollists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoollists for child jobs.
START_JOB	Starts the newly defined job.
TARGET_JOB_NAME	Name to give the newly created job.
TARGET_VARIANT	One or more replacement variants for ABAP program job steps in an SAP job.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 2.5 SUBMIT JOB Command Options

## 2.3.5 SUBMIT VARIANT Command


The SUBMIT VARIANT command defines a new variant to an SAP system for a specified ABAP report.

Note: SUBMIT VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

### SUBMIT VARIANT Command Line Syntax

[Figure 2.7](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT VARIANT command.



```
-sub ddname
```

Figure 2.7 SUBMIT VARIANT Command Line Syntax

### SUBMIT VARIANT Command Argument

The SUBMIT VARIANT command can be expressed as either:

- -U           Short form
- -sub        Long form

The SUBMIT VARIANT command argument, *ddname*, specifies the name of the file that contains the variant definition.

See Section [4.8 Variant Definition File](#) for additional information on the variant definition file.

## 2.3.6 SUBMIT INTERCEPT CRITERIA TABLE Command

The SUBMIT INTERCEPT CRITERIA TABLE command appends or replaces the SAP intercept criteria table.

### SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax

[Figure 2.8](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT INTERCEPT CRITERIA TABLE command.

```
-sub ddname
```

Figure 2.8 SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax

### SUBMIT INTERCEPT CRITERIA TABLE Command Argument

The SUBMIT INTERCEPT CRITERIA TABLE command can be expressed as either:

- -U           Short form
- -sub         Long form

The SUBMIT INTERCEPT CRITERIA TABLE command argument, *ddname*, specifies the name of the file that contains the intercept criteria table definition.

See [Section 4.9 Job Intercept Table Definition File](#) for additional information on the variant definition file.

## 2.3.7 SUBMIT FS JOBNET Command

The SUBMIT FS JOBNET command defines a new FS jobnet to an SAP system.

### SUBMIT FS JOBNET Command Line Syntax

Figure 2.9, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT FS JOBNET command.

```
-sub {ddname | -jobname jobname -jobid jobid}
  [-start
    [-wait
      [-poll seconds]
      [-purge]
    ]
  ]
```

Figure 2.9 SUBMIT FS JOBNET Command Line Syntax

### SUBMIT FS JOBNET Command Argument

The SUBMIT FS JOBNET command can be expressed as either:

- -U           Short form
- -sub         Long form

The SUBMIT FS JOBNET command argument, *ddname*, specifies the name of the file that contains the FS jobnet definition.

See Section [4.10 FS Job Network Definition File](#) for additional information on the variant definition file.

### SUBMIT FS JOBNET Command Options

Option Name	Description
PURGE_JOB	Purge job that has completed processing from SAP system.
START_JOB	Starts the newly defined job.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.

Table 2.6 SUBMIT FS JOBNET Command Options

## 2.3.8 MODIFY JOB Command

The MODIFY JOB command is used to modify an SAP job that already exists in an SAP system. A USAP job definition file is used to specify the modifications.

Job definition files are used to define new SAP jobs and to modify existing SAP jobs. The same syntactical rules apply to the job definition file in both cases with the following exceptions when modifying jobs:

1. SAP job identifier must be specified in order to identify the existing job to modify. The job identifier is specified in the job definition file using the JOBCOUNT keyword of the Job Header statement or the `-jobid` option of the MODIFY command. If both are used, the `-jobid` option overrides the JOBCOUNT value.
2. ABAP Step and External Step job definition statements must specify the step number of the existing job step to modify. The step number is specified using the STEP\_NUMBER keyword of the ABAP Step and External Step job definition statements.

The parameter values specified in job definition file replace existing values in the SAP job definition. If a parameter is not specified in the job definition file, no change is made to the corresponding value in the existing SAP job definition.

See [Chapter 4 Universal Connector Job Definition Files](#) for additional information on the job definition file.

### MODIFY JOB Command Line Syntax

[Figure 2.10](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MODIFY JOB command.

```
-modify ddname
  [-jobid jobid]
  [-start
    [-immediate]
    [-targetserver server]
    [-wait
      [-poll seconds]
      [-joblog {yes|no}]
      [-spoollist {yes|no}]
      [-purge]
      [-waitchild {yes|no}]
      [-joblogchild {yes|no|error}]
      [-spoollistchild {yes|no}]
      [-purgechild {yes|no}]
    ]
  ]
```

Figure 2.10 MODIFY JOB Command Line Syntax

## MODIFY JOB Command Argument

The MODIFY JOB command can be expressed as either:

- -M            Short form
- -modify     Long form

The MODIFY JOB command argument, *ddname*, specifies the name of the job definition file that contains the modification information.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the variant definition file.

## MODIFY JOB Command Options

Option Name	Description
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to be modified.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.
START_JOB	Starts the newly defined job.
TARGET_SERVER	Server on which the job will run.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 2.7 MODIFY JOB Command Options



## 2.3.9 MODIFY VARIANT Command

The MODIFY VARIANT command is used to modify an SAP variant that already exists in an SAP system. A USAP variant definition file is used to specify the modifications.

Note: MODIFY VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

Variant definition files are used to define new SAP variants and to modify existing SAP variants. The same syntactical rules apply to the variant definition file in both cases.

The parameter values specified in a variant definition file replace existing values in the SAP variant definition. If a parameter is not specified in the variant definition file, no change is made to the corresponding value in the existing SAP variant definition.

See Section [4.8 Variant Definition File](#) for additional information on the variant definition file.

### MODIFY VARIANT Command Line Syntax

[Figure 2.11](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MODIFY VARIANT command.

```
-modify ddname
```

Figure 2.11 MODIFY VARIANT Command Line Syntax

### MODIFY VARIANT Command Argument

The MODIFY VARIANT command can be expressed as either:

- -M Short form
- -modify Long form

The MODIFY VARIANT command argument, *ddname*, specifies the name of the variant definition file that contains the modification information.

See Section [4.8 Variant Definition File](#) for additional information on the variant definition file.

## 2.3.10 START JOB Command

The START JOB command starts a currently defined SAP job.

### START JOB Command Line Syntax

Figure 2.12, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the START JOB command.

```
-start -jobname jobname -jobid jobid
  [-immediate]
  [-targetserver server]
  [-wait
    [-poll seconds]
    [-joblog {yes|no}]
    [-spoollist {yes|no}]
    [-purge]
    [-terminatedec exitcode]
    [-finishedec exitcode]
  ]
  [-bdcwait
    [-bdcjobnameptrn pattern]
    [-bdcjobidptrn pattern]
    [-bdcqidptrn pattern]
    [-qtobecreatedec exitcode]
    [-qunprocessedec exitcode]
    [-qinbackgroundec exitcode]
    [-qfinishedec exitcode]
    [-qerrorec exitcode]
  ]
]
```

Figure 2.12 START JOB Command Line Syntax

## START JOB Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state 'S' (in background).
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state 'C' (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state 'E' (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state 'F' (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state ' ' (unprocessed).
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.
TARGET_SERVER	Server on which the job will run.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 2.8 START JOB Command Options

## 2.3.11 START FS JOBNET Command

The START FS JOBNET command starts a specified FS job network on an SAP system.

### START FS JOBNET Command Line Syntax

Figure 2.13, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the START FS JOBNET command.

```
-start -jnetid jobnet_id -jnetprcid jobnet_process_id
      [-wait
        [-poll seconds]
        [-purge]
      ]
```

Figure 2.13 START FS JOBNET Command Line Syntax

### START FS JOBNET Command Options

Option Name	Description
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.
PURGE_JOB	Purge job that has completed processing from SAP system.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.

Table 2.9 START FS JOBNET Command Options

## 2.3.12 WAIT for JOB Command

The WAIT for JOB command allows USAP to reconnect to a started job and monitor it through completion.

### WAIT for JOB Command Line Syntax

Figure 2.14, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the WAIT for JOB command.

```
-wait -jobname jobname -jobid jobid
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-joblog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-server_stop_conditions codes]
  [-spoollist {yes|no}]
  [-spool_codepage codepage]
  [-transtab translation_table]
  [-terminatedec exitcode]
  [-finishedec exitcode]
  [-poll seconds]
  [-purge]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-waitchild {yes|no}]
  [-max_child_depth depth]
  [-joblogchild {yes|no|error}]
  [-spoollistchild {yes|no}]
  [-purgechild {yes|no}]
  [-max_log_size size]
  [-max_spool_size size]
```

Figure 2.14 WAIT for JOB Command Line Syntax

## WAIT for JOB Command Options

Option Name	Description
WAIT	Causes USAP to wait for the SAP job to complete processing
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_CHILD_DEPTH	Controls the maximum relationship depth that will be monitored by USAP.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.
SERVER_STOP_CONDITIONS	Exit code(s) of the executing Universal Connector process that should trigger the locally running Universal Broker to cancel the corresponding SAP job.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job <b>end</b> time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
TRANSLATION_TABLE	Spoolist translation table file to use for formatting returned spoolists.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 2.10 WAIT for JOB Command Options

## 2.3.13 MASS ACTIVITY WAIT Command

The MASS ACTIVITY WAIT command allows USAP to wait for (or reconnect and wait for) a started mass activity job and monitor it, and all its interval jobs, through completion.

### MASS ACTIVITY WAIT Command Line Syntax

Figure 2.15, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MASS ACTIVITY WAIT command.

```
-mawait -jobname jobname -jobid jobid
  [-poll seconds]
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-applog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-transtab translation_table]
  [-purge]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-terminatedec exitcode]
  [-finishedec exitcode]
```

Figure 2.15 MASS ACTIVITY WAIT Command Line Syntax

## MASS ACTIVITY WAIT Command Options

Option Name	Description
MASS_ACTIVITY_WAIT	Causes USAP to wait for the SAP mass activity jobs to complete processing.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job <b>end</b> time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
TRANSLATION_TABLE	Spoolist translation table file to use for formatting returned spoolists.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.

Table 2.11 MASS ACTIVITY WAIT Command Options



## 2.3.14 WAIT for FS JOB NETWORK Command

The WAIT for FS JOB NETWORK command allows USAP to reconnect to a started FS job network and monitor it through completion.

### WAIT for FS JOB NETWORK Command Line Syntax

Figure 2.16, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the WAIT for FS JOB NETWORK command.

```

-wait -jnetid jobnetid -jnetprcid processid
      [-poll seconds]
      [-purge]
      [-syslog {yes|no}
        [-syslogpre seconds]
        [-syslogpost seconds]
      ]
      [-max_log_size size]
      [-max_spool_size size

```

Figure 2.16 WAIT for FS JOB NETWORK Command Line Syntax

### WAIT for FS JOB NETWORK Command Options

Option Name	Description
WAIT	Causes USAP to wait for the SAP job network to complete processing.
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
PURGE_JOB	Purge job that has completed processing from SAP system.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job end time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
USAP_POLL	Length of time to wait between job status calls to the SAP system.

Table 2.12 WAIT for FS JOB NETWORK Command Options

## 2.3.15 BDCWAIT Command

The BDCWAIT command allows USAP to reconnect to a started batch input processing job and monitor it, and all its generated session processing jobs, through completion.

### BDCWAIT Command Line Syntax

Figure 2.17, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the BDCWAIT command.

```
-bdcwait -jobname jobname -jobid jobid
  [-poll seconds]
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-applog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-transtab translation_table]
  [-purge]
  [-purge_bdc_map {yes|no}]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-terminatedec exitcode]
  [-finishedec exitcode]
  [-qtobecreatedec exitcode]
  [-qunprocessedec exitcode]
  [-qinbackgroundec exitcode]
  [-qfinishedec exitcode]
  [-qerrorec exitcode]
  [-bdcjobnameptrn pattern]
  [-bdcjobidptrn pattern]
  [-bdcqidptrn pattern]
```

Figure 2.17 BDCWAIT Command Line Syntax

## BDCWAIT Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state 'S' (in background).
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state 'C' (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state 'E' (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state 'F' (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state ' ' (unprocessed).
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.
PURGE_BDC_MAP	Specification for whether or not to delete BDC Batch input session queues that have been processed successfully.
PURGE_JOB	Purge job that has completed processing from SAP system.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the <b>RSBDCSUB</b> batch input processing report.
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job end time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
TRANSLATION_TABLE	Spoolist translation table file to use for formatting returned spoolists.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.

Table 2.13 BDCWAIT Command Options

## 2.3.16 ABORT Command

The ABORT command cancels a running SAP job.

### ABORT Command Line Syntax

Figure 2.18, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the ABORT command.

```
-abort -jobname jobname -jobid jobid
```

Figure 2.18 ABORT Command Line Syntax

### ABORT Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 2.14 ABORT Command Options

## 2.3.17 PURGE JOB Command

The PURGE JOB command deletes a defined SAP job, its joblog, and all of its spoolists. This command is not available on SAP 3.1 and SAP 4.0 systems.

### PURGE JOB Command Line Syntax

Figure 2.19, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the PURGE JOB command.

```
-purge -jobname jobname -jobid jobid
```

Figure 2.19 PURGE JOB Command Line Syntax

### PURGE JOB Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 2.15 PURGE JOB Command Options

## 2.3.18 PURGE FS JOB NETWORK Command

The PURGE FS JOB NETWORK command deletes a defined SAP FS job network.

### PURGE FS JOB NETWORK Command Line Syntax

Figure 2.20, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the PURGE FS JOB NETWORK command.

```
-purge -jnetid jobnetid -jnetpcid processid
```

Figure 2.20 PURGE FS JOB NETWORK Command Line Syntax

### PURGE FS JOB NETWORK Command Options

Option Name	Description
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.

Table 2.16 PURGE FS JOB NETWORK Command Options

## 2.3.19 RAISE EVENT Command

The RAISE EVENT command raises the specified SAP background processing event.

### RAISE EVENT Command Line Syntax

Figure 2.21, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RAISE EVENT command.

```
-raise_bp_event -event_id id -event_parm parm
```

Figure 2.21 RAISE EVENT Command Line Syntax

### RAISE EVENT Command Options

Option Name	Description
EVENT_ID	Name of the event.
EVENT_PARAMETER	Optional parameter value for the event.

Table 2.17 RAISE EVENT Command Options

## 2.3.20 SYNTAX Command

The SYNTAX command checks the syntax of a USAP definition file.

### SYNTAX Command Line Syntax

[Figure 2.22](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SYNTAX command.

```
-syntax ddname
```

Figure 2.22 SYNTAX Command Line Syntax

### SYNTAX Command Argument

The SYNTAX command can be expressed as either:

- -X           Short form
- -syntax     Long form

The SYNTAX command argument, *ddname*, specifies the name of the definition file that contains the job, variant, or FS job network definition.

- See [Chapter 4 Universal Connector Job Definition Files](#) for additional information on the job definition file.
- See [Section 4.8 Variant Definition File](#) for additional information on the variant definition file.
- See [Section 4.10 FS Job Network Definition File](#) for additional information on the FS Job Network definition file.



## 2.3.21 DISPLAY JOBLOG Command

The DISPLAY JOBLOG command displays the job log for a specified SAP job.

### DISPLAY JOBLOG Command Line Syntax

Figure 2.23, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY JOBLOG command.

```
-display joblog -jobname jobname -jobid jobid -max_log_size size
```

Figure 2.23 DISPLAY JOBLOG Command Line Syntax

### DISPLAY JOBLOG Command Argument

The DISPLAY JOBLOG command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY JOBLOG command argument, **joblog**, requests the display of a job's joblog.

### DISPLAY JOBLOG Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_JOB_LOG_SIZE	Maximum size for job logs.

Table 2.18 DISPLAY JOBLOG Command Options

## 2.3.22 DISPLAY SPOOLLIST Command

The DISPLAY SPOOLLIST command displays the spoolist for a job step.

### DISPLAY SPOOLLIST Command Line Syntax

Figure 2.24, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SPOOLLIST command.

```

-display spoolist -jobname jobname -jobid jobid
      -stepnum stepnumber -max_spool_size size
      [-spool_codepage codepage]
      [-transtab translation_table]
```

Figure 2.24 DISPLAY SPOOLLIST Command Line Syntax

### DISPLAY SPOOLLIST Command Argument

The DISPLAY SPOOLLIST command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY SPOOLLIST command argument, **spoolist**, requests the display of a job step’s spoolist.

### DISPLAY SPOOLLIST Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
STEP_NUMBER	Step number of the SAP job step.
TRANSLATION_TABLE	spoolist translation table file to use for formatting returned spoolists.

Table 2.19 DISPLAY SPOOLLIST Command Options

## 2.3.23 DISPLAY STATUS Command

The DISPLAY STATUS command displays the current status for an SAP job. The status is printed to standard output and the exit code of **usap** indicates the status. See Section [2.5 Exit Codes](#) for a complete list of job status exit codes.

### DISPLAY STATUS Command Line Syntax

[Figure 2.25](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY STATUS command.

```
-display status -jobname jobname -jobid jobid  
    [-activeec exitcode ]  
    [-readyec exitcode ]  
    [-scheduledec exitcode ]  
    [-releasedec exitcode ]  
    [-terminatedec exitcode ]  
    [-finishedec exitcode ]
```

Figure 2.25 DISPLAY STATUS Command Line Syntax

### DISPLAY STATUS Command Argument

The DISPLAY STATUS command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY STATUS command argument, **status**, requests a job status.

The status is printed to standard output and the exit code of USAP indicates the status. See Section [2.5 Exit Codes](#) for a complete list of job status exit codes.

## DISPLAY STATUS Command Options

Option Name	Description
EXIT_JOB_ACTIVE	USAP exit code for the SAP job <b>active</b> status.
EXIT_JOB_FINISHED	USAP exit code for the SAP job <b>finished</b> status.
EXIT_JOB_READY	USAP exit code for the SAP job <b>ready</b> status.
EXIT_JOB_RELEASED	USAP exit code for the SAP job <b>released</b> status.
EXIT_JOB_SCHEDULED	USAP exit code for the SAP job <b>scheduled</b> status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job <b>terminated</b> status.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 2.20 DISPLAY STATUS Command Options

## 2.3.24 DISPLAY VARIANTS Command

The DISPLAY VARIANTS command displays the variants available for the specified ABAP program.

### DISPLAY VARIANTS Command Line Syntax

Figure 2.26, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY VARIANTS command.

```
-display variants -abapname abapname -varselopt {A|B}
```

Figure 2.26 DISPLAY VARIANTS Command Line Syntax

### DISPLAY VARIANTS Command Argument

The DISPLAY VARIANTS command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY VARIANTS command argument, **variants**, displays the variants defined for ABAP program **abapname**.

- Using **-varselopt A** will display the variants that are available for batch and dialog mode.
- Using **-varselopt B** will display the variants that are available for batch mode only.

### DISPLAY VARIANTS Command Options

Option Name	Description
ABAP_NAME	Name of an ABAP program in an SAP system.
VARIANT_SELECTION	Specification to display either variants available for batch and dialog mode or variants available only for batch mode.

Table 2.21 DISPLAY VARIANTS Command Options

## 2.3.25 DISPLAY VARIANT Command

The DISPLAY VARIANT command displays the contents of a specified variant.

Note: DISPLAY VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

### DISPLAY VARIANT Command Line Syntax

Figure 2.27, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY VARIANT command.

```
-display variant -variant variantname -varlang language
-abapname abapname
```

Figure 2.27 DISPLAY VARIANT Command Line Syntax

### DISPLAY VARIANT Command Argument

The DISPLAY VARIANT command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY VARIANT command argument, **variant**, displays the specified SAP variant.

### DISPLAY VARIANT Command Options

Option Name	Description
<a href="#">ABAP_NAME</a>	Name of an ABAP program in an SAP system.
<a href="#">VARIANT</a>	Pre-existing SAP variant whose contents will be displayed.
<a href="#">VARIANT_LANGUAGE</a>	Preferred language in which to return the variant description.

Table 2.22 DISPLAY VARIANT Command Options

## 2.3.26 DISPLAY JOBDEF Command

The DISPLAY JOBDEF command displays the definition of the specified SAP job.

### DISPLAY JOBDEF Command Line Syntax

Figure 2.28, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY JOBDEF command.

```
-display jobdef -jobname jobname -jobid jobid
```

Figure 2.28 DISPLAY JOBDEF Command Line Syntax

### DISPLAY JOBDEF Command Argument

The DISPLAY JOBDEF command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY JOBDEF command argument, **jobdef**, requests the display of a job's definition.

### DISPLAY JOBDEF Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 2.23 DISPLAY JOBDEF Command Options

## 2.3.27 DISPLAY SELECT Command

The DISPLAY SELECT command displays a variety of attributes for a list of SAP jobs that match the specified criteria.

### DISPLAY SELECT Command Line Syntax

Figure 2.29, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SELECT command.

```
-display select -jobname jobmask
  [-jobid idmask ]
  [-selusername userid ]
  [-fromdate date ]
  [-todate date ]
  [-fromtime time ]
  [-totime time ]
  [-nodate {yes|no} ]
  [-withpred {yes|no} ]
  [-released {yes|no} ]
  [-scheduled {yes|no} ]
  [-ready {yes|no} ]
  [-running {yes|no} ]
  [-finished {yes|no} ]
  [-aborted {yes|no} ]
  [-output output-field-list]
```

Figure 2.29 DISPLAY SELECT Command Line Syntax

### DISPLAY SELECT Command Argument

The DISPLAY SELECT command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY SELECT command argument, **select**, requests the display of all jobs matching the **jobmask** and any additional selection criteria specified. The default output for this command is the job name and job ID for each job found. However, additional fields can be printed using the **-output** option.

Note: This command is not available on SAP 3.1 and SAP 4.0 systems.



## DISPLAY SELECT Command Options

Option Name	Description
FROM_DATE	Earliest date to use for job selection or syslog request.
FROM_TIME	Earliest time to use for job selection or syslog request.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
NO_START_DATE	Specification for whether or not to include jobs with no start date in selection criteria.
OUTPUT_FIELD_LIST	Additional fields to write for the <b>select</b> command.
STATUS_ABORTED	Specification for whether or not to include jobs with status aborted in selection criteria.
STATUS_FINISHED	Specification for whether or not to include jobs with status finished in selection criteria.
STATUS_READY	Specification for whether or not to include jobs with status ready in selection criteria.
STATUS_RELEASED	Specification for whether or not to include jobs with status released in selection criteria.
STATUS_RUNNING	Specification for whether or not to include jobs with status running in selection criteria.
STATUS_SCHEDULED	Specification for whether or not to include jobs with status scheduled in selection criteria.
TO_DATE	Latest date to use for job selection or syslog request.
TO_TIME	Latest time to use for job selection or syslog request.
USER_NAME	User ID associated with a job.
WITH_PREDECESSOR	Specification for whether or not to include jobs with start after predecessor in selection criteria.

Table 2.24 DISPLAY SELECT Command Options

## 2.3.28 DISPLAY SYSLOG Command

The DISPLAY SYSLOG command displays a portion of an SAP syslog that meets the specified date/time constraints.

### DISPLAY SYSLOG Command Line Syntax

Figure 2.30, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SYSLOG command.

```

-display syslog -fromdate date -todate date
    [-fromtime time      ]
    [-totime time       ]
    [-pagelimit limit   ]
    [-targetserver server]
```

Figure 2.30 DISPLAY SYSLOG Command Line Syntax

### DISPLAY SYSLOG Command Argument

The DISPLAY SYSLOG command can be expressed as either:

- -D            Short form
- -display    Long form

The DISPLAY SYSLOG command argument, **syslog**, requests entries from an SAP System syslog for a specified date and time range.

### DISPLAY SYSLOG Command Options

Option Name	Description
FROM_DATE	Earliest date to use for job selection or syslog request.
FROM_TIME	Earliest time to use for job selection or syslog request.
PAGE_LIMIT	Maximum number of pages that can be returned in the syslog report.
TARGET_SERVER	Name of the server whose syslog will be read.
TO_DATE	Latest date to use for job selection or syslog request.
TO_TIME	Latest time to use for job selection or syslog request.

Table 2.25 DISPLAY SYSLOG Command Options

## 2.3.29 DISPLAY INTERCEPTED\_JOBS Command

The DISPLAY INTERCEPTED\_JOBS command displays intercepted jobs for the connected SAP system.

### DISPLAY INTERCEPTED\_JOBS Command Line Syntax

Figure 2.31, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY INTERCEPTED\_JOBS command.

```
-display intercepted_jobs -dspclient client
```

Figure 2.31 DISPLAY INTERCEPTED\_JOBS Command Line Syntax

### DISPLAY INTERCEPTED\_JOBS Command Argument

The DISPLAY INTERCEPTED\_JOBS command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY INTERCEPTED\_JOBS command argument, **intercepted\_jobs**, requests the display of an SAP system’s intercepted jobs. Unless a specific client is identified, intercepted jobs for all clients are displayed.

### DISPLAY INTERCEPTED\_JOBS Command Options

Option Name	Description
DISPLAY_CLIENT	Specific SAP client whose intercepted jobs will be reported.

Table 2.26 DISPLAY INTERCEPTED\_JOBS Command Options

## 2.3.30 DISPLAY INTERCEPT\_TABLE Command

---

The DISPLAY INTERCEPT\_TABLE command displays the contents of the job intercept criteria table for the connected SAP system.

### DISPLAY INTERCEPT\_TABLE Command Line Syntax

Figure 2.32, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY INTERCEPT\_TABLE command.

```
-display intercept_table
```

Figure 2.32 DISPLAY INTERCEPT\_TABLE Command Line Syntax

### DISPLAY INTERCEPT\_TABLE Command Argument

The DISPLAY INTERCEPT\_TABLE command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY INTERCEPT\_TABLE command argument, **intercept\_table**, requests the display of an SAP system's job intercept criteria table.

## 2.3.31 DISPLAY QSTATE Command

The DISPLAY QSTATE command displays the state of a specific Batch Input / BDC session queue in an SAP system.

### DISPLAY QSTATE Command Line Syntax

Figure 2.33, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY QSTATE command.

```
-display qstate -qid queueid
```

Figure 2.33 DISPLAY QSTATE Command Line Syntax

### DISPLAY QSTATE Command Argument

The DISPLAY QSTATE command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY QSTATE command argument, **qstate**, requests the state of a queue used to process a batch input session. See Section [2.5.4 DISPLAY QSTATE Exit Codes](#) for a complete list of queue state exit codes.

### DISPLAY QSTATE Command Options

Option Name	Description
<a href="#">QUEUE_ID</a>	Queue identifier associated with the batch input session.

Table 2.27 DISPLAY QSTATE Command Options

## 2.3.32 DISPLAY REPORTS Command

The DISPLAY REPORTS command displays a list of ABAP reports that match the specified criteria.

### DISPLAY REPORTS Command Line Syntax

Figure 2.34, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY REPORTS command.

```
-display reports -abapname abapmask -count max_hit_count
```

Figure 2.34 DISPLAY REPORTS Command Line Syntax

### DISPLAY REPORTS Command Argument

The DISPLAY REPORTS command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY REPORTS command argument, **reports**, requests the display of a list of ABAP reports that match the specified criteria.

### DISPLAY REPORTS Command Options

Option Name	Description
<code>ABAP_NAME</code>	Complete ABAP name or a mask used to select SAP ABAP reports that match the mask.
<code>MAX_HIT_COUNT</code>	Maximum number of ABAP reports to be returned.

Table 2.28 DISPLAY REPORTS Command Options

## 2.3.33 DISPLAY COMMANDS Command

The DISPLAY COMMANDS command displays a list of SAP external commands that match the specified criteria.

### DISPLAY COMMANDS Command Line Syntax

Figure 2.35, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY COMMANDS command.

```
-display commands -cmd external_command_mask -opsys operating_system
```

Figure 2.35 DISPLAY COMMANDS Command Line Syntax

### DISPLAY COMMANDS Command Argument

The DISPLAY COMMANDS command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY COMMANDS command argument, **commands**, requests the display of a list of SAP external commands that match the specified criteria.

### DISPLAY COMMANDS Command Options

Option Name	Description
EXTERNAL_COMMAND	Complete command name or a mask used to select SAP external commands that match the mask.
OPERATING_SYSTEM	Name of the operating system for which external commands are searched.

Table 2.29 DISPLAY COMMANDS Command Options

## 2.3.34 DISPLAY OUTPUT\_DEVICES Command

The DISPLAY OUTPUT\_DEVICES command displays a list of SAP output devices that match the specified criteria.

### DISPLAY OUTPUT\_DEVICES Command Line Syntax

Figure 2.36, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY OUTPUT\_DEVICES command.

```
-display output_devices -short_name technical_device_name_mask
      -long_name long_device_name_mask
```

Figure 2.36 DISPLAY OUTPUT\_DEVICES Command Line Syntax

### DISPLAY OUTPUT\_DEVICES Command Argument

The DISPLAY OUTPUT\_DEVICES command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY OUTPUT\_DEVICES command argument, **output\_devices**, requests the display of a list of SAP output devices that match the specified criteria.

### DISPLAY OUTPUT\_DEVICES Command Options

Option Name	Description
TECHNICAL_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.
LONG_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.

Table 2.30 DISPLAY OUTPUT\_DEVICES Command Options



## 2.3.35 DISPLAY PRINT\_FORMATS Command

The DISPLAY PRINT\_FORMATS command displays a list of print formats that are available for the specified printer.

### DISPLAY PRINT\_FORMATS Command Line Syntax

Figure 2.37, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY PRINT\_FORMATS command.

```
-display print_formats -printer printer_name -layout layout
```

Figure 2.37 DISPLAY PRINT\_FORMATS Command Line Syntax

### DISPLAY PRINT\_FORMAT Command Argument

The DISPLAY PRINT\_FORMAT command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY PRINT\_FORMAT command argument, **print\_formats**, requests the display of a list of print formats available for the specified printer.

### DISPLAY PRINT\_FORMATS Command Options

Option Name	Description
LAYOUT_NAME	Complete layout name or a mask used to select printer layouts that match the mask.
PRINTER_NAME	Name of a printer for which the print formats will be retrieved.

Table 2.31 DISPLAY PRINT\_FORMATS Command Options

## 2.3.36 GENERATE JOB DEFINITION FILE Command

The GENERATE JOB DEFINITION FILE command generates a USAP job definition file based on a model SAP job. The generated definition file is written to standard output.

### GENERATE JOB DEFINITION FILE Command Line Syntax

Figure 2.38, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the GENERATE JOB DEFINITION FILE command.

```
-generate jobdef -jobname jobname -jobid jobid
```

Figure 2.38 GENERATE JOB DEFINITION FILE Command Line Syntax

### GENERATE JOB DEFINITION FILE Command Argument

The GENERATE JOB DEFINITION FILE command can be expressed as:

- -generate Long form

The GENERATE JOB DEFINITION FILE command argument, **jobdef**, generates a usap job definition file based on the specified SAP job definition. The generated job definition is printed to standard output.

This command option makes it easy to create complex job definitions based on pre-existing SAP jobs. It also eliminates typing errors that can be introduced by manually coding job definition files.

### GENERATE JOB DEFINITION FILE Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to select as the model job.
JOB_NAME	Name of an existing SAP job to select as the model job.

Table 2.32 GENERATE JOB DEFINITION FILE Command Options

## 2.3.37 GENERATE VARIANT DEFINITION FILE Command

The GENERATE VARIANT DEFINITION FILE command generates a USAP variant definition file based on a model SAP variant. The generated definition file is written to standard output.

Note: GENERATE VARIANT DEFINITION FILE requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

### GENERATE VARIANT DEFINITION FILE Command Line Syntax

Figure 2.39, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the GENERATE VARIANT DEFINITION FILE command.

```
-generate vardef -variant variantname -abapname abapname
```

Figure 2.39 GENERATE VARIANT DEFINITION FILE Command Line Syntax

### GENERATE VARIANT DEFINITION FILE Command Argument

The GENERATE VARIANT DEFINITION FILE command can be expressed as:

- -generate Long form

The GENERATE VARIANT DEFINITION FILE command argument, **vardef**, generates a usap variant definition file based on the specified SAP variant. The generated variant definition is printed to standard output.

This command option makes it easy to create complex variant definitions based on pre-existing SAP variants. It also eliminates typing errors that can be introduced by manually coding variant definition files.

### GENERATE VARIANT DEFINITION FILE Command Options

Option Name	Description
VARIANT	Pre-existing SAP variant name to use as the model variant.
ABAP_NAME	Name of an ABAP program in an SAP system to which the model variant belongs.

Table 2.33 GENERATE VARIANT DEFINITION FILE Command Options

## 2.4 Configuration Options

This section identifies the Universal Connector for z/OS configuration options that are not associated with one or more Universal Connector commands. Some of these options are required for every execution of Universal Connector; others are optional for any execution.

(For detailed information on configuration options that are associated with one or more specific commands, see Section [2.3 Commands](#).)

### 2.4.1 Configuration Option Categories

The configuration options not associated with one or more specific commands are categorized into logical areas of application, as shown in [Table 2.34](#), below.

The name of each category is a link to the following information in this section:

- [Description](#) Description of the options in the category.
- [Options syntax](#) Syntax of the options on the command line.
- [Options](#) Description of the configuration options in the category and a link to detailed information about those options.

Option Categories	Description
<b>Required</b>	
<a href="#">HOST Options</a>	Specifies the SAP host to which a connection should be made.
<a href="#">USER Options</a>	Identifies the SAP user account with which the command executes.
<b>Optional</b>	
<a href="#">CFT Options</a>	Configures client fault tolerant connection.
<a href="#">COMMAND FILE Options</a>	Specifies an additional source of command options.
<a href="#">EVENT Options</a>	Specifies USAP options required for event generation.
<a href="#">Exit Codes</a>	Requests information pertaining to the USAP program.
<a href="#">LOCAL Options</a>	Specifies USAP options required for local broker registration.
<a href="#">MESSAGE Options</a>	Requests information pertaining to the USAP program.
<a href="#">RFC Options</a>	Configures fault tolerant RFC connection.

Table 2.34 Universal Connector for z/OS - Configuration Option Categories

## 2.4.2 HOST Options

The HOST options are required to establish a connection with an SAP system.

### HOST Options Syntax

Figure 2.40, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the HOST options.

```
{-dest destination | -ashost hostname -sysnr number}
-client client
[-max_xbp version]
[-saplang language]
[-xmiaudit {0|1|2|3}]
```

Figure 2.40 HOST Options Syntax

### HOST Options

Option Name	Description
AS_HOST	Host name of an SAP application server.
DESTINATION	Name of a destination defined in the <code>saprfc.ini</code> file.
CLIENT	SAP client number.
LOGON_LANGUAGE	SAP logon language used for the USAP session.
MAX_XBP	Maximum version of the SAP XBP interface that will be used during USAP execution.
SYSTEM_NUMBER	SAP system number of an SAP application server.
XMI_AUDIT_LEVEL	Sets the XMI audit level to be used for the execution of the command.

Table 2.35 HOST Options

## 2.4.3 USER Options

The USER options are required to establish an RFC connection to an SAP system. They establish the SAP user identity.

### USER Options Syntax

Figure 2.41, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the USER options.

```
-userid userid  
-pwd password
```

Figure 2.41 USER Options Syntax

### USER Options

Option Name	Description
<a href="#">USER_ID</a>	SAP user ID with which to logon to the SAP system.
<a href="#">PASSWORD</a>	Password for the SAP user ID.

Table 2.36 USER Options

## 2.4.4 CFT Options

The CFT options are used to configure a client fault tolerant job run. Client fault tolerance is requested for a USAP job run by specifying a `COMMAND_ID`.

### CFT Options Syntax

Figure 2.42, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the CFT options.

```
-cmdid id
-restart {yes|no|auto}
-autorestartok {yes|no}
-cft_secure_cft {yes|no}
-cft_abap abap_program
-cft_target_host host
-cft_cmd_prefix command_prefix
```

Figure 2.42 CFT Options Syntax

### CFT Options

Option Name	Description
<code>ALLOW_AUTO_RESTART</code>	Specification for whether or not a <b>RESTART</b> value of <b>AUTO</b> will be allowed.
<code>CFT_ABAP_PROGRAM</code>	ABAP program to use for the command ID job step.
<code>CFT_COMMAND_PREFIX</code>	In pre-XBP 2.0 CFT mode, the prefix command required for the operating system of the target host.
<code>CFT_TARGET_HOST</code>	In pre-XBP 2.0 CFT mode, the target host to use for the command ID job step when the command ID option is used.
<code>COMMAND_ID</code>	Identifier used to identify the unit of work represented by a USAP command and the associated SAP job.
<code>RESTART</code>	Specification for whether or not this execution of USAP is a restart of a previous client fault tolerant USAP command.
<code>SECURE_CFT</code>	Mode of client fault tolerance to be used for the command invocation.

Table 2.37 CFT Options

## 2.4.5 COMMAND FILE Options

The COMMAND FILE options are used to specify a file as a source of configuration options used for a command execution. The options read from a command file are processed exactly like options from any other input source.

Encrypted command files are an excellent place to store sensitive data such as user IDs and passwords. Use the Universal Encrypt utility to encrypt a plain text command file. (For information on Universal Encrypt, see the Stonebranch Solutions Utilities 4.2.0 Reference Guide.)

**Note:** All options, including required and command-specific options, can be placed in a command file.

USAP can process both plain text and encrypted command files. Either type of file can be used, but not both. If both are specified, the plain text file will be used.

### COMMAND FILE (Plain Text) Options Syntax

Figure 2.43, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the COMMAND FILE (Plain Text) options.

```
-file [ddname]
```

Figure 2.43 Command File (Plain Text) Options Syntax

### COMMAND FILE (Plain Text) Options

Option Name	Description
FILE_NAME	Name of a plain text command file.

Table 2.38 COMMAND FILE (Plain Text) Options



## COMMAND FILE (Encrypted) Options Syntax

Figure 2.44, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the COMMAND FILE (Encrypted) options.

```
-encryptedfile [ddname [-key key] ]
```

Figure 2.44 Command File (Encrypted) Options Syntax

## COMMAND FILE (Encrypted) Options

Option Name	Description
ENCRYPT_FILE	Name of an encrypted command file.
ENCRYPTION_KEY	Key used to encrypt the command file.

Table 2.39 COMMAND FILE (Encrypted) Options

## 2.4.6 EVENT Options

The EVENT options are required for event generation.

**Note:** EVENT options can be specified only in the configuration file. They have no command line or environment variable parameters.

### EVENT Options Syntax

Figure 2.45, below, illustrates the configuration file syntax of the EVENT options.

```
activity_monitoring {yes|no}
event_generation types
```

Figure 2.45 EVENT Options Syntax

### EVENT Options

Option Name	Description
ACTIVITY_MONITORING	Specification for whether or not product activity monitoring events are generated.
EVENT_GENERATION	Events to be generated as persistent events.

Table 2.40 EVENT Options

## 2.4.7 INFORMATIONAL Options

The INFORMATIONAL options request information pertaining to the USAP program.

### INFORMATIONAL Options Syntax

Figure 2.46, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the INFORMATIONAL options.

```
-help
-version
```

Figure 2.46 INFORMATIONAL Options Syntax

### INFORMATIONAL Options

Option Name	Description
HELP	Writes command line help.
VERSION	Writes USAP version and copyright information.

Table 2.41 INFORMATIONAL Options

## 2.4.8 LOCAL Options

The LOCAL options are required for local broker registration.

### LOCAL Options Syntax

Figure 2.47, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the LOCAL options.

```
-system_id id
```

Figure 2.47 LOCAL Options Syntax

### LOCAL Options

Option Name	Description
SYSTEM_ID	Local Universal Broker with which USAP must register.

Table 2.42 LOCAL Options

## 2.4.9 MESSAGE Options

The MESSAGE options specify different characteristics of **usap** messages.

### MESSAGE Options Syntax

Figure 2.48, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MESSAGE options.

```
-lang language
-level {trace|audit|info|warn|error}
-trace_file_lines lines
-trace_table size,condition
```

Figure 2.48 MESSAGE Options Syntax

### MESSAGE Options

Option Name	Description
MESSAGE_LANGUAGE	Language in which messages are written.
MESSAGE_LEVEL	Level of messages to be written.
TRACE_FILE_LINES	Maximum number of lines to write to the trace file.
TRACE_TABLE	Trace table size and under what conditions it is written to a file.

Table 2.43 MESSAGE Options

## 2.4.10 RFC Options

The RFC options always are used to configure a fault tolerant RFC connection. All RFC options have default values that are used if additional values are not provided.

### RFC Options Syntax

Figure 2.49, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the HOST options.

```
-rfc_logon_retry_interval interval
-rfc_logon_retry_count count
-rfc_listen_interval interval
-rfc_timeout interval
-rfc_retry_interval interval
-rfc_retry_count count
-rfc_trace_dir path
```

Figure 2.49 RFC Options Syntax

### RFC Options

Option Name	Description
LOGON_RETRY_INTERVAL	Number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.
LOGON_RETRY_COUNT	Number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.
LISTEN_INTERVAL	Number of seconds that will elapse between RFC listen calls.
TIMEOUT_INTERVAL	Number of seconds that can elapse before USAP considers an RFC call to have timed out.
RETRY_CALL_INTERVAL	Number of seconds that will elapse between a failed RFC call and the retry of that call.
SECURE_CFT	Number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.
TRACE_DIRECTORY	Directory where RFC trace files will be written.

Table 2.44 RFC Options

## 2.5 Exit Codes

The USAP exit code depends on the command being issued.

The following sections identify the exit codes for the various USAP commands.

**Note:** The default values listed for the exit codes are the installed (configuration file) values. These values may be different than the internal default values.

### 2.5.1 WAIT for JOB Exit Codes

If the WAIT for JOB command is specified, USAP will map the job's status upon completion to the user-definable job exit code parameters.

[Table 2.45](#), below, illustrates this mapping. USAP default values are listed in parentheses.

Job Completion Status in SAP	Exit Code
Terminated	terminated_exit_code (8)
Finished	finished_exit_code (0)
Unknown	22
Error in USAP processing (see <a href="#">Table 2.49</a> ).	> 200

Table 2.45 z/OS Wait for Job Exit Codes

### 2.5.2 WAIT for FS JOB NETWORK Exit Codes

If the WAIT for FS JOB NETWORK command is specified, USAP will map the job network's return code pair to the user-definable job network return code parameters. In this case, the exit codes are hard coded and the return code pairs used in the matching process are user definable.

[Table 2.46](#), below, illustrates this relationship. USAP default values are listed in parentheses.

Job Network Return Code Pairs Used for Matching	Exit Code
job_net_rc_00 (02,00;02,02)	0
job_net_rc_04 (02,02)	4
job_net_rc_08 (02,04)	8
job_net_rc_16 (07,00;04,00;02,08)	16
Error in USAP processing (see <a href="#">Table 2.49</a> ).	> 200

Table 2.46 z/OS Wait for FS Job Network Exit Codes

## 2.5.3 DISPLAY STATUS Exit Codes

If the DISPLAY STATUS command is specified, USAP will map the job's current status to the user definable job exit code parameters.

[Table 2.47](#), below, illustrates this relationship. USAP default values are listed in parentheses.

Job Completion Status in SAP	Exit Code
Active	active_exit_code (10)
Ready	ready_exit_code (12)
Scheduled	scheduled_exit_code (14)
Released	released_exit_code (16)
Terminated	terminated_exit_code (8)
Finished	finished_exit_code (0)
Unknown	22
Error in USAP processing (see <a href="#">Table 2.49</a> ).	> 200

Table 2.47 z/OS DISPLAY STATUS Exit Codes

## 2.5.4 DISPLAY QSTATE Exit Codes

If the DISPLAY QSTATE command is specified, USAP will map the queue's current state to the user definable `qstate` exit code parameters.

[Table 2.48](#), below, illustrates this relationship. USAP default values are listed in parentheses.

Queue State	Exit Code
'C' to be created	qtobecreated_exit_code (14)
' ' unprocessed	qunprocessed_exit_code (12)
'S' in background	qinbackground_exit_code (10)
'E' error	qerror_exit_code (8)
'F' finished	qfinished_exit_code (0)
Undefined	20
Error in USAP processing (see <a href="#">Table 2.49</a> ).	> 200

Table 2.48 z/OS Queue State Exit Codes



## 2.5.5 All Other Command Exit Codes

If USAP is not performing the WAIT for JOB, WAIT for FS JOB NETWORK, DISPLAY STATUS, or DISPLAY QSTATE command, the exit code indicates the success of the requested actions.

Table 2.49, below, lists the USAP for z/OS exit codes.

Exit Code	Description
0	Successfully completed all requested actions.
201	An error occurred processing the requested actions. Messages are printed providing details about the error.
210	Indicates an error with product configuration options or command line options.
211	An error occurred in the initialization phase of message processing. It is possible the error prohibited messages from printing.

Table 2.49 USAP for z/OS - Exit Codes

# Universal Connector for UNIX

---

## 3.1 Overview

This chapter documents Universal Connector (USAP) at a detailed level, specific to UNIX-based operating systems.

It provides sections of the following information:

- [Usage](#)
- [Commands](#)
- [Configuration Options](#)
- [Exit Codes](#)

## 3.2 Usage

Universal Connector for UNIX executes as a command line application.

Each command line execution contains:

1. Universal Connector command (and argument).
2. Configuration options associated with that command.
3. Configuration options (required and optional) not associated with any specific command.

Each execution of Universal Connector performs an operation specified by the command. The configuration options describe information / actions for that operation.

### 3.2.1 Command Line Syntax

[Figure 3.1](#), below, illustrates the command line syntax of Universal Connector for UNIX.

```
usap {RUN | SUBMIT | MODIFY | START | WAIT | ABORT | DISPLAY | GENERATE |
      PURGE | SYNTAX | RAISE EVENT} HOST USER [CFT] [EVENT] [INSTALLATION]
      [INFORMATIONAL] [LOCAL] [MESSAGE] [RFC] [COMMAND FILE]
```

Figure 3.1 Universal Connector for UNIX - Command Line Syntax

Names enclosed in {BRACES} identify command groups. For each execution, a single command is specified from one of these groups. One or more configuration options associated with each command also can be used to specify additional information / actions for the execution.

See [Section 3.3 Commands](#) for detailed information on the commands, and their associated configuration options, in each command group.

Names not enclosed in {BRACES} or [BRACKETS] identify categories of configuration options that are not associated with specific commands but from which one or more options are required.

Names encoded in [BRACKETS] identify categories of configuration options that are not associated with specific commands and from which options are not required.

See [Section 3.4 Configuration Options](#) for detailed information on configuration options not associated with one or more commands.

#### Example

The following is an example of a command line syntax executing Universal Connector:

```
usap -sub file.usp -immediate -client 987 -dest -userid 123 -pwd ABC
-lang english -level info
```

## 3.3 Commands

This section identifies all of the Universal Connector for UNIX commands.

Each command has configuration options associated with it that can be used to specify additional information / actions for an execution of that command.

(For detailed information on configuration options not associated with one or more specific commands, see Section [3.4 Configuration Options](#)).

### 3.3.1 Command Groups

Universal Connector groups commands into areas of common functionality, as shown in [Table 3.1](#), below. Each row identifies a command group, the commands in that group, and the type of operation performed by those commands.

The name of each command is a link to the following information in this section:

- **Command description** Description of the operation(s) performed by the command.
- **Command line syntax** Syntax of the command and its options on the command line.
- **Command argument** Command line expression (short and/or long form) and description of the command argument.
- **Command options** Description of the configuration options associated with the option and a link to detailed information about those options.

Command Groups	Description
RUN <ul style="list-style-type: none"> <li>• <a href="#">RUN JOB Command</a></li> <li>• <a href="#">RUN FS JOB NETWORK Command</a></li> </ul>	Performs the following actions: <ol style="list-style-type: none"> <li>1. Defines an SAP job.</li> <li>2. Starts the job.</li> <li>3. Waits for the job to complete.</li> <li>4. Writes the joblog and spoolists of the job.</li> <li>5. Purges the job from the SAP system.</li> </ol>
SUBMIT <ul style="list-style-type: none"> <li>• <a href="#">SUBMIT FS JOBNET Command</a></li> <li>• <a href="#">SUBMIT JOB Command</a></li> <li>• <a href="#">SUBMIT INTERCEPT CRITERIA TABLE Command</a></li> <li>• <a href="#">SUBMIT VARIANT Command</a></li> </ul>	Defines a job to the SAP system.
MODIFY <ul style="list-style-type: none"> <li>• <a href="#">MODIFY JOB Command</a></li> <li>• <a href="#">MODIFY VARIANT Command</a></li> </ul>	Modifies a job in an SAP job.
START <ul style="list-style-type: none"> <li>• <a href="#">START FS JOBNET Command</a></li> <li>• <a href="#">START JOB Command</a></li> </ul>	Starts a defined SAP job.

Command Groups	Description
WAIT <ul style="list-style-type: none"> <li>• <a href="#">WAIT for JOB Command</a></li> <li>• <a href="#">MASS ACTIVITY WAIT Command</a></li> <li>• <a href="#">WAIT for FS JOB NETWORK Command</a></li> <li>• <a href="#">BDCWAIT Command</a></li> </ul>	Allows USAP to reconnect to a started job and monitor it through completion.
ABORT <ul style="list-style-type: none"> <li>• <a href="#">ABORT Command</a></li> </ul>	Cancels a running SAP job.
DISPLAY <ul style="list-style-type: none"> <li>• <a href="#">DISPLAY COMMANDS Command</a></li> <li>• <a href="#">DISPLAY INTERCEPTED_JOBS Command</a></li> <li>• <a href="#">DISPLAY INTERCEPT_TABLE Command</a></li> <li>• <a href="#">DISPLAY JOBDEF Command</a></li> <li>• <a href="#">DISPLAY JOBLOG Command</a></li> <li>• <a href="#">DISPLAY OUTPUT_DEVICES Command</a></li> <li>• <a href="#">DISPLAY PRINT_FORMATS Command</a></li> <li>• <a href="#">DISPLAY QSTATE Command</a></li> <li>• <a href="#">DISPLAY REPORTS Command</a></li> <li>• <a href="#">DISPLAY SPOOLLIST Command</a></li> <li>• <a href="#">DISPLAY STATUS Command</a></li> <li>• <a href="#">DISPLAY VARIANT Command</a></li> <li>• <a href="#">DISPLAY VARIANTS Command</a></li> <li>• <a href="#">DISPLAY SELECT Command</a></li> <li>• <a href="#">DISPLAY SYSLOG Command</a></li> </ul>	Displays various SAP job data.
GENERATE <ul style="list-style-type: none"> <li>• <a href="#">GENERATE JOB DEFINITION FILE Command</a></li> <li>• <a href="#">GENERATE VARIANT DEFINITION FILE Command</a></li> </ul>	Generates USAP job or variant definitions based on model SAP jobs or variants.
PURGE <ul style="list-style-type: none"> <li>• <a href="#">PURGE JOB Command</a></li> <li>• <a href="#">PURGE FS JOB NETWORK Command</a></li> </ul>	Deletes SAP jobs.
<a href="#">RAISE EVENT Command</a>	Raises the specified SAP background processing event.
<a href="#">SYNTAX Command</a>	Checks the syntax of a job definition file.

Table 3.1 USAP for UNIX - Command Groups

---

## 3.3.2 RUN JOB Command

---

The RUN JOB command performs the following actions:

1. Defines a new SAP job, based on either a job definition specification or an existing SAP job definition.
2. Starts the defined job.
3. Waits for the job to complete.
4. Writes the job's joblog to standard error and the spoolists to standard output.
5. Purges the job from the SAP system.

The exit code of USAP will indicate the completion status of the SAP job.

See Section [3.5.1 WAIT for JOB Exit Codes](#) for a complete list of job status exit codes.

## RUN JOB Command Line Syntax

Figure 3.2, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RUN JOB command.

```
-run {filename | -jobname jobname -jobid jobid}
  [-target_jobname jobname]
  [-poll seconds]
  [-job_stat_check_interval seconds]
  [-targetserver server]
  [-target_variant job step,variant name;job step,variant name;...]
  [-immediate]
  [-activeec exitcode]
  [-readyec exitcode]
  [-scheduledec exitcode]
  [-releasedec exitcode]
  [-terminatedec exitcode]
  [-finishedec exitcode]
  [-max_log_size size]
  [-max_spool_size size]
  [-spool_codepage codepage]
  [-bdcwait
    [-bdcjobnameptrn pattern]
    [-bdcjobidptrn pattern]
    [-bdcqidptrn pattern]
    [-qtobecreatedec exitcode]
    [-qunprocessedec exitcode]
    [-qinbackgroundec exitcode]
    [-qfinishedec exitcode]
    [-qerrorec exitcode]
  ]
```

Figure 3.2 RUN JOB Command Line Syntax

## RUN JOB Command Argument

The RUN JOB command can be expressed as either:

- -R           Short form
- -run         Long form

The RUN JOB command argument, *filename*, specifies the name of the file that contains the job definition.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the job definition file.

## RUN JOB Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.
EXIT_JOB_ACTIVE	USAP exit code for the SAP job active status.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_READY	USAP exit code for the SAP job ready status.
EXIT_JOB_RELEASED	USAP exit code for the SAP job released status.
EXIT_JOB_SCHEDULED	USAP exit code for the SAP job scheduled status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state <b>S</b> (in background).
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state <b>C</b> (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state <b>E</b> (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state <b>F</b> (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state [ ] (unprocessed).
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
TARGET_JOB_NAME	Name to give the newly created job.
TARGET_SERVER	Server on which the job will run.
TARGET_VARIANT	One or more replacement variants for ABAP program job steps in an SAP job.
USAP_POLL	Length of time to wait between job status calls to the SAP system.

Table 3.2 RUN JOB Command Options



### 3.3.3 RUN FS JOB NETWORK Command

The RUN FS JOB NETWORK command performs the following actions:

1. Defines a new SAP FS job network based on a USAP FS Job Network definition file.
2. Starts the defined FS job network.
3. Waits for the started FS job network to complete.
4. Purges the FS job network from the SAP system.

The exit code of **usap** will indicate the completion status of the FS job network.

See Section [3.5.2 WAIT for FS JOB NETWORK Exit Codes](#) for a complete list of job status exit codes.

#### RUN FS JOB NETWORK Command Line Syntax

[Figure 3.3](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RUN JOB NETWORK command.

```
-run {filename | -jnetid jobnetid -jnetpcid processid}
```

Figure 3.3 RUN FS JOB NETWORK Command Line Syntax

#### RUN FS JOB Command Argument

The RUN FS JOB command can be expressed as either:

- -R            Short form
- -run        Long form

The RUN FS JOB command argument, *filename*, specifies the name of the file that contains the FS job network definition.

See Section [4.10 FS Job Network Definition File](#) for additional information on the FS job network definition file.

#### RUN FS JOB NETWORK Command Options

Option Name	Description
<a href="#">JOB_NETWORK_ID</a>	Network identifier for the pre-existing SAP FS job network being started.
<a href="#">JOB_PROCESS_ID</a>	Process ID of an existing SAP FS job network process to start.

Table 3.3 RUN FS JOB NETWORK Command Options

### 3.3.4 SUBMIT JOB Command

The SUBMIT JOB command defines a new SAP job.

#### SUBMIT JOB Command Line Syntax

Figure 3.4, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT JOB command.

```
-sub {filename | -jobname jobname -jobid jobid}
  [-target_jobname jobname]
  [-start
    [-immediate]
    [-targetserver server]
    [-target_variant job step,variant name;job step,variant name;...]
    [-wait
      [-poll seconds]
      [-joblog {yes|no}]
      [-spoolist {yes|no}]
      [-purge]
      [-waitchild {yes|no}]
      [-max_child_depth depth]
      [-joblogchild {yes|no|error}]
      [-spoolistchild {yes|no}]
      [-purgechild {yes|no}]
    ]
  ]
```

Figure 3.4 SUBMIT JOB Command Line Syntax

#### SUBMIT JOB Command Argument

The SUBMIT JOB command can be expressed as either:

- -U            Short form
- -sub         Long form

The SUBMIT JOB command argument, *filename*, specifies the name of the file that contains the job definition.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the job definition file.

## SUBMIT JOB Command Options

Option Name	Description
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_CHILD_DEPTH	Controls the maximum relationship depth that will be monitored by USAP.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoollists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoollists for child jobs.
START_JOB	Starts the newly defined job.
TARGET_JOB_NAME	Name to give the newly created job.
TARGET_VARIANT	One or more replacement variants for ABAP program job steps in an SAP job.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 3.4 SUBMIT JOB Command Options

### 3.3.5 SUBMIT VARIANT Command


The SUBMIT VARIANT command defines a new variant to an SAP system for a specified ABAP report.

Note: SUBMIT VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

#### SUBMIT VARIANT Command Line Syntax

[Figure 3.5](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT VARIANT command.



```
-sub filename
```

Figure 3.5 SUBMIT VARIANT Command Line Syntax

#### SUBMIT VARIANT Command Argument

The SUBMIT VARIANT command can be expressed as either:

- -U           Short form
- -sub        Long form

The SUBMIT VARIANT command argument, *filename*, specifies the name of the file that contains the variant definition.

See Section [4.8 Variant Definition File](#) for additional information on the variant definition file.

## 3.3.6 SUBMIT INTERCEPT CRITERIA TABLE Command

The SUBMIT INTERCEPT CRITERIA TABLE command appends or replaces the SAP intercept criteria table.

### SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax

[Figure 3.6](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT INTERCEPT CRITERIA TABLE command.

```
-sub filename
```

Figure 3.6 SUBMIT INTERCEPT CRITERIA TABLE Command Line Syntax

### SUBMIT INTERCEPT CRITERIA TABLE Command Argument

The SUBMIT INTERCEPT CRITERIA TABLE command can be expressed as either:

- -U           Short form
- -sub         Long form

The SUBMIT INTERCEPT CRITERIA TABLE command argument, *filename*, specifies the name of the file that contains the intercept criteria table definition.

See [Section 4.9 Job Intercept Table Definition File](#) for additional information on the variant definition file.

### 3.3.7 SUBMIT FS JOBNET Command

The SUBMIT FS JOBNET command defines a new FS jobnet to an SAP system.

#### SUBMIT FS JOBNET Command Line Syntax

Figure 3.7, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SUBMIT FS JOBNET command.

```
-sub {filename | -jobname jobname -jobid jobid}
  [-start
    [-wait
      [-poll seconds]
      [-purge]
    ]
  ]
```

Figure 3.7 SUBMIT FS JOBNET Command Line Syntax

#### SUBMIT FS JOBNET Command Argument

The SUBMIT FS JOBNET command can be expressed as either:

- -U           Short form
- -sub         Long form

The SUBMIT FS JOBNET command argument, *filename*, specifies the name of the file that contains the FS jobnet definition.

See Section [4.10 FS Job Network Definition File](#) for additional information on the variant definition file.

#### SUBMIT FS JOBNET Command Options

Option Name	Description
PURGE_JOB	Purge job that has completed processing from SAP system.
START_JOB	Starts the newly defined job.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.

Table 3.5 SUBMIT FS JOBNET Command Options

---

## 3.3.8 MODIFY JOB Command

---

The MODIFY JOB command is used to modify an SAP job that already exists in an SAP system. A USAP job definition file is used to specify the modifications.

Job definition files are used to define new SAP jobs and to modify existing SAP jobs. The same syntactical rules apply to the job definition file in both cases with the following exceptions when modifying jobs:

1. SAP job identifier must be specified in order to identify the existing job to modify. The job identifier is specified in the job definition file using the JOBCOUNT keyword of the Job Header statement or the `-jobid` option of the MODIFY command. If both are used, the `-jobid` option overrides the JOBCOUNT value.
2. ABAP Step and External Step job definition statements must specify the step number of the existing job step to modify. The step number is specified using the STEP\_NUMBER keyword of the ABAP Step and External Step job definition statements.

The parameter values specified in job definition file replace existing values in the SAP job definition. If a parameter is not specified in the job definition file, no change is made to the corresponding value in the existing SAP job definition.

See [Chapter 4 Universal Connector Job Definition Files](#) for additional information on the job definition file.

## MODIFY JOB Command Line Syntax

Figure 3.8, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MODIFY JOB command.

```
-modify filename
  [-jobid jobid]
  [-start
    [-immediate]
    [-targetserver server]
    [-wait
      [-poll seconds]
      [-joblog {yes|no}]
      [-spoollist {yes|no}]
      [-purge]
      [-waitchild {yes|no}]
      [-joblogchild {yes|no|error}]
      [-spoollistchild {yes|no}]
      [-purgechild {yes|no}]
    ]
  ]
```

Figure 3.8 MODIFY JOB Command Line Syntax

## MODIFY JOB Command Argument

The MODIFY JOB command can be expressed as either:

- -M           Short form
- -modify     Long form

The MODIFY JOB command argument, *filename*, specifies the name of the job definition file that contains the modification information.

See Chapter 4 [Universal Connector Job Definition Files](#) for additional information on the variant definition file.



## MODIFY JOB Command Options

Option Name	Description
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to be modified.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.
START_JOB	Starts the newly defined job.
TARGET_SERVER	Server on which the job will run.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 3.6 MODIFY JOB Command Options

### 3.3.9 MODIFY VARIANT Command

The MODIFY VARIANT command is used to modify an SAP variant that already exists in an SAP system. A USAP variant definition file is used to specify the modifications.

Note: MODIFY VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)


Variant definition files are used to define new SAP variants and to modify existing SAP variants. The same syntactical rules apply to the variant definition file in both cases.

The parameter values specified in a variant definition file replace existing values in the SAP variant definition. If a parameter is not specified in the variant definition file, no change is made to the corresponding value in the existing SAP variant definition.

See Section 5.10 Variant Definition File for additional information on the variant definition file.

#### MODIFY VARIANT Command Line Syntax

[Figure 3.9](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MODIFY VARIANT command.



```
-modify filename
```

Figure 3.9 MODIFY VARIANT Command Line Syntax

#### MODIFY VARIANT Command Argument

The MODIFY VARIANT command can be expressed as either:

- -M Short form
- -modify Long form

The MODIFY VARIANT command argument, *filename*, specifies the name of the variant definition file that contains the modification information.

See Section [4.8 Variant Definition File](#) for additional information on the variant definition file.

## 3.3.10 START JOB Command

The START JOB command starts a currently defined SAP job.

### START JOB Command Line Syntax

Figure 3.10, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the START JOB command.

```
-start -jobname jobname -jobid jobid
  [-immediate]
  [-targetserver server]
  [-wait
    [-poll seconds]
    [-joblog {yes|no}]
    [-spoollist {yes|no}]
    [-purge]
    [-terminatedec exitcode]
    [-finishedec exitcode]
  ]
  [-bdcwait
    [-bdcjobnameptrn pattern]
    [-bdcjobidptrn pattern]
    [-bdcqidptrn pattern]
    [-qtobecreatedec exitcode]
    [-qunprocessedec exitcode]
    [-qinbackgroundec exitcode]
    [-qfinishedec exitcode]
    [-qerrorec exitcode]
  ]
]
```

Figure 3.10 START JOB Command Line Syntax

## START JOB Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state 'S' (in background)
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state 'C' (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state 'E' (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state 'F' (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state ' ' (unprocessed).
IMMEDIATE_JOB	Causes the job to be started immediately.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.
TARGET_SERVER	Server on which the job will run.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 3.7 START JOB Command Options

### 3.3.11 START FS JOBNET Command

The START FS JOBNET command starts a specified FS job network on an SAP system.

#### START FS JOBNET Command Line Syntax

Figure 3.11, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the START FS JOBNET command.

```
-start -jnetid jobnet_id -jnetprcid jobnet_process_id
  [-wait
    [-poll seconds]
    [-purge]
  ]
```

Figure 3.11 START FS JOBNET Command Line Syntax

#### START FS JOBNET Command Options

Option Name	Description
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.
PURGE_JOB	Purge job that has completed processing from SAP system.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
WAIT	Wait for the SAP job to complete processing.

Table 3.8 START FS JOBNET Command Options

### 3.3.12 WAIT for JOB Command

The WAIT for JOB command allows USAP to reconnect to a started job and monitor it through completion.

#### WAIT for JOB Command Line Syntax

Figure 3.12, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the WAIT for JOB command.

```
-wait -jobname jobname -jobid jobid
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-applog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-spoollist {yes|no}]
  [-spool_codepage codepage]
  [-transtab translation_table]
  [-terminatedec exitcode]
  [-finishedec exitcode]
  [-poll seconds]
  [-purge]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-waitchild {yes|no}]
  [-max_child_depth depth]
  [-joblogchild {yes|no|error}]
  [-spoollistchild {yes|no}]
  [-purgechild {yes|no}]
  [-max_log_size size]
  [-max_spool_size size]
```

Figure 3.12 WAIT for JOB Command Line Syntax

## WAIT for JOB Command Options

Option Name	Description
WAIT	Causes USAP to wait for the SAP job to complete processing
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_LOG_CHILD	Controls the printing of job logs for child jobs.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_CHILD_DEPTH	Controls the maximum relationship depth that will be monitored by USAP.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
PURGE_CHILD_JOBS	Controls the purging of child jobs.
PURGE_JOB	Purge job that has completed processing from SAP system.
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
RETURN_SPOOL_LIST	Specification for whether or not the spoollists of all job steps are returned.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
SPOOL_LIST_CHILD	Controls the printing of spoollists for child jobs.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job <b>end</b> time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
TRANSLATION_TABLE	Spoollist translation table file to use for formatting returned spoollists.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.

Table 3.9 WAIT for JOB Command Options

### 3.3.13 MASS ACTIVITY WAIT Command

The MASS ACTIVITY WAIT command allows USAP to wait for (or reconnect and wait for) a started mass activity job and monitor it, and all its interval jobs, through completion.

#### MASS ACTIVITY WAIT Command Line Syntax

Figure 3.13, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MASS ACTIVITY WAIT command.

```
-mawait -jobname jobname -jobid jobid
  [-poll seconds]
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-applog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-transtab translation_table]
  [-purge]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-terminatedec exitcode]
  [-finishedec exitcode]
```

Figure 3.13 MASS ACTIVITY WAIT Command Line Syntax



## MASS ACTIVITY WAIT Command Options

Option Name	Description
<a href="#">MASS_ACTIVITY_WAIT</a>	Causes USAP to wait for the SAP mass activity jobs to complete processing.
<a href="#">EXIT_JOB_FINISHED</a>	USAP exit code for the SAP job finished status.
<a href="#">EXIT_JOB_TERMINATED</a>	USAP exit code for the SAP job terminated status.
<a href="#">JOB_ID</a>	Job ID of an existing SAP job to use as a model for the new job definition.
<a href="#">JOB_NAME</a>	Name of an existing SAP job to use as a model for the new job definition.
<a href="#">PURGE_JOB</a>	Purge job that has completed processing from SAP system.
<a href="#">RETURN_APPLICATION_LOG</a>	Specification for whether or not the job's application log is returned.
<a href="#">RETURN_APPLICATION_RC</a>	Specification for whether or not the job's application return codes are returned.
<a href="#">RETURN_JOB_LOG</a>	Specification for whether or not the job's joblog is returned.
<a href="#">STATUS_CHECK_INTERVAL</a>	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
<a href="#">SYSLOG</a>	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
<a href="#">SYSLOG_POST_TIME</a>	Length of time to add to the job <b>end</b> time when calculating the <b>to</b> time for the syslog report.
<a href="#">SYSLOG_PRE_TIME</a>	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
<a href="#">TRANSLATION_TABLE</a>	Spoolist translation table file to use for formatting returned spoolists.
<a href="#">USAP_POLL</a>	Length of time to wait between job status calls to the SAP system.
<a href="#">USE_APPLICATION_RC</a>	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.

Table 3.10 MASS ACTIVITY WAIT Command Options

### 3.3.14 WAIT for FS JOB NETWORK Command

The WAIT for FS JOB NETWORK command allows USAP to reconnect to a started FS job network and monitor it through completion.

#### WAIT for FS JOB NETWORK Command Line Syntax

Figure 3.14, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the WAIT for FS JOB NETWORK command.

```

-wait -jnetid jobnetid -jnetprcid processid
      [-poll seconds]
      [-purge]
      [-syslog {yes|no}
        [-syslogpre seconds]
        [-syslogpost seconds]
      ]
      [-max_log_size size]
      [-max_spool_size size

```

Figure 3.14 WAIT for FS JOB NETWORK Command Line Syntax

#### WAIT for FS JOB NETWORK Command Options

Option Name	Description
WAIT	Causes USAP to wait for the SAP job network to complete processing.
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.
MAX_JOB_LOG_SIZE	Maximum size for job logs.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
PURGE_JOB	Purge job that has completed processing from SAP system.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job end time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
USAP_POLL	Length of time to wait between job status calls to the SAP system.

Table 3.11 WAIT for FS JOB NETWORK Command Options

## 3.3.15 BDCWAIT Command

The BDCWAIT command allows USAP to reconnect to a started batch input processing job and monitor it, and all its generated session processing jobs, through completion.

### BDCWAIT Command Line Syntax

Figure 3.15, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the BDCWAIT command.

```
-bdcwait -jobname jobname -jobid jobid
  [-poll seconds]
  [-job_stat_check_interval seconds]
  [-joblog {yes|no}]
  [-applog {yes|no}]
  [-printapprc {yes|no}]
  [-useapprc {yes|no}]
  [-transtab translation_table]
  [-purge]
  [-purge_bdc_map {yes|no}]
  [-syslog {yes|no}
    [-syslogpre seconds]
    [-syslogpost seconds]
  ]
  [-terminatedec exitcode]
  [-finishedec exitcode]
  [-qtobecreatedec exitcode]
  [-qunprocessedec exitcode]
  [-qinbackgroundec exitcode]
  [-qfinishedec exitcode]
  [-qerrorec exitcode]
  [-bdcjobnameptrn pattern]
  [-bdcjobidptrn pattern]
  [-bdcqidptrn pattern]
```

Figure 3.15 BDCWAIT Command Line Syntax

## BDCWAIT Command Options

Option Name	Description
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.
EXIT_JOB_FINISHED	USAP exit code for the SAP job finished status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job terminated status.
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state 'S' (in background).
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state 'C' (to be created).
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state 'E' (error).
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state 'F' (finished).
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state ' ' (unprocessed).
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the <b>RSBDCSUB</b> batch input processing report.
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the <b>RSBDCSUB</b> batch input processing report.
PURGE_BDC_MAP	Specification for whether or not to delete BDC Batch input session queues that have been processed successfully.
PURGE_JOB	Purge job that has completed processing from SAP system.
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the <b>RSBDCSUB</b> batch input processing report.
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.
RETURN_JOB_LOG	Specification for whether or not the job's joblog is returned.
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.
SYSLOG	Specification for whether or not a syslog report is generated on standard error if the job does not complete successfully.
SYSLOG_POST_TIME	Length of time to add to the job end time when calculating the <b>to</b> time for the syslog report.
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.
TRANSLATION_TABLE	Spoolist translation table file to use for formatting returned spoolists.
USAP_POLL	Length of time to wait between job status calls to the SAP system.
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the USAP job.

Table 3.12 BDCWAIT Command Options

## 3.3.16 ABORT Command

The ABORT command cancels a running SAP job.

### ABORT Command Line Syntax

Figure 3.16, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the ABORT command.

```
-abort -jobname jobname -jobid jobid
```

Figure 3.16 ABORT Command Line Syntax

### ABORT Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 3.13 ABORT Command Options

### 3.3.17 PURGE JOB Command

The PURGE JOB command deletes a defined SAP job, its joblog, and all of its spoolists. This command is not available on SAP 3.1 and SAP 4.0 systems.

#### PURGE JOB Command Line Syntax

Figure 3.17, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the PURGE JOB command.

```
-purge -jobname jobname -jobid jobid
```

Figure 3.17 PURGE JOB Command Line Syntax

#### PURGE JOB Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 3.14 PURGE JOB Command Options

### 3.3.18 PURGE FS JOB NETWORK Command

The PURGE FS JOB NETWORK command deletes a defined SAP FS job network.

#### PURGE FS JOB NETWORK Command Line Syntax

Figure 3.18, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the PURGE FS JOB NETWORK command.

```
-purge -jnetid jobnetid -jnetpcid processid
```

Figure 3.18 PURGE FS JOB NETWORK Command Line Syntax

#### PURGE FS JOB NETWORK Command Options

Option Name	Description
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.

Table 3.15 PURGE FS JOB NETWORK Command Options

### 3.3.19 RAISE EVENT Command

The RAISE EVENT command raises the specified SAP background processing event.

#### RAISE EVENT Command Line Syntax

Figure 3.19, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RAISE EVENT command.

```
-raise_bp_event -event_id id -event_parm parm
```

Figure 3.19 RAISE EVENT Command Line Syntax

#### RAISE EVENT Command Options

Option Name	Description
EVENT_ID	Name of the event.
EVENT_PARAMETER	Optional parameter value for the event.

Table 3.16 RAISE EVENT Command Options



## 3.3.20 SYNTAX Command

---

The SYNTAX command checks the syntax of a USAP definition file.

### SYNTAX Command Line Syntax

[Figure 3.20](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the SYNTAX command.

```
-syntax filename
```

Figure 3.20 SYNTAX Command Line Syntax

### SYNTAX Command Argument

The SYNTAX command can be expressed as either:

- -X           Short form
- -syntax     Long form

The SYNTAX command argument, *filename*, specifies the name of the definition file that contains the job, variant, or FS job network definition.

- See [Chapter 4 Universal Connector Job Definition Files](#) for additional information on the job definition file.
- See [Section 4.8 Variant Definition File](#) for additional information on the variant definition file.
- See [Section 4.10 FS Job Network Definition File](#) for additional information on the FS Job Network definition file.

### 3.3.21 DISPLAY JOBLOG Command

The DISPLAY JOBLOG command displays the job log for a specified SAP job.

#### DISPLAY JOBLOG Command Line Syntax

Figure 3.21, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY JOBLOG command.

```
-display joblog -jobname jobname -jobid jobid -max_log_size size
```

Figure 3.21 DISPLAY JOBLOG Command Line Syntax

#### DISPLAY JOBLOG Command Argument

The DISPLAY JOBLOG command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY JOBLOG command argument, **joblog**, requests the display of a job's joblog.

#### DISPLAY JOBLOG Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_JOB_LOG_SIZE	Maximum size for job logs.

Table 3.17 DISPLAY JOBLOG Command Options

### 3.3.22 DISPLAY SPOOLLIST Command

The DISPLAY SPOOLLIST command displays the spoollist for a job step.

#### DISPLAY SPOOLLIST Command Line Syntax

Figure 3.22, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SPOOLLIST command.

```

-display spoollist -jobname jobname -jobid jobid
      -stepnum stepnumber -max_spool_size size
      [-spool_codepage codepage]
      [-transtab translation_table]
```

Figure 3.22 DISPLAY SPOOLLIST Command Line Syntax

#### DISPLAY SPOOLLIST Command Argument

The DISPLAY SPOOLLIST command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY SPOOLLIST command argument, **spoollist**, requests the display of a job step’s spoollist.

#### DISPLAY SPOOLLIST Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.
SPOOL_CODEPAGE	Codepage used for transferring spool lists from SAP system.
STEP_NUMBER	Step number of the SAP job step.
TRANSLATION_TABLE	spoollist translation table file to use for formatting returned spoollists.

Table 3.18 DISPLAY SPOOLLIST Command Options

### 3.3.23 DISPLAY STATUS Command

The DISPLAY STATUS command displays the current status for an SAP job. The status is printed to standard output and the exit code of **usap** indicates the status. See Section [3.5 Exit Codes](#) for a complete list of job status exit codes.

#### DISPLAY STATUS Command Line Syntax

[Figure 3.23](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY STATUS command.

```
-display status -jobname jobname -jobid jobid  
  [-activeec exitcode ]  
  [-readyec exitcode ]  
  [-schedulec exitcode ]  
  [-releasedec exitcode ]  
  [-terminatedec exitcode ]  
  [-finishedec exitcode ]
```

Figure 3.23 DISPLAY STATUS Command Line Syntax

#### DISPLAY STATUS Command Argument

The DISPLAY STATUS command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY STATUS command argument, **status**, requests a job status.

The status is printed to standard output and the exit code of USAP indicates the status. See Section [3.5 Exit Codes](#) for a complete list of job status exit codes.

## DISPLAY STATUS Command Options

Option Name	Description
EXIT_JOB_ACTIVE	USAP exit code for the SAP job <b>active</b> status.
EXIT_JOB_FINISHED	USAP exit code for the SAP job <b>finished</b> status.
EXIT_JOB_READY	USAP exit code for the SAP job <b>ready</b> status.
EXIT_JOB_RELEASED	USAP exit code for the SAP job <b>released</b> status.
EXIT_JOB_SCHEDULED	USAP exit code for the SAP job <b>scheduled</b> status.
EXIT_JOB_TERMINATED	USAP exit code for the SAP job <b>terminated</b> status.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 3.19 DISPLAY STATUS Command Options

### 3.3.24 DISPLAY VARIANTS Command

The DISPLAY VARIANTS command displays the variants available for the specified ABAP program.

#### DISPLAY VARIANTS Command Line Syntax

Figure 3.24, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY VARIANTS command.

```
-display variants -abapname abapname -varselopt {A|B}
```

Figure 3.24 DISPLAY VARIANTS Command Line Syntax

#### DISPLAY VARIANTS Command Argument

The DISPLAY VARIANTS command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY VARIANTS command argument, **variants**, displays the variants defined for ABAP program **abapname**.

- Using **-varselopt A** will display the variants that are available for batch and dialog mode.
- Using **-varselopt B** will display the variants that are available for batch mode only.

#### DISPLAY VARIANTS Command Options

Option Name	Description
ABAP_NAME	Name of an ABAP program in an SAP system.
VARIANT_SELECTION	Specification to display either variants available for batch and dialog mode or variants available only for batch mode.

Table 3.20 DISPLAY VARIANTS Command Options

### 3.3.25 DISPLAY VARIANT Command

The DISPLAY VARIANT command displays the contents of a specified variant.

Note: DISPLAY VARIANT requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

#### DISPLAY VARIANT Command Line Syntax

Figure 3.25, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY VARIANT command.

```
-display variant -variant variantname -varlang language
-abapname abapname
```

Figure 3.25 DISPLAY VARIANT Command Line Syntax

#### DISPLAY VARIANT Command Argument

The DISPLAY VARIANT command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY VARIANT command argument, **variant**, displays the specified SAP variant.

#### DISPLAY VARIANT Command Options

Option Name	Description
<a href="#">ABAP_NAME</a>	Name of an ABAP program in an SAP system.
<a href="#">VARIANT</a>	Pre-existing SAP variant whose contents will be displayed.
<a href="#">VARIANT_LANGUAGE</a>	Preferred language in which to return the variant description.

Table 3.21 DISPLAY VARIANT Command Options

### 3.3.26 DISPLAY JOBDEF Command

The DISPLAY JOBDEF command displays the definition of the specified SAP job.

#### DISPLAY JOBDEF Command Line Syntax

Figure 3.26, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY JOBDEF command.

```
-display jobdef -jobname jobname -jobid jobid
```

Figure 3.26 DISPLAY JOBDEF Command Line Syntax

#### DISPLAY JOBDEF Command Argument

The DISPLAY JOBDEF command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY JOBDEF command argument, **jobdef**, requests the display of a job's definition.

#### DISPLAY JOBDEF Command Options

Option Name	Description
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.

Table 3.22 DISPLAY JOBDEF Command Options



### 3.3.27 DISPLAY SELECT Command

The DISPLAY SELECT command displays a variety of attributes for a list of SAP jobs that match the specified criteria.

#### DISPLAY SELECT Command Line Syntax

Figure 3.27, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SELECT command.

```
-display select -jobname jobmask
  [-jobid idmask ]
  [-selusername userid ]
  [-fromdate date ]
  [-todate date ]
  [-fromtime time ]
  [-totime time ]
  [-nodate {yes|no} ]
  [-withpred {yes|no} ]
  [-released {yes|no} ]
  [-scheduled {yes|no} ]
  [-ready {yes|no} ]
  [-running {yes|no} ]
  [-finished {yes|no} ]
  [-aborted {yes|no} ]
  [-output output-field-list]
```

Figure 3.27 DISPLAY SELECT Command Line Syntax

#### DISPLAY SELECT Command Argument

The DISPLAY SELECT command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY SELECT command argument, **select**, requests the display of all jobs matching the **jobmask** and any additional selection criteria specified. The default output for this command is the job name and job ID for each job found. However, additional fields can be printed using the **-output** option.

Note: This command is not available on SAP 3.1 and SAP 4.0 systems.

## DISPLAY SELECT Command Options

Option Name	Description
FROM_DATE	Earliest date to use for job selection or syslog request.
FROM_TIME	Earliest time to use for job selection or syslog request.
JOB_ID	Job ID of an existing SAP job to use as a model for the new job definition.
JOB_NAME	Name of an existing SAP job to use as a model for the new job definition.
NO_START_DATE	Specification for whether or not to include jobs with no start date in selection criteria.
OUTPUT_FIELD_LIST	Additional fields to write for the <b>select</b> command.
STATUS_ABORTED	Specification for whether or not to include jobs with status aborted in selection criteria.
STATUS_FINISHED	Specification for whether or not to include jobs with status finished in selection criteria.
STATUS_READY	Specification for whether or not to include jobs with status ready in selection criteria.
STATUS_RELEASED	Specification for whether or not to include jobs with status released in selection criteria.
STATUS_RUNNING	Specification for whether or not to include jobs with status running in selection criteria.
STATUS_SCHEDULED	Specification for whether or not to include jobs with status scheduled in selection criteria.
TO_DATE	Latest date to use for job selection or syslog request.
TO_TIME	Latest time to use for job selection or syslog request.
USER_NAME	User ID associated with a job.
WITH_PREDECESSOR	Specification for whether or not to include jobs with start after predecessor in selection criteria.

Table 3.23 DISPLAY SELECT Command Options

### 3.3.28 DISPLAY SYSLOG Command

The DISPLAY SYSLOG command displays a portion of an SAP syslog that meets the specified date/time constraints.

#### DISPLAY SYSLOG Command Line Syntax

Figure 3.28, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY SYSLOG command.

```
-display syslog -fromdate date -todate date
  [-fromtime time      ]
  [-totime time        ]
  [-pagelimit limit    ]
  [-targetserver server]
```

Figure 3.28 DISPLAY SYSLOG Command Line Syntax

#### DISPLAY SYSLOG Command Argument

The DISPLAY SYSLOG command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY SYSLOG command argument, **syslog**, requests entries from an SAP System syslog for a specified date and time range.

#### DISPLAY SYSLOG Command Options

Option Name	Description
FROM_DATE	Earliest date to use for job selection or syslog request.
FROM_TIME	Earliest time to use for job selection or syslog request.
PAGE_LIMIT	Maximum number of pages that can be returned in the syslog report.
TARGET_SERVER	Name of the server whose syslog will be read.
TO_DATE	Latest date to use for job selection or syslog request.
TO_TIME	Latest time to use for job selection or syslog request.

Table 3.24 DISPLAY SYSLOG Command Options

### 3.3.29 DISPLAY INTERCEPTED\_JOBS Command

The DISPLAY INTERCEPTED\_JOBS command displays the job intercept for the connected SAP system.

#### DISPLAY INTERCEPTED\_JOBS Command Line Syntax

Figure 3.29, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY INTERCEPTED\_JOBS command.

```
-display intercepted_jobs -dspclient client
```

Figure 3.29 DISPLAY INTERCEPT\_JOBS Command Line Syntax

#### DISPLAY INTERCEPTED\_JOBS Command Argument

The DISPLAY INTERCEPTED\_TABLE command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY INTERCEPTED\_JOBS command argument, **intercepted\_jobs**, requests the display of an SAP system's intercepted jobs. Unless a specific client is identified, intercepted jobs for all clients are displayed.

#### DISPLAY INTERCEPTED\_JOBS Command Options

Option Name	Description
DISPLAY_CLIENT	Specific SAP client whose intercepted jobs will be reported.

Table 3.25 DISPLAY INTERCEPTED\_JOBS Command Options

### 3.3.30 DISPLAY INTERCEPT\_TABLE Command

---

The DISPLAY INTERCEPT\_TABLE command displays the contents of the job intercept criteria table for the connected SAP system.

#### DISPLAY INTERCEPT\_TABLE Command Line Syntax

Figure 3.30, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY INTERCEPT\_TABLE command.

```
-display intercept_table
```

Figure 3.30 DISPLAY INTERCEPT\_TABLE Command Line Syntax

#### DISPLAY INTERCEPT\_TABLE Command Argument

The DISPLAY INTERCEPT\_TABLE command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY INTERCEPT\_TABLE command argument, **intercept\_table**, requests the display of an SAP system's job intercept criteria table.

### 3.3.31 DISPLAY QSTATE Command

The DISPLAY QSTATE command displays the state of a specific Batch Input / BDC session queue in an SAP system.

#### DISPLAY QSTATE Command Line Syntax

Figure 3.31, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY QSTATE command.

```
-display qstate -qid queueid
```

Figure 3.31 DISPLAY QSTATE Command Line Syntax

#### DISPLAY QSTATE Command Argument

The DISPLAY QSTATE command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY QSTATE command argument, **qstate**, requests the state of a queue used to process a batch input session. See Section [3.5.4 DISPLAY QSTATE Exit Codes](#) for a complete list of queue state exit codes.

#### DISPLAY QSTATE Command Options

Option Name	Description
<a href="#">QUEUE_ID</a>	Queue identifier associated with the batch input session.

Table 3.26 DISPLAY QSTATE Command Options

### 3.3.32 DISPLAY REPORTS Command

The DISPLAY REPORTS command displays a list of ABAP reports that match the specified criteria.

#### DISPLAY REPORTS Command Line Syntax

Figure 3.32, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY REPORTS command.

```
-display reports -abapname abapmask -count max_hit_count
```

Figure 3.32 DISPLAY REPORTS Command Line Syntax

#### DISPLAY REPORTS Command Argument

The DISPLAY REPORTS command can be expressed as either:

- -D            Short form
- -display    Long form

The DISPLAY REPORTS command argument, **reports**, requests the display of a list of ABAP reports that match the specified criteria.

#### DISPLAY REPORTS Command Options

Option Name	Description
<code>ABAP_NAME</code>	Complete ABAP name or a mask used to select SAP ABAP reports that match the mask.
<code>MAX_HIT_COUNT</code>	Maximum number of ABAP reports to be returned.

Table 3.27 DISPLAY REPORTS Command Options

### 3.3.33 DISPLAY COMMANDS Command

The DISPLAY COMMANDS command displays a list of SAP external commands that match the specified criteria.

#### DISPLAY COMMANDS Command Line Syntax

Figure 3.33, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY COMMANDS command.

```
-display commands -cmd external_command_mask -opsys operating_system
```

Figure 3.33 DISPLAY COMMANDS Command Line Syntax

#### DISPLAY COMMANDS Command Argument

The DISPLAY COMMANDS command can be expressed as either:

- -D Short form
- -display Long form

The DISPLAY COMMANDS command argument, **commands**, requests the display of a list of SAP external commands that match the specified criteria.

#### DISPLAY COMMANDS Command Options

Option Name	Description
EXTERNAL_COMMAND	Complete command name or a mask used to select SAP external commands that match the mask.
OPERATING_SYSTEM	Name of the operating system for which external commands are searched.

Table 3.28 DISPLAY COMMANDS Command Options



### 3.3.34 DISPLAY OUTPUT\_DEVICES Command

The DISPLAY OUTPUT\_DEVICES command displays a list of SAP output devices that match the specified criteria.

#### DISPLAY OUTPUT\_DEVICES Command Line Syntax

Figure 3.34, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY OUTPUT\_DEVICES command.

```
-display output_devices -short_name technical_device_name_mask
      -long_name long_device_name_mask
```

Figure 3.34 DISPLAY OUTPUT\_DEVICES Command Line Syntax

#### DISPLAY OUTPUT\_DEVICES Command Argument

The DISPLAY OUTPUT\_DEVICES command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY OUTPUT\_DEVICES command argument, **output\_devices**, requests the display of a list of SAP output devices that match the specified criteria.

#### DISPLAY OUTPUT\_DEVICES Command Options

Option Name	Description
TECHNICAL_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.
LONG_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.

Table 3.29 DISPLAY OUTPUT\_DEVICES Command Options

### 3.3.35 DISPLAY PRINT\_FORMATS Command

The DISPLAY PRINT\_FORMATS command displays a list of print formats that are available for the specified printer.

#### DISPLAY PRINT\_FORMATS Command Line Syntax

Figure 3.35, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the DISPLAY PRINT\_FORMATS command.

```
-display print_formats -printer printer_name -layout layout
```

Figure 3.35 DISPLAY PRINT\_FORMATS Command Line Syntax

#### DISPLAY PRINT\_FORMAT Command Argument

The DISPLAY PRINT\_FORMAT command can be expressed as either:

- -D           Short form
- -display    Long form

The DISPLAY PRINT\_FORMAT command argument, **print\_formats**, requests the display of a list of print formats available for the specified printer.

#### DISPLAY PRINT\_FORMATS Command Options

Option Name	Description
LAYOUT_NAME	Complete layout name or a mask used to select printer layouts that match the mask.
PRINTER_NAME	Name of a printer for which the print formats will be retrieved.

Table 3.30 DISPLAY PRINT\_FORMATS Command Options

### 3.3.36 GENERATE JOB DEFINITION FILE Command

The GENERATE JOB DEFINITION FILE command generates a USAP job definition file based on a model SAP job. The generated definition file is written to standard output.

#### GENERATE JOB DEFINITION FILE Command Line Syntax

Figure 3.36, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the GENERATE JOB DEFINITION FILE command.

```
-generate jobdef -jobname jobname -jobid jobid
```

Figure 3.36 GENERATE JOB DEFINITION FILE Command Line Syntax

#### GENERATE JOB DEFINITION FILE Command Argument

The GENERATE JOB DEFINITION FILE command can be expressed as:

- -generate Long form

The GENERATE JOB DEFINITION FILE command argument, **jobdef**, generates a usap job definition file based on the specified SAP job definition. The generated job definition is printed to standard output.

This command option makes it easy to create complex job definitions based on pre-existing SAP jobs. It also eliminates typing errors that can be introduced by manually coding job definition files.

#### GENERATE JOB DEFINITION FILE Command Options

Option Name	Description
<code>JOB_NAME</code>	Name of an existing SAP job to select as the model job.
<code>JOB_ID</code>	Job ID of an existing SAP job to select as the model job.

Table 3.31 GENERATE JOB DEFINITION FILE Command Options

### 3.3.37 GENERATE VARIANT DEFINITION FILE Command

The GENERATE VARIANT DEFINITION FILE command generates a USAP variant definition file based on a model SAP variant. The generated definition file is written to standard output.

Note: GENERATE VARIANT DEFINITION FILE requires XBP interface 2.0.

(See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for information on XBP interface 2.0.)

#### GENERATE VARIANT DEFINITION FILE Command Line Syntax

[Figure 3.37](#), below, illustrates the command line syntax – using the command line, long form of the configuration options – of the GENERATE VARIANT DEFINITION FILE command.

```
-generate vardef -variant variantname -abapname abapname
```

Figure 3.37 GENERATE VARIANT DEFINITION FILE Command Line Syntax

#### GENERATE VARIANT DEFINITION FILE Command Argument

The GENERATE VARIANT DEFINITION FILE command can be expressed as:

- -generate Long form

The GENERATE VARIANT DEFINITION FILE command argument, **vardef**, generates a usap variant definition file based on the specified SAP variant. The generated variant definition is printed to standard output.

This command option makes it easy to create complex variant definitions based on pre-existing SAP variants. It also eliminates typing errors that can be introduced by manually coding variant definition files.

#### GENERATE VARIANT DEFINITION FILE Command Options

Option Name	Description
VARIANT	Pre-existing SAP variant name to use as the model variant.
ABAP_NAME	Name of an ABAP program in an SAP system to which the model variant belongs.

Table 3.32 GENERATE VARIANT DEFINITION FILE Command Options

## 3.4 Configuration Options

This section identifies the Universal Connector for UNIX configuration options that are not associated with one or more Universal Connector commands. Some of these options are required for every execution of Universal Connector; others are optional for any execution.

(For detailed information on configuration options that are associated with one or more specific commands, see Section [3.3 Commands](#).)

### 3.4.1 Configuration Option Categories

The configuration options not associated with one or more specific commands are categorized into logical areas of application, as shown in [Table 3.33](#), below.

The name of each category is a link to the following information in this section:

- [Description](#) Description of the options in the category.
- [Options syntax](#) Syntax of the options on the command line.
- [Options](#) Description of the configuration options in the category and a link to detailed information about those options in the Universal Connector 4.2.0 Reference Guide.

Option Categories	Description
<b>Required</b>	
<a href="#">HOST Options</a>	Specifies the SAP host to which a connection should be made.
<a href="#">USER Options</a>	Identifies the SAP user account with which the command executes.
<b>Optional</b>	
<a href="#">CFT Options</a>	Configures client fault tolerant connection.
<a href="#">COMMAND FILE Options</a>	Specifies an additional source of command options.
<a href="#">EVENT Options</a>	Specifies USAP options required for event generation.
<a href="#">Exit Codes</a>	Requests information pertaining to the USAP program.
<a href="#">INSTALLATION Options</a>	Specifies USAP options required for installation.
<a href="#">LOCAL Options</a>	Specifies USAP options required for local broker registration.
<a href="#">MESSAGE Options</a>	Requests information pertaining to the USAP program.
<a href="#">RFC Options</a>	Configures fault tolerant RFC connection.

Table 3.33 Universal Connector for UNIX - Configuration Option Categories

## 3.4.2 HOST Options

The HOST options are required to establish a connection with an SAP system.

### HOST Options Syntax

Figure 3.38, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the HOST options.

```
{-dest destination | -ashost hostname -sysnr number}
-client client
[-max_xbp version]
[-saplang language]
[-xmiaudit {0|1|2|3}]
```

Figure 3.38 HOST Options Syntax

### HOST Options

Option Name	Description
AS_HOST	Host name of an SAP application server.
DESTINATION	Name of a destination defined in the <code>saprfc.ini</code> file.
CLIENT	SAP client number.
LOGON_LANGUAGE	SAP logon language used for the USAP session.
MAX_XBP	Maximum version of the SAP XBP interface that will be used during USAP execution.
SYSTEM_NUMBER	SAP system number of an SAP application server.
XMI_AUDIT_LEVEL	Sets the XMI audit level to be used for the execution of the command.

Table 3.34 HOST Options

### 3.4.3 USER Options

The USER options are required to establish an RFC connection to an SAP system. They establish the SAP user identity.

#### USER Options Syntax

Figure 3.39, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the USER options.

```
-userid userid  
-pwd password
```

Figure 3.39 USER Options Syntax

#### USER Options

Option Name	Description
USER_ID	SAP user ID with which to logon to the SAP system.
PASSWORD	Password for the SAP user ID.

Table 3.35 USER Options

## 3.4.4 CFT Options

The CFT options are used to configure a client fault tolerant job run. Client fault tolerance is requested for a USAP job run by specifying a `COMMAND_ID`.

### CFT Options Syntax

Figure 3.40, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the CFT options.

```
-cmdid id
-restart {yes|no|auto}
-autorestartok {yes|no}
-cft_secure_cft {yes|no}
-cft_abap abap_program
-cft_target_host host
-cft_cmd_prefix command_prefix
```

Figure 3.40 CFT Options Syntax

### CFT Options

Option Name	Description
<code>ALLOW_AUTO_RESTART</code>	Specification for whether or not a <b>RESTART</b> value of <b>AUTO</b> will be allowed.
<code>CFT_ABAP_PROGRAM</code>	ABAP program to use for the command ID job step.
<code>CFT_COMMAND_PREFIX</code>	In pre-XBP 2.0 CFT mode, the prefix command required for the operating system of the target host.
<code>CFT_TARGET_HOST</code>	In pre-XBP 2.0 CFT mode, the target host to use for the command ID job step when the command ID option is used.
<code>COMMAND_ID</code>	Identifier used to identify the unit of work represented by a USAP command and the associated SAP job.
<code>RESTART</code>	Specification for whether or not this execution of USAP is a restart of a previous client fault tolerant USAP command.
<code>SECURE_CFT</code>	Mode of client fault tolerance to be used for the command invocation.

Table 3.36 CFT Options



## 3.4.5 COMMAND FILE Options

The COMMAND FILE options are used to specify a file as a source of configuration options used for a command execution. The options read from a command file are processed exactly like options from any other input source.

Encrypted command files are an excellent place to store sensitive data such as user IDs and passwords. Use the Universal Encrypt utility to encrypt a plain text command file. (For information on Universal Encrypt, see the Stonebranch Solutions Utilities 4.2.0 Reference Guide.)

**Note:** All options, including required and command-specific options, can be placed in a command file.

USAP can process both plain text and encrypted command files. Either type of file can be used, but not both. If both are specified, the plain text file will be used.

### COMMAND FILE (Plain Text) Options Syntax

Figure 3.41, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the COMMAND FILE (Plain Text) options.

```
-file [filename]
```

Figure 3.41 COMMAND FILE (Plain Text) Options Syntax

### COMMAND FILE (Plain Text) Options

Option Name	Description
<code>FILE_NAME</code>	Name of a plain text command file.

Table 3.37 COMMAND FILE (Plain Text) Options

## COMMAND FILE (Encrypted) Options Syntax

Figure 3.42, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the COMMAND FILE (Encrypted) options.

```
-encryptedfile [filename [-key key] ]
```

Figure 3.42 COMMAND FILE (Encrypted) Options Syntax

## COMMAND FILE (Encrypted) Options

Option Name	Description
ENCRYPT_FILE	Name of an encrypted command file.
ENCRYPTION_KEY	Key used to encrypt the command file.

Table 3.38 COMMAND FILE (Encrypted) Options

## 3.4.6 EVENT Options

The EVENT options are required for event generation.

**Note:** EVENT options can be specified only in the configuration file. They have no command line or environment variable parameters.

### EVENT Options Syntax

Figure 3.43, below, illustrates the configuration file syntax of the EVENT options.

```
activity_monitoring {yes|no}
event_generation types
```

Figure 3.43 EVENT Options Syntax

### EVENT Options

Option Name	Description
ACTIVITY_MONITORING	Specification for whether or not product activity monitoring events are generated.
EVENT_GENERATION	Events to be generated as persistent events.

Table 3.39 EVENT Options

## 3.4.7 INFORMATIONAL Options

The INFORMATIONAL options request information pertaining to the USAP program.

### INFORMATIONAL Options Syntax

Figure 3.44, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the INFORMATIONAL options.

```
-help
-version
```

Figure 3.44 INFORMATIONAL Options Syntax

### INFORMATIONAL Options

Option Name	Description
HELP	Writes command line help.
VERSION	Writes USAP version and copyright information.

Table 3.40 INFORMATIONAL Options

## 3.4.8 INSTALLATION Options

The INSTALLATION options are required for product installation.

**Note:** INSTALLATION options can be specified only in the configuration file. They have no command line or environment variable parameters.

### INSTALLATION Options Syntax

Figure 3.45, below, illustrates the configuration file syntax of the EVENT options.

```
installation_directory directory
```

Figure 3.45 INSTALLATION Options Syntax

### INSTALLATION Options

Option Name	Description
INSTALLATION_DIRECTORY	Location in which USAP is installed.

Table 3.41 INSTALLATION Options

## 3.4.9 LOCAL Options

The LOCAL options are required for local broker registration.

### LOCAL Options Syntax

Figure 3.46, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the LOCAL options.

```
-bif_directory directory
-plf_directory directory
```

Figure 3.46 LOCAL Options Syntax

### LOCAL Options

Option Name	Description
BIF_DIRECTORY	Broker Interface File (BIF) directory where the Universal Broker interface file is located.
PLF_DIRECTORY	Program Lock File (PLF) directory where the program lock files are located.

Table 3.42 LOCAL Options

## 3.4.10 MESSAGE Options

The MESSAGE options specify different characteristics of **usap** messages.

### MESSAGE Options Syntax

Figure 3.47, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the MESSAGE options.

```
-lang language
-level {trace|audit|info|warn|error}
-trace_file_lines lines
-trace_table size,condition
```

Figure 3.47 MESSAGE Options Syntax

### MESSAGE Options

Option Name	Description
MESSAGE_LANGUAGE	Language in which messages are written.
MESSAGE_LEVEL	Level of messages to be written.
TRACE_FILE_LINES	Maximum number of lines to write to the trace file.
TRACE_TABLE	Trace table size and under what conditions it is written to a file.

Table 3.43 MESSAGE Options

## 3.4.11 RFC Options

The RFC options are always used to configure a fault tolerant RFC connection. All RFC options have default values that are used if additional values are not provided.

### RFC Options Syntax

Figure 3.48, below, illustrates the command line syntax – using the command line, long form of the configuration options – of the RFC options.

```
-rfc_logon_retry_interval interval
-rfc_logon_retry_count count
-rfc_listen_interval interval
-rfc_timeout interval
-rfc_retry_interval interval
-rfc_retry_count count
```

Figure 3.48 RFC Options Syntax

### RFC Options

Option Name	Description
LOGON_RETRY_INTERVAL	Number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.
LOGON_RETRY_COUNT	Number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.
LISTEN_INTERVAL	Number of seconds that will elapse between RFC listen calls.
TIMEOUT_INTERVAL	Number of seconds that can elapse before USAP considers an RFC call to have timed out.
RETRY_CALL_INTERVAL	Number of seconds that will elapse between a failed RFC call and the retry of that call.
SECURE_CFT	Number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.

Table 3.44 RFC Options



## 3.5 Exit Codes

The exit code of **usap** depends on the command being issued.

The following sections identify the exit codes for the various USAP commands.

**Note:** The default values listed for the exit codes are the installed (configuration file) values. These values may be different than the internal default values (see the Exit Code options in the Universal Connector 4.2.0 Reference Guide).

### 3.5.1 WAIT for JOB Exit Codes

If the WAIT for JOB command is specified, USAP will map the job's status upon completion to the user definable job exit code parameters.

[Table 3.45](#), below, illustrates this mapping; USAP default values are listed in parentheses.

Job Completion Status in SAP	Exit Code
Terminated	terminated_exit_code (8)
Finished	finished_exit_code (0)
Unknown	22
Error in USAP processing (see <a href="#">Table 3.49</a> ).	> 200

Table 3.45 UNIX Wait for Job Exit Codes

### 3.5.2 WAIT for FS JOB NETWORK Exit Codes

If the WAIT for FS JOB NETWORK command is specified, USAP will map the job network's return code pair to the user definable job network return code parameters. In this case, the exit codes are hard coded and the return code pairs used in the matching process are user definable.

[Table 3.46](#), below, illustrates this mapping; USAP default values are listed in parentheses.

Job network return code pairs used for matching	Exit Code
job_net_rc_00 (02,00;02,02)	0
job_net_rc_04 (02,02)	4
job_net_rc_08 (02,04)	8
job_net_rc_16 (07,00;04,00;02,08)	16
Error in USAP processing (see <a href="#">Table 3.49</a> ).	> 200

Table 3.46 UNIX Wait for FS Job Network Exit Codes

### 3.5.3 DISPLAY STATUS Exit Codes

If the DISPLAY STATUS command is specified, USAP will map the job's current status to the user definable job exit code parameters.

Table 3.47, below, illustrates this mapping; USAP default values are listed in parentheses.

Job Completion Status in SAP	Exit Code
Active	active_exit_code (10)
Ready	ready_exit_code (12)
Scheduled	scheduled_exit_code (14)
Released	released_exit_code (16)
Terminated	terminated_exit_code (8)
Finished	finished_exit_code (0)
Unknown	22
Error in USAP processing (see Table 3.49).	> 200

Table 3.47 UNIX DISPLAY STATUS Exit Codes

### 3.5.4 DISPLAY QSTATE Exit Codes

If the DISPLAY QSTATE command is specified, USAP will map the queue's current state to the user definable `qstate` exit code parameters.

Table 3.48, below, illustrates this mapping; USAP default values are listed in parentheses.

Queue State	Exit Code
'C' to be created	qtobecreated_exit_code (14)
' ' unprocessed	qunprocessed_exit_code (12)
'S' in background	qinbackground_exit_code (10)
'E' error	qerror_exit_code (8)
'F' finished	qfinished_exit_code (0)
Undefined	20
Error in USAP processing (see Table 3.49).	> 200

Table 3.48 UNIX Queue State Exit Codes

## 3.5.5 All Other Command Exit Codes

If USAP is not performing the WAIT for JOB, WAIT for FS JOB NETWORK, DISPLAY STATUS, or DISPLAY QSTATE command, the exit code indicates the success of the requested actions.

Table 3.49, below, lists the USAP exit codes.

Description	Exit Code
Successfully completed all requested actions.	0
An error occurred processing the requested actions. Messages are printed providing details about the error.	201
Indicates an error with product configuration options or command line options.	210
An error occurred in the initialization phase of message processing. It is possible the error prohibited messages from printing.	211

Table 3.49 USAP for UNIX - Exit Codes

# Universal Connector Job Definition Files

---

## 4.1 Overview

This chapter provides information on Universal Connector job definition files, which contain statements that specify the attributes of jobs. These job definitions are used by the SUBMIT, MODIFY, and RUN commands to define or modify jobs in an SAP system.

USAP supports several different job types. The following is a detailed description of the syntax options and requirements for each type of job definition.

## 4.2 Standard USAP Job Definition File Syntax

The standard USAP job is equivalent to defining a background job SAP via transaction SM36. There are four types of statements used to define a standard USAP job:

1. Job Header statement
2. ABAP Step statement
3. External Step statement
4. External Command Step statement

A job definition requires a Job Header statement followed by one or more ABAP Step statements. Statements are made up of keyword = value assignments and are terminated with a semi-colon ( ; ). Each statement type has a specific unique keyword that is required to start the keyword = value assignment list.

Figure 4.1, below., illustrates the syntax of a USAP standard job definition.

```
Job_Header_Statement Step_Statement [Step_Statements]
```

Figure 4.1 USAP Standard Job Definition Syntax

### 4.2.1 Keywords

The following tables list the keywords available for each statement, the maximum length of the associated values, whether or not they are required, and any restricted value sets.

The first keyword in each table is the keyword required to start the corresponding statement.

## 4.3 Keywords for Job Header Statement

Table 4.1, below, identifies the keywords for a Job Header statement.

Keyword	Length	Required	Restricted Values / Description
JOBNAME	32	Yes	
TARGET_SERVER	20	No	
JOBCOUNT	8	No	This keyword is useful only for the modify command. In all other cases, it is ignored; it will not cause a syntax error.
JOB_CLASS	1	No	A, B, C  This keyword is only valid if at least one of the following requirements is met: <ol style="list-style-type: none"> <li>1. Job definition file is being used with an SAP 46C system with support package SAPKB46C44.</li> <li>2. Job definition file is being used with an SAP 610 system with support package SAPKB61033.</li> <li>3. Job definition file is being used with an SAP 620 system with support package SAPKB62023.</li> </ol>
<b>The following keywords represent SAP job start conditions.</b>			
SDLSTRDT	8	No	YYYYMMDD
SDLSTRTM	6	No	HHMMSS
LASTSTRDT	8	No	YYYYMMDD
LASTSTRTM	6	No	HHMMSS
PREDJOB	32	No	
PREDJOBCNT	8	No	
EVENTID	32	No	
EVENTPARM	64	No	
CHECKSTAT	1	No	<ul style="list-style-type: none"> <li>• 'X' = Check job status for subsequent job start.</li> <li>• '' = Do not check job status for subsequent job start.</li> </ul>
PERIODIC	1	No	<ul style="list-style-type: none"> <li>• 'X' = Job is periodic.</li> <li>• '' = Job is not periodic.</li> </ul>
CALENDARID	2	No	
PRDMINS	2	No	00-99
PRDHOURS	2	No	00-99
PRDDAYS	3	No	00-999
PRDWEEEKS	2	No	00-99
PRDMONTHS	2	No	00-99
WDAYNO	2	No	00-99
WDAYCDIR	1	No	Work day relative to: <ul style="list-style-type: none"> <li>• '1' = Beginning of month.</li> <li>• '2' = End of month.</li> </ul>

Keyword	Length	Required	Restricted Values / Description
PRDBEHAV	1	No	Start Date Restrictions: <ul style="list-style-type: none"> <li>• ‘ ‘ = Always execute job.</li> <li>• ‘D’ = Do not execute job on Sundays or holidays.</li> <li>• ‘B’ = Move job to previous day.</li> <li>• ‘A’ = Move job to next work day.</li> </ul>
NOTBEFORE	8	No	YYMMDD
<b>The following keywords represent SAP spool list recipient.</b>			
LOGSYS	10	No	
OBJTYPE	10	No	
OBJKEY	70	No	
DESCRIBE	10	No	

Table 4.1 Job Header Keywords

## 4.4 Keywords for ABAP Step Statement

Table 4.2, below, identifies the keywords for an ABAP Step statement.

Keyword	Length	Required	Restricted Values / Description
ABAP_STEP	40	Yes	
STEP_NUMBER	8	Yes	This keyword is only required and useful for the MODIFY command. It is ignored in all other cases and will not cause a syntax error.
ABAP_PROGRAM_NAME	40	Yes	
SAP_USER_NAME	12	No	
LANGUAGE	1	No	
VARIANT_NAME	14	No	
<b>The following keywords represent SAP printing parameters.</b>			
OUTPUT_DEVICE	4	No	
PRINT_IMMEDIATELY	1	No	<ul style="list-style-type: none"> <li>'X' = Output.</li> <li>' ' = Do not output.</li> </ul>
RELEASE	1	No	<ul style="list-style-type: none"> <li>'X' = Delete after output.</li> </ul>
COPIES	3	No	
ARCHIVING_MODE	1	No	<ul style="list-style-type: none"> <li>'1' = only print the document.</li> <li>'2' = only archive the document.</li> <li>'3' = both print and archive the document.</li> </ul>
SAP_BANNER	1	No	<ul style="list-style-type: none"> <li>' ' = no cover sheet.</li> <li>'X' = output cover sheet.</li> <li>'D' = cover sheet output depends on the setting of the output device (printer) being used.</li> </ul>
BANNER_PAGE	1	No	<ul style="list-style-type: none"> <li>' ' = no cover sheet.</li> <li>'X' = output cover sheet.</li> </ul>
EXPIRATION	1	No	
RECIPIENT	12	No	
NUM_LINES	10	No	
NUM_COLUMNS	10	No	
AUTHORIZATION	12	No	
PLIST	12	No	<p>Spool Request Name</p> <p>This keyword is valid only if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
PRTXT	68	No	<p>Spoolist Title</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>



Keyword	Length	Required	Restricted Values / Description
PRNEW	1	No	<p>New Spool Request:</p> <ul style="list-style-type: none"> <li>• 'X' = Create a new spoolist for each spoolist generated.</li> <li>• '' = Append all spoolists.</li> </ul> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
PRABT	12	No	<p>Department</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
PAART	16	No	<p>Print format</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
PRDSN	6	No	<p>Spool Data Set</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
PTYPE	12	No	<p>Spool Request Type</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
FOOTL	1	No	<p>Footer:</p> <ul style="list-style-type: none"> <li>• 'X' = yes.</li> <li>• '' = no.</li> </ul> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>
<b>The following keywords represent SAP archiving parameters.</b>			
SAP_OBJECT	10	No	Object Type
AR_OBJECT	10	No	Document Type
INFO	3	No	Info Field
ARCHIV_ID	2	No	<p>Target Storage System</p> <p>This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.</p>

Keyword	Length	Required	Restricted Values / Description
DOC_TYPE	20	No	Document Class  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
RPC_HOST	32	No	RPC Host  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
RPC_SERVIC	32	No	RPC Service / RFC Destination  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
AR_INTERFACE	14	No	Communication Component  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
MANDANT	3	No	Client  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
REPORT	40	No	Report Name  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
ARCTEXT	40	No	Text Information  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
DATUM	8	No	Archiving Date  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
ARCUSER	12	No	Data Element for User  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.

Keyword	Length	Required	Restricted Values / Description
PRINTER	4	No	Target Printer  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
FORMULAR	16	No	Output Format  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
ARCHIVPATH	70	No	Standard Archive Path  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
PROTOKOLL	8	No	Storage Connection Protocol  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.
VERSION	4	No	Version Number  This keyword is only valid if the XBP 2.0 interface is installed on the target SAP system. The XBP 2.0 interface will be used if present.

Table 4.2 ABAP Step Keywords

## 4.5 Keywords for External Step Statement

Table 4.3, below, identifies the keywords for an External Step statement.

Keyword	Length	Required	Restricted Values / Description
EXTERNAL_STEP	40	Yes	
STEP_NUMBER	8	Yes	This keyword is required (and useful) only for the Modify command. In all other cases, it is ignored and will not cause a syntax error.
PROGRAM_NAME	128	Yes	
PROGRAM_PARAMETERS	255	No	
SAP_USER_NAME	12	No	
TARGET_HOST	32	Yes	
WAIT_FOR_TERMINATION	1	No	<ul style="list-style-type: none"> <li>' ' or 'W' = Don't wait.</li> <li>'X' or 'C' = Wait.</li> <li>'E' = The external program signals its time limitation over a Event to the SAP system.</li> </ul>
CONNCNTL	1	No	<ul style="list-style-type: none"> <li>'R' = Communication way is held after starting the external program.</li> <li>'H' = Communication way is diminished after starting the external program.</li> </ul>
STDINCNTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard input closes.</li> <li>'R' = Return standard input.</li> </ul>
STDOUTCNTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard output expenditure closes.</li> <li>'R' = Return standard output expenditure.</li> <li>'T' = Return standard output into the trace file.</li> <li>'M' = Write standard output expenditure into main storage.</li> </ul>
STDERRCNTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard error expenditure closes.</li> <li>'R' = Return standard error expenditure.</li> <li>'M' = Write standard error expenditure into main storage.</li> </ul>
TRACECNTL	1	No	<ul style="list-style-type: none"> <li>'0' = Level 0, no trace.</li> <li>'1' = Level 1, function call trace.</li> <li>'2' = Level 2, minutes trace.</li> <li>'3' = Level 3, expression of all messages.</li> </ul>

Table 4.3 External Step Keywords

## 4.6 Keywords for External Command Step Statement

Table 4.4, below, identifies the keywords for an External Command Step statement.

Keyword	Length	Required	Restricted Values / Description
COMMAND_STEP	40	Yes	
STEP_NUMBER	8	Yes	This keyword is required (and useful) only for the Modify command. In all other cases, it is ignored and will not cause a syntax error.
COMMAND_NAME	128	Yes	
COMMAND_PARAMETERS	255	No	
SAP_USER_NAME	12	No	
TARGET_HOST	32	Yes	
OPSYSTEM	10	Yes	
WAIT_FOR_TERMINATION	1	No	<ul style="list-style-type: none"> <li>' ' or 'W' = Don't wait.</li> <li>'X' or 'C' = Wait.</li> <li>'E' = The external program signals its time limitation over a Event to the SAP system.</li> </ul>
CONNCTL	1	No	<ul style="list-style-type: none"> <li>'R' = Communication way is held after starting the external program.</li> <li>'H' = Communication way is diminished after starting the external program.</li> </ul>
STDINCTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard input closes.</li> <li>'R' = Return standard input.</li> </ul>
STDOUTCTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard output expenditure closes.</li> <li>'R' = Return standard output expenditure.</li> <li>'T' = Return standard output into the trace file.</li> <li>'M' = Write standard output expenditure into main storage.</li> </ul>
STDERRCTL	1	No	<ul style="list-style-type: none"> <li>'N' = No change.</li> <li>'C' = Standard error expenditure closes.</li> <li>'R' = Return standard error expenditure.</li> <li>'M' = Write standard error expenditure into main storage.</li> </ul>
TRACECTL	1	No	<ul style="list-style-type: none"> <li>'0' = Level 0, no trace.</li> <li>'1' = Level 1, function call trace.</li> <li>'2' = Level 2, minutes trace.</li> <li>'3' = Level 3, expression of all messages.</li> </ul>

Table 4.4 External Command Step Keywords

## 4.7 Sample USAP Job Definition File

Figure 4.2, below, illustrates a sample job definition file that defines a job with 1 ABAP step running ABAP report BTCSPool.

```
/* Job Header statement */
JOBNAME                = "SAMPLE_1"
  JOB_CLASS             = "B"
;

/* ABAP_STEP Step statement */
ABAP_STEP              = "1"
  ABAP_PROGRAM_NAME    = "BTCSPool"
  PRTXT                = "Sample 1"
  PRNEW                = "X"
;
```

Figure 4.2 USAP Job Definition File

## 4.8 Variant Definition File

USAP variant definition files contains statements that specify the attributes of variants. These variant definitions are used by the SUBMIT and MODIFY commands to define or modify variants in an SAP system. The following is a detailed description of the syntax options and requirements for variant definition files.

### 4.8.1 Variant Definition File Syntax

The USAP variant definition file is used to create or modify a variant in an SAP system. There are three types of statements used to define a variant:

1. Variant Header Statement
2. Variant Text Statement
3. Variant Content Statement

A variant definition requires a Variant Header statement followed by Text and Content statements. Statements are made up of keyword = value assignments and are terminated with a semi-colon (;). Each statement type has a specific unique keyword that is required to start the keyword = value assignment list.

Figure 4.3, below, illustrates the syntax of a USAP variant definition.

```
Variant_Header_Statement Variant_Text_Statement Variant_Content_Statement  
[Variant_Content_Statements]
```

Figure 4.3 USAP Variant Definition Syntax

## 4.8.2 Keywords

The following tables list the keywords available for each statement, the maximum length of the associated values, whether or not they are required, and any restricted value sets. The first keyword in each table is the keyword required to start the corresponding statement.

### Keywords for Variant Header Statement

Table 4.5, below, identifies the keywords for a Variant Header statement.

Keyword	Length	Required	Restricted Values
VARIANT_NAME	14	Yes	Variant name.
REPORT	40	Yes	ABAP report for which variant is defined.

Table 4.5 Variant Header Keywords

### Keywords for Variant Text Statement

Table 4.6, below, identifies the keywords for a Variant Text statement.

Keyword	Length	Required	Restricted Values
VARIANT_TEXT	30	Yes	
LANGUAGE	2	Yes	

Table 4.6 Variant Text Step Keywords



## Keywords for Variant Content Statement

Table 4.7, below, identifies the keywords for a Variant Content statement.

Keyword	Length	Required	Restricted values
SELNAME	8	Yes	
KIND	1	Yes	Field type: <ul style="list-style-type: none"> <li>'P' = Field type is a parameter.</li> <li>'S' = Field type is a selection option.</li> </ul>
SIGN	1	Yes	Selection sign: <ul style="list-style-type: none"> <li>'I' = Include values based on field selection criteria.</li> <li>'E' = Exclude values based on field selection criteria.</li> </ul>
OPTION	2	Yes	Selection option: <ul style="list-style-type: none"> <li>'CP' = Pattern.</li> <li>'EQ' = Single value.</li> <li>'GE' = Greater than or equal to.</li> <li>'LE' = Less than or equal to.</li> <li>'GT' = Greater than.</li> <li>'LT' = Less than.</li> <li>'NE' = Not equal to.</li> </ul>
LOW	45	No	Selection value.
HIGH	45	No	Selection value.
PROTECTED	1	No	<ul style="list-style-type: none"> <li>'X' = Field is protected.</li> <li>' ' = Field is not protected.</li> </ul>
APPENDAGE	1	No	<ul style="list-style-type: none"> <li>'X' = Appendage.</li> <li>' ' = Not appendage.</li> </ul>
VNAME	30	No	Name of variant variable.
VTTYPE	1	No	Variant variable type: <ul style="list-style-type: none"> <li>'T' = Table variable from TVARV.</li> <li>'D' = Dynamic date calculation.</li> <li>'B' = User defined variables.</li> </ul>
INVISIBLE	1	No	Hide field: <ul style="list-style-type: none"> <li>'X' = Invisible.</li> <li>' ' = Not invisible.</li> </ul>
NOINT	1	No	Hide field 'BIS': <ul style="list-style-type: none"> <li>'X' = Invisible.</li> <li>' ' = Not invisible.</li> </ul>
SCREENNR	4	No	Screen number.
NO_IMPORT	1	No	Save field without values: <ul style="list-style-type: none"> <li>'X' = Yes</li> <li>' ' = No</li> </ul>
OBLI	1	No	Required field: <ul style="list-style-type: none"> <li>'X' = Yes</li> <li>' ' = No</li> </ul>

Table 4.7 Variant Content Step Keywords

### 4.8.3 Sample Variant Definition File

Figure 4.4, below, illustrates a sample variant definition file.

This file will define variant **SAMPLE\_1** for ABAP report **RSUSR002**. The **USER** field will contain value **S\***.

```
/* Variant Header statement. */
VARIANT_NAME   = "SAMPLE_1"
  REPORT       = "RSUSR002"
;

/* Variant text statement. */
VARIANT_TEXT   = "SAMPLE_1"
  LANGUAGE     = "EN"
;

/* User */
SELNAME        = "USER"
  KIND         = "S"
  SIGN        = "I"
  OPTION      = "CP"
  LOW         = "S*"
  HIGH        = ""
  PROTECTED   = ""
  APPENDAGE   = ""
  VNAME       = ""
  VTYPE       = ""
  INVISIBLE   = ""
  SCREENNR    = ""
  NO_IMPORT   = ""
  SPAGPA      = ""
  OBLI        = ""
  NOINT       = ""
;
```

Figure 4.4 Variant Definition File (Sample)

## 4.9 Job Intercept Table Definition File

USAP job intercept table definition files contains statements that specify criteria rows. These definitions are used by the SUBMIT command to replace or append the job intercept table in an SAP system.

The following is a detailed description of the syntax options and requirements for job intercept table definition files.

### 4.9.1 Job Intercept Table Definition File Syntax

The USAP job intercept table definition file is used to replace or append the job intercept in an SAP system.

There are two types of statements used to define a job intercept table:

1. Job Intercept Table Header Statement
2. Job Intercept Table Row Statement

A job intercept table definition requires a Header statement followed by row statements. Statements are made up of keyword = value assignments and are terminated with a semi-colon (;). Each statement type has a specific unique keyword that is required to start the keyword = value assignment list.

Figure 4.5, below, illustrates the syntax of a USAP job intercept table definition.

```
Job_Intercept_Table_Header_Statement [Job_Intercept_Table_Row_Statements]
```

Figure 4.5 USAP Job Intercept Table Definition Syntax

## 4.9.2 Keywords

The following tables list the keywords available for each statement, the maximum length of the associated values, whether or not they are required, and any restricted value sets. The first keyword in each table is the keyword required to start the corresponding statement.

### Keywords for Job Intercept Table Header Statement

Table 4.8, below, identifies the keywords for a Job Intercept Table Header statement.

Keyword	Length	Required	Restricted values
INTERCEPT_TABLE	1024	Yes	Table name **This value is only used internally by USAP. It does not effect the SAP table definition.
APPEND	1	Yes	<ul style="list-style-type: none"> <li>'X' = Append.</li> <li>' ' = Replace.</li> </ul>

Table 4.8 Job Intercept Table Header Keywords

### Keywords for Job Intercept Table Row Statement

Table 4.9, below, identifies the keywords for a Job Intercept Table Row statement.

Keyword	Length	Required	Restricted Values
INTERCEPT_ROW	1024	Yes	Row name **This value is only used internally by USAP. It does not effect the SAP table definition.
CLIENT	3	No	
JOB_NAME	32	No	
JOB_CREATOR	12	No	

Table 4.9 Job Intercept Row Step Keywords

### 4.9.3 Sample Job Intercept Table Definition File

Figure 4.6, below, illustrates a sample job intercept table definition file.

The file will append 4 rows to the SAP job intercept criteria table.

```
/* Job Intercept Table Header statement */
INTERCEPT_TABLE      = "TABLE_1"
  APPEND                = "X"
;

/* Job Intercept Row statement */
INTERCEPT_ROW        = "1"
  CLIENT                = "850"
  JOB_NAME              = "TEST*"
  JOB_CREATOR           = "stonebranch"
;

/* Job Intercept Row statement */
INTERCEPT_ROW        = "2"
  CLIENT                = "850"
  JOB_NAME              = "TST*"
  JOB_CREATOR           = "stonebranch"
;

/* Job Intercept Row statement */
INTERCEPT_ROW        = "3"
  CLIENT                = "850"
  JOB_NAME              = "DEV*"
  JOB_CREATOR           = "stonebranch"
;

/* Job Intercept Row statement */
INTERCEPT_ROW        = "4"
  CLIENT                = "*"
  JOB_NAME              = "*"
  JOB_CREATOR           = "BOB"
;
```

Figure 4.6 Job Intercept Table Definition File (Sample)

## 4.10 FS Job Network Definition File

USAP FS job network definition files contains statements that specify the attributes of FS job networks. These variant definitions are used by the SUBMIT, START, and RUN commands to define and start FS job networks in an SAP system.

The following is a detailed description of the syntax options and requirements for FS job network definition files.

### 4.10.1 FS Job Network Definition File Syntax

The USAP FS job network definition file is used to create an FS job network in an SAP system.

There are three types of statements used to define an FS job network:

1. FS Jobnet Header statement.
2. FS Jobnet Process statement.
3. FS Jobnet Process Relation statement.

An FS jobnet definition requires an FS Jobnet Header statement followed by FS Jobnet Process Statements, then FS Jobnet Process Relation statements. Statements are made up of keyword = value assignments and are terminated with a semi-colon ( ; ). Each statement type has a specific unique keyword that is required to start the keyword = value assignment list.

[Figure 4.7](#), below, illustrates the syntax of a USAP FS Job Network definition.

```
FS_Jobnet_Header FS_Jobnet_Process [FS_Jobnet_Process]  
FS_Jobnet_Process_Relation [FS_Jobnet_Process_Relation]
```

Figure 4.7 USAP FS Jobnet Definition Syntax

## 4.10.2 Keywords

The following tables list the keywords available for each statement, the maximum length of the associated values, whether or not they are required, and any restricted value sets.

The first keyword in each table is the keyword required to start the corresponding statement.

### Keywords for FS Jobnet Header Statement

Table 4.10, below, identifies the keywords for an FS Jobnet Header statement.

Keyword	Length	Required	Restricted Values
NETWORKIDENTIFIER	50	Yes	Network identifier.

Table 4.10 FS Jobnet Header Keywords

### Keywords for FS Jobnet Process Statement

Table 4.11, below, identifies the keywords for an FS Jobnet Process statement.

Keyword	Length	Required	Restricted Values
PROCESS_IDENTIFIER	50	Yes	Process identifier.
REPORT_NUMBER	3	Yes	Report number: 001-999
REPORT_NAME	40	Yes	Report name.
REPORT_VARIANT	14	No	Report variant.
JOBNAME	32	Yes	Job name.

Table 4.11 FS Jobnet Process Step Keywords

## Keywords for FS Jobnet Process Relation Statement

Table 4.12, below, identifies the keywords for an FS Jobnet Process Relation statement.

Keyword	Length	Required	Restricted Values
PROCESS_RELATION	3	Yes	Process relation number: 001-999.
REPORT_NUMBER_PREDECESSOR	3	Yes	Report number predecessor: 001-999.
REPORT_NUMBER_SUCCESOR	3	Yes	Report number successor: 001-999.

Table 4.12 FS Jobnet Process Relation Step Keywords



## Sample FS Job Network Definition File

Figure 4.8, below, illustrates a sample FS job network definition file.

```
/******  
**  
** Sample FS Job Network definition file for USAP for  
** SAP  
**  
** Demonstrates creation of a multi-process jobnet.  
**  
***/  
  
/* Jobnet Header statement */  
NETWORKIDENTIFIER          = "SB-NETID_01";  
  
/* Add Jobnet Process statements */  
PROCESS_IDENTIFIER         = "SB-PRC_01"  
    REPORT_NUMBER           = "001"  
    REPORT_NAME             = "Z_TEST_NETWORK"  
    REPORT_VARIANT          = "RC_00"  
    JOBNAME                 = "SB-Z_TEST_NETWORK"  
    ;  
  
PROCESS_IDENTIFIER         = "SB-PRC_02"  
    REPORT_NUMBER           = "002"  
    REPORT_NAME             = "RSUSR000"  
    JOBNAME                 = "SB-RSUSR000"  
    ;
```

```
PROCESS_IDENTIFIER      = "SB-PRC_03"
  REPORT_NUMBER         = "003"
  REPORT_NAME           = "BTCSPool"
  JOBNAME               = "SB-BTCSPool"
;

/* Add Jobnet Process Relations statements. */
PROCESS_RELATION       = "1"
  REPORT_NUMBER_PREDECESSOR = "001"
  REPORT_NUMBER_SUCESSOR   = "002"
;

PROCESS_RELATION       = "2"
  REPORT_NUMBER_PREDECESSOR = "002"
  REPORT_NUMBER_SUCESSOR   = "003"
;
```

Figure 4.8 FS Job Network Definition File (Sample)

## 4.1.1 Spoolist Translation Tables

USAP returns spoolists in a raw (SAP internal) format. This raw format contains all of the formatting control codes that the SAP system needs to display or print the spoolist. In most cases, this raw format will not be desirable. Therefore, USAP provides the ability to translate the raw spoolist into a desirable format. The translation is performed using a user definable translation table. Multiple translation tables can be defined to achieve different formatting results. The required translation table can be specified at run time.

On UNIX systems, the Spoolist Translation (STT) files are located in the NLS subdirectory of the installation directory.

### z/OS

The STT files are located in the library allocated to the UNVNLS DD statement.

USAP ships with two Spoolist Translation files: `default.stt` and `raw.stt`. The default Spoolist Translation Table file is `default`. This translation table contains translations for the standard SAP formatting codes to appropriate character representations. The `raw` translation table defines no translations and allows USAP to return the spoolist in its SAP internal format.

### 4.1.1.1 Spoolist Translation Table File Format

The Spoolist Translation Table files consist of three white space-separated columns.

#### Column 1

This is a compare string to look for in the raw unformatted spoolist. This compare string is built by combining comma delimited values. The values are combined to make up the actual compare string. The values can be quoted strings, hexadecimal values representing characters, or decimal values representing characters.

**Note:** Spaces cannot be used to separate values in the comma delimited list.

#### Column 2

This is a replace string that will be used to replace the compare string in the raw unformatted spoolist. This replace string is built from comma delimited values. The values are combined to make up the actual replace string. The values can be quoted strings, hexadecimal values representing characters, or decimal values representing characters.

**Note:** Spaces cannot be used to separate values in the comma delimited list.

#### Column 3

This is a single decimal value used to restrict the comparison to a specific starting column. A value is not required in this column. If no value is specified in this column, the compare string will be replaced in every location that it is found.

# Universal Connector Configuration Options

---

## 5.1 Overview

This chapter provides detailed information for all Universal Connector configuration options.

The options are listed alphabetically, without regard to any specific operating system.

Section [5.2 Configuration Options Information](#) provides a guideline for understanding the information presented for each option.

## 5.2 Configuration Options Information

For each configuration option, this chapter provides the following information.

### Description

---

Describes the configuration option and how it is used.

### Usage

---

Provides a table of the following information:

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<Format / Value>					
Command Line, Long Form	<Format / Value>					
Environment Variable	<Format / Value>					
Configuration File Keyword	<Format / Value>					

### Method

Identifies the different methods used to specify Universal Connector configuration options:

- Command Line Option, Short Form
- Command Line Option, Long Form
- Environment Variable
- Configuration File Keyword

**Note:** Each option can be specified using one or more methods.

---

## Syntax

Identifies the syntax of each method that can be used to specify the option:

- **Format** Specific characters that identify the option.
- **Value** Type of value(s) to be supplied for this method.

**Note:** If a Method is not valid for specifying the option, the Syntax field contains **n/a**.

## (Operating System)

Identifies (with a ✓) the operating systems for which each method of specifying the option is valid:

- IBM i
- NonStop (HP NonStop)
- UNIX
- Windows
- z/OS

---

## Values

Identifies all possible values for the specified value type.

Defaults are identified in **[bracketed bold type]**.

---

## <Additional Information>

Identifies any additional information specific to the option.

## 5.3 Configuration Options List

[Table 5.1](#), below, identifies all Universal Connector configuration options.

The **Page** column provides a link to detailed information about each option.

Option	Description	Page
ABAP_NAME	Name of an ABAP program in an SAP system.	<a href="#">196</a>
ACTIVITY_MONITORING	Specification for whether or not product activity monitoring events are generated.	<a href="#">197</a>
ALLOW_AUTO_RESTART	Specification for whether or not a RESTART value of <b>AUTO</b> will be allowed.	<a href="#">198</a>
AS_HOST	Host name of an SAP application server.	<a href="#">199</a>
BATCH_MONITOR	Causes USAP to perform batch input monitoring for the job being started.	<a href="#">200</a>
BIF_DIRECTORY	Broker Interface Directory that specifies the location of the Universal Broker interface file.	<a href="#">201</a>
CFT_ABAP_PROGRAM	ABAP program to use for the command ID job step.	<a href="#">202</a>
CFT_COMMAND_PREFIX	In pre-XBP 2.0 CFT mode, the prefix command required for the operating system of the target host.	<a href="#">203</a>
CFT_TARGET_HOST	In pre-XBP 2.0 CFT mode, the target host to use for the command ID job step when the command ID option is used.	<a href="#">204</a>
CLIENT	SAP client number.	<a href="#">205</a>
COMMAND_ID	Identifier used to identify the unit of work represented by a USAP command and the associated SAP job.	<a href="#">206</a>
DESTINATION	Name of a destination defined in the <code>saprfc.ini</code> file.	<a href="#">207</a>
DISPLAY_CLIENT	Identify a specific SAP client whose intercepted jobs will be reported.	<a href="#">208</a>
ENCRYPT_FILE	Name of an encrypted text command file.	<a href="#">209</a>
ENCRYPTION_KEY	Key used to encrypt the command file.	<a href="#">210</a>
EVENT_GENERATION	Events to be generated as persistent events.	<a href="#">211</a>
EVENT_ID	Name of the event.	<a href="#">213</a>
EVENT_PARAMETER	Optional parameter value for the event.	<a href="#">214</a>
EXIT_JOB_ACTIVE	USAP exit code for the SAP job <b>active</b> status.	<a href="#">215</a>
EXIT_JOB_FINISHED	USAP exit code for the SAP job <b>finished</b> status.	<a href="#">216</a>
EXIT_JOB_READY	USAP exit code for the SAP job <b>ready</b> status.	<a href="#">217</a>
EXIT_JOB_RELEASED	USAP exit code for the SAP job <b>released</b> status.	<a href="#">218</a>
EXIT_JOB_SCHEDULED	USAP exit code for the SAP job <b>scheduled</b> status.	<a href="#">219</a>
EXIT_JOB_TERMINATED	USAP exit code for the SAP job <b>terminated</b> status.	<a href="#">220</a>
EXIT_QUEUE_BACKGROUND	USAP exit code for the SAP queue state <b>S</b> (in background).	<a href="#">221</a>
EXIT_QUEUE_CREATED	USAP exit code for the SAP queue state <b>C</b> (to be created).	<a href="#">222</a>
EXIT_QUEUE_ERROR	USAP exit code for the SAP queue state <b>E</b> (error).	<a href="#">223</a>

Option	Description	Page
EXIT_QUEUE_FINISHED	USAP exit code for the SAP queue state F (finished).	224
EXIT_QUEUE_UNPROCESSED	USAP exit code for the SAP queue state [ ] (unprocessed).	225
EXTERNAL_COMMAND	Complete command name or a mask used to select SAP external commands that match the mask.	226
FILE_NAME	Name of a plain text command file.	227
FROM_DATE	Earliest date to use for job selection or syslog request.	228
FROM_TIME	Earliest time to use for job selection or syslog request.	229
HELP	Writes command line help.	230
IMMEDIATE_JOB	Causes the job to be started immediately.	231
INSTALLATION_DIRECTORY	Location in which USAP is installed.	232
JOB_ID	Job ID of an existing SAP job.	233
JOB_ID_PATTERN	Locates the header record and determines the offset of the job ID in the RSBDCSUB batch input processing report.	234
JOB_LOG_CHILD	Controls the writing of job logs for child jobs.	235
JOB_NAME	Name of an existing SAP job.	236
JOB_NAME_PATTERN	Locates the header record and determines the offset of the job name in the RSBDCSUB batch input processing report.	237
JOB_NETWORK_ID	Network identifier for the pre-existing SAP FS job network being started.	238
JOB_PROCESS_ID	Process ID of an existing SAP FS job network process to start.	239
LAYOUT_NAME	Complete layout name or a mask used to select printer layouts that match the mask.	240
LISTEN_INTERVAL	Number of seconds that will elapse between RFC listen calls.	241
LOGON_LANGUAGE	SAP logon language used for the USAP session.	242
LOGON_RETRY_COUNT	Number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.	243
LOGON_RETRY_INTERVAL	Number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.	244
LONG_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.	245
MASS_ACTIVITY_WAIT	Causes USAP to wait for the SAP mass activity jobs to complete processing.	246
MAX_CHILD_DEPTH	Controls the maximum relationship depth that will be monitored by USAP.	247
MAX_HIT_COUNT	Maximum number of ABAP reports to be returned.	248
MAX_JOB_LOG_SIZE	Maximum size for job logs.	249
MAX_SPOOL_LIST_SIZE	Maximum size for spool lists.	250



Option	Description	Page
MAX_XBP	Maximum version of the SAP XBP interface that will be used during USAP execution.	251
MESSAGE_LANGUAGE	Language in which messages are written.	252
MESSAGE_LEVEL	Level of messages to written.	253
NO_START_DATE	Specification for whether or not to include jobs with no start date in selection criteria.	254
OPERATING_SYSTEM	Name of the operating system for which external commands are searched.	255
OUTPUT_FIELD_LIST	Additional fields to write for the <b>select</b> command.	256
PAGE_LIMIT	Maximum number of pages that can be returned in the syslog report.	258
PASSWORD	Password for the SAP user ID.	259
PLF_DIRECTORY	Program Lock File directory that specifies the location of the USAP program lock file.	260
PRINTER_NAME	Name of a printer for which the print formats will be retrieved.	261
PURGE_BDC_MAP	Specification for whether or not to delete BDC Batch input session queues that have been processed successfully.	262
PURGE_CHILD_JOBS	Controls the purging of child jobs.	263
PURGE_JOB	Purge job that has completed processing from SAP system.	264
QUEUE_ID	Queue identifier associated with the batch input session.	265
QUEUE_ID_PATTERN	Locates the header record and determines the offset of the queue ID in the RSBDCSUB batch input processing report.	266
RESTART	Specification for whether or not this execution of USAP is a restart of a previous client fault tolerant USAP command.	267
RETRY_CALL_COUNT	Number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.	269
RETRY_CALL_INTERVAL	Number of seconds that will elapse between a failed RFC call and the retry of that call.	270
RETURN_APPLICATION_LOG	Specification for whether or not the job's application log is returned.	271
RETURN_APPLICATION_RC	Specification for whether or not the job's application return codes are returned.	272
RETURN_JOB_LOG	Specification for whether or not the job's job log is returned.	273
RETURN_SPOOL_LIST	Specification for whether or not the spoolists of all job steps are returned.	274
SECURE_CFT	Mode of client fault tolerance to be used for the command invocation.	275
SERVER_STOP_CONDITIONS	Exit code(s) of the executing Universal Connector process that should trigger the locally running Universal Broker to cancel the corresponding SAP job.	276

Option	Description	Page
SPOOL_CODEPAGE	Codepage to be used for transferring spool lists from the SAP system.	277
SPOOL_LIST_CHILD	Controls the printing of spoolists for child jobs.	278
START_JOB	Starts the newly defined job.	279
STATUS_ABORTED	Specification for whether or not to include jobs with status aborted in selection criteria.	280
STATUS_CHECK_INTERVAL	Length of time that can elapse, without a change in job status, before a call will be made to synchronize the actual job status with the SAP stored status.	281
STATUS_FINISHED	Specification for whether or not to include jobs with status finished in selection criteria.	282
STATUS_READY	Specification for whether or not to include jobs with status ready in selection criteria.	283
STATUS_RELEASED	Specification for whether or not to include jobs with status released in selection criteria.	284
STATUS_RUNNING	Specification for whether or not to include jobs with status running in selection criteria.	285
STATUS_SCHEDULED	Specification for whether or not to include jobs with status scheduled in selection criteria.	286
STEP_NUMBER	Step number of the SAP job step.	287
SYSLOG	Requests entries from an SAP System syslog for a specified date and time range.	288
SYSLOG_POST_TIME	Length of time to add to the job end time when calculating the <b>to</b> time for the syslog report.	289
SYSLOG_PRE_TIME	Length of time to subtract from the job release time when calculating the <b>from</b> time for the syslog report.	290
SYSTEM_ID	Local Universal Broker with which USAP must register before the Manager performs any request.	291
SYSTEM_NUMBER	SAP system number of an SAP application server.	292
TARGET_JOB_NAME	Name to give the newly created job.	293
TARGET_SERVER	Server on which the job will run.	294
TARGET_VARIANT	One or more replacement variants for ABAP program job steps in an SAP job.	295
TECHNICAL_DEVICE_NAME	Complete device name or a mask used to select SAP output devices that match the mask.	296
TIMEOUT_INTERVAL	Number of seconds that can elapse before USAP considers an RFC call to have timed out.	297
TO_DATE	Latest date to use for job selection or syslog request.	298
TO_TIME	Latest time to use for job selection or syslog request.	299
TRACE_DIRECTORY	Directory where RFC trace files will be written.	300
TRACE_FILE_LINES	Maximum number of lines to write to the trace file.	301
TRACE_TABLE	Trace table size and under what conditions it is written to a file.	302

Option	Description	Page
TRANSLATION_TABLE	Spoolist translation table file to use for formatting returned spoolists.	304
USAP_POLL	Length of time to wait between job status calls to the SAP system.	305
USE_APPLICATION_RC	Specification for whether or not the job's application return codes are used to determine the exit code of the Universal Connector job.	306
USER_ID	SAP user ID with which to logon to the SAP system.	307
USER_NAME	User ID associated with a job.	308
VARIANT	Pre-existing SAP variant name to use as the model variant.	309
VARIANT_LANGUAGE	Preferred language in which to return the variant description.	310
VARIANT_SELECTION	Specification to display either variants available for batch and dialog mode or variants available only for batch mode.	311
VERSION	Writes USAP version and copyright information.	312
WAIT	Wait for the SAP job to complete processing.	313
WAIT_FOR_CHILD_JOBS	Controls the monitoring of child jobs.	314
WITH_PREDECESSOR	Specification for whether or not to include jobs with start after predecessor in selection criteria.	315
XMI_AUDIT_LEVEL	Sets the XMI audit level to be used for the execution of the command.	316

Table 5.1 Universal Connector - Configuration Options

## 5.4 ABAP\_NAME

### Description

The ABAP\_NAME option specifies the name of an ABAP program in an SAP system.

**Note:** For the DISPLAY\_REPORTS command, ABAP\_NAME is either a complete ABAP name or a mask used to select SAP ABAP reports that match the mask. A mask contains an asterisk ( \* ) to represent 0 or more characters of an ABAP name.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-a <i>abapname</i>			√		√
Command Line, Long Form	-abapname <i>abapname</i>			√		√
Environment Variable	USAPABAPNAME= <i>abapname</i>			√		
Configuration File Keyword	n/a					

### Value

*abapname* is the name of an ABAP program.

**Note:** For the GENERATE VARIANT DEFINITION FILE command, *abapname* is the name of an ABAP program in an SAP system to which the model variant belongs.

## 5.5 ACTIVITY\_MONITORING

### Description

The ACTIVITY\_MONITORING option specifies whether or not product activity monitoring events are generated.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	n/a					
Environment Variable	n/a					
Configuration File Keyword	activity_monitoring <i>option</i>			√		√

### Values

*option* is the specification for whether or not product activity monitoring events are generated.

Valid values for *option* are:

- **yes**  
Activate product activity monitoring events
- **no**  
Deactivate product activity monitoring events

**[Default is yes).]**

## 5.6 ALLOW\_AUTO\_RESTART

### Description

The ALLOW\_AUTO\_RESTART option specifies whether or not a [RESTART](#) option value of *AUTO* will be allowed.

ALLOW\_AUTO\_RESTART is intended to provide some protection from the incorrect use of the RESTART AUTO option. The idea is that when ALLOW\_AUTO\_RESTART is set to NO in the configuration file, it takes a conscious effort to override the option for a given command.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-autorestartok <i>option</i>			√		√
Environment Variable	USAPAUTORESTARTOK= <i>option</i>			√		
Configuration File Keyword	auto_restart_ok <i>option</i>			√		√

### Value

*option* is the specification for whether or not a [RESTART](#) option value of *AUTO* will be allowed.

Valid values for *option* are:

- **yes**  
USAP is restarting an existing unit of work represented by a command ID.  
The [COMMAND\\_ID](#) and client fault tolerant (CFT) options are required.
- **no**  
USAP is not restarting.

**[Default is no.]**

## 5.7 AS\_HOST

### Description

The AS\_HOST option specifies the host name of an SAP application server.

AS\_HOST, in conjunction with the [SYSTEM\\_NUMBER](#) option, can be used instead of the [DESTINATION](#) option to define a connection to an SAP system.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ashost <i>hostname</i>			√		√
Environment Variable	USAPASHOST <i>hostname</i>			√		
Configuration File Keyword	ashost <i>hostname</i>			√		√

### Value

*hostname* is the host name of an SAP application server.

## 5.8 BATCH\_MONITOR

### Description

The BATCH\_MONITOR option causes USAP to perform batch input monitoring for the job specified by **JOB\_NAME** and **JOB\_ID**.

Note: This requires that the job being started is a single step job executing ABAP program RSBDCSUB.

USAP will wait for the job to complete.

- If the job completes unsuccessfully, USAP will exit with USAP **terminated** job status exit code.
- If the job completes successfully, USAP will retrieve the spoolist generated by RSBDCSUB.
  - If RSBDCSUB does not select any sessions for processing, USAP will issue a warning message and end with exit code 4.
  - If RSBDCSUB selects sessions for processing, USAP extracts the session processing information from the RSBDCSUB spoolist and begins monitoring all session processing jobs kicked off by RSBDCSUB.

As each session processing job completes, USAP retrieves the state of the corresponding queue and converts it to a USAP queue state exit code. When all session processing jobs have completed, USAP prints a completion status message to standard out and exits with the highest USAP queue state exit code retrieved.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-bdcwait			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

(There are no values used with this option.)



## 5.9 BIF\_DIRECTORY

### Description

---

The BIF\_DIRECTORY option specifies the Broker Interface File (BIF) directory where the Universal Broker interface file, `ubroker.bif`, is located.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	<code>-bif_directory directory</code>			✓		
Environment Variable	<code>USAPBIFDIRECTORY=directory</code>			✓		
Configuration File Keyword	n/a					

### Values

---

*directory* is the name of the BIF directory.

**[Default is `/var/opt/universa1.`]**

## 5.10 CFT\_ABAP\_PROGRAM

### Description

The CFT\_ABAP\_PROGRAM option specifies the ABAP program to use for the command ID job step.

CFT\_ABAP\_PROGRAM applies only when the secure CFT mode is used (see the [SECURE\\_CFT](#) option). It is ignored otherwise.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cft_abap <i>program</i>			✓		✓
Environment Variable	USAP_CFT_ABAP= <i>program</i>			✓		
Configuration File Keyword	cft_abap <i>program</i>			✓		✓

### Value

*program* is the ABAP program to use for the command ID job step.

**[Default is *BTCTEST*.]**

## 5.11 CFT\_COMMAND\_PREFIX

### Description

The CFT\_COMMAND\_PREFIX option specifies (in pre-XBP 2.0 CFT mode only) the command prefix required for the operating system of the target host.

CFT\_COMMAND\_PREFIX is used with (and only applies to) the [COMMAND\\_ID](#) option.

If the pre-XBP 2.0 CFT mode is not used, CFT\_COMMAND\_PREFIX is ignored.

See Section 2.3.2.2 Client Fault Tolerance Command Prefix for additional information.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cft_cmd_prefix <i>prefix</i>			✓		✓
Environment Variable	USAP_CFT_CMD_PREFIX <i>host</i>			✓		
Configuration File Keyword	cft_cmd_prefix <i>prefix</i>			✓		✓

### Value

*prefix* is the target host to use for the command ID job step when the command ID option is used.

**[Default is "cmd/C".]**

## 5.12 CFT\_TARGET\_HOST

### Description

The CFT\_TARGET\_HOST option specifies (in pre-XBP 2.0 CFT mode only) the target host to use for the command ID job step when the command ID option is used.

If the pre-XBP 2.0 CFT mode is not used, CFT\_TARGET\_HOST is ignored (see [SECURE\\_CFT](#)).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cft_target_host <i>host</i>			✓		✓
Environment Variable	USAP_CFT_TARGET_HOST <i>host</i>			✓		
Configuration File Keyword	cft_target_host <i>host</i>			✓		✓

### Value

*host* is the target host to use for the command ID job step when the command ID option is used.

## 5.13 CLIENT

### Description

---

The CLIENT option specifies the SAP client number.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-c <i>client</i></code>			√		√
Command Line, Long Form	<code>-client <i>client</i></code>			√		√
Environment Variable	<code>USAPCLIENT=<i>client</i></code>			√		
Configuration File Keyword	<code>client <i>client</i></code>			√		√

### Value

---

*client* is the SAP client number.

## 5.14 COMMAND\_ID

### Description

The `COMMAND_ID` option specifies an identifier used to identify the unit of work represented by a USAP command and the associated SAP job.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cmdid <i>id</i>			✓		✓
Environment Variable	USAPCMDID= <i>id</i>			✓		
Configuration File Keyword	n/a					

### Value

*id* is the identifier used to identify the unit of work represented by a USAP command and the associated SAP job.

*id* can be any value (maximum length of 50 characters).

If *id* contains spaces, it must be enclosed in double ( " ) or single ( ' ) quotation marks.

## 5.15 DESTINATION

### Description

The DESTINATION option specifies the name of a destination defined in the `saprfc.ini` file.

The `saprfc.ini` file must be in the current directory, or its full path must be specified in environment variable `RFC_INI`.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-e destination</code>			✓		✓
Command Line, Long Form	<code>-dest destination</code>			✓		✓
Environment Variable	<code>USAPDEST=destination</code>			✓		
Configuration File Keyword	Destination <code>destination</code>			✓		✓

### Value

*destination* is the name of a destination defined in the `saprfc.ini` file.

## 5.16 DISPLAY\_CLIENT

### Description

The DISPLAY\_CLIENT option identifies a specific SAP client whose intercepted jobs will be reported.

If a specific client is not specified with this option, intercepted jobs from all clients will be included in the report.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-dspclient <i>client</i>			✓		✓
Environment Variable	USAPDSPCLIENT <i>client</i>			✓		
Configuration File Keyword	dspclient <i>client</i>			✓		✓

### Value

*client* is the specific SAP client whose intercepted jobs will be reported.



## 5.17 ENCRYPT\_FILE

### Description

The ENCRYPT\_FILE option specifies the file name (ddname for z/OS) of an encrypted text command file.

If ENCRYPT\_FILE does not specify a file name, the command file is read from stdin.

Note: If both the ENCRYPT\_FILE and FILE\_NAME options are used, ENCRYPT\_FILE is ignored.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-x <i>name</i>			✓		✓
Command Line, Long Form	-encryptedfile <i>name</i>			✓		✓
Environment Variable	USAPENCRYPTEDFILE= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

*name* is the name (ddname for z/OS) of the encrypted text command file.

## 5.18 ENCRYPTION\_KEY

### Description

The ENCRYPTION\_KEY option specifies the key used to encrypt the command file.

This key acts much like a password for the encrypted command file. If a key was used to encrypt a command file (when Universal Encrypt was run), that same key must be specified to decrypt the file; otherwise, the decryption will fail.

If no key is specified, a default value is provided.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-K <i>key</i>			✓		✓
Command Line, Long Form	-key <i>key</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*key* is the name of the key used to encrypt the command file.

## 5.19 EVENT\_GENERATION

### Description

The `EVENT_GENERATION` option specifies which events are to be generated and processed as persistent events.

A persistent event record is saved in a Universal Enterprise Controller (UEC) database for long-term storage.

(For a list of all event types for all Stonebranch Solutions components, see the Universal Event Subsystem 4.2.0 Event Definitions document.)

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	n/a					
Environment Variable	n/a					
Configuration File Keyword	<code>event_generation types</code>			✓		✓

### Values

*type* specifies a comma-separated list of event types. It allows for all or a subset of all potential event message types to be selected.

Event type ranges can be specified by separating the lower and upper range values with a dash ( - ) character.

Event types can be selected for inclusion or exclusion:

- Inclusion operator is an asterisk ( \* ).
- Exclusion operator is **X** or **x**.

---

## Examples

---

- 100,101,102  
Generate event types 100, 101, and 102.
- 100-102  
Generate event types 100 through 102.
- 100-102,200  
Generate event types 100 through 102 and 200.
- \*  
Generate all event types.
- \*,X100  
Generate all event types except for 100.
- x\*  
Generate no event types.
- \*,X200-250,!300  
Generate all event types except for 200 through 250 and 300.

**[Default is X\* (no event types).]**

## 5.20 EVENT\_ID

### Description

---

The EVENT\_ID option specifies the name of the event.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-event_id <i>id</i>			✓		✓
Environment Variable	USAPREVENTID= <i>id</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*id* is the name of the event.

## 5.21 EVENT\_PARAMETER

### Description

---

The EVENT\_PARAMETER option specifies the optional parameter value for the event.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-event_parm <i>parm</i>			✓		✓
Environment Variable	USAPREVENTPARM= <i>parm</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*parm* is the optional parameter value for the event.

## 5.22 EXIT\_JOB\_ACTIVE

### Description

The EXIT\_JOB\_ACTIVE option specifies the USAP exit code for the SAP job `active` status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-activeec <i>exitcode</i>			✓		✓
Environment Variable	USAPACTIVEEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	active_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job `active` status.

#### Defaults

**[Internal default is 10.]**

**[Configuration default is 10.]**

## 5.23 EXIT\_JOB\_FINISHED

### Description

The EXIT\_JOB\_FINISHED option specifies the USAP exit code for the SAP job **finished** status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-finishedec <i>exitcode</i>			✓		✓
Environment Variable	USAPFINISHEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	finished_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job **finished** status.

#### Defaults

**[Internal default is 20.]**

**[Configuration default is 0.]**



## 5.24 EXIT\_JOB\_READY

### Description

The EXIT\_JOB\_READY option specifies the USAP exit code for the SAP job ready status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-readyec <i>exitcode</i>			✓		✓
Environment Variable	USAPREADYEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	ready_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job ready status.

#### Defaults

**[Internal default is 12.]**

**[Configuration default is 12.]**

## 5.25 EXIT\_JOB\_RELEASED

### Description

The EXIT\_JOB\_RELEASED option specifies the USAP exit code for the SAP job **re1eased** status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-releasedec <i>exitcode</i>			✓		✓
Environment Variable	USAPRELEASEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	released_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job **re1eased** status.

#### Defaults

**[Internal default is 16.]**

**[Configuration default is 16.]**

## 5.26 EXIT\_JOB\_SCHEDULED

### Description

The EXIT\_JOB\_SCHEDULED option specifies the USAP exit code for the SAP job `scheduled` status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-scheduledec <i>exitcode</i>			✓		✓
Environment Variable	USAPCHEDULEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	scheduled_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job `scheduled` status.

#### Defaults

**[Internal default is 14.]**

**[Configuration default is 14.]**

## 5.27 EXIT\_JOB\_TERMINATED

### Description

The EXIT\_JOB\_TERMINATED option specifies the USAP exit code for the SAP job **terminated** status.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-terminatedec <i>exitcode</i>			✓		✓
Environment Variable	USAPTERMINATEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	terminated_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP job **terminated** status.

#### Defaults

**[Internal default is 18.]**

**[Configuration default is 8.]**

## 5.28 EXIT\_QUEUE\_BACKGROUND

### Description

The EXIT\_QUEUE\_BACKGROUND option specifies the USAP exit code for the SAP queue state S (in background).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-qinbackgroundec <i>exitcode</i>			✓		✓
Environment Variable	USAPINBACKGROUNDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	-qinbackground_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP queue state S (in background).

#### Defaults

**[Internal default is 14.]**

**[Configuration default is 10.]**

## 5.29 EXIT\_QUEUE\_CREATED

### Description

The EXIT\_QUEUE\_CREATED option specifies the USAP exit code for the SAP queue state C (to be created).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-qtobecreatedec <i>exitcode</i>			✓		✓
Environment Variable	USAPTOBECREATEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	-qtobecreated_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP queue state C (created).

#### Defaults

**[Internal default is 10.]**

**[Configuration default is 14.]**

## 5.30 EXIT\_QUEUE\_ERROR

### Description

The EXIT\_QUEUE\_ERROR option specifies the USAP exit code for the SAP queue state E (error).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-qerrorec <i>exitcode</i>			✓		✓
Environment Variable	USAPERROREXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	-qerror_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP queue state E (error).

#### Defaults

**[Internal default is 18.]**

**[Configuration default is 8.]**

## 5.31 EXIT\_QUEUE\_FINISHED

### Description

The EXIT\_QUEUE\_FINISHED option specifies the USAP exit code for the SAP queue state F (finished).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-qfinishedec <i>exitcode</i>			✓		✓
Environment Variable	USAPFINISHEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	-qfinished_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP queue state F (finished).

#### Defaults

**[Internal default is 16.]**

**[Configuration default is 0.]**



## 5.32 EXIT\_QUEUE\_UNPROCESSED

### Description

The EXIT\_QUEUE\_UNPROCESSED option specifies the USAP exit code for the SAP queue state [ ] (unprocessed).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-qunprocessedec <i>exitcode</i>			✓		✓
Environment Variable	USAPUNPROCESSEDEXITCODE= <i>exitcode</i>			✓		
Configuration File Keyword	-qunprocessed_exit_code <i>exitcode</i>			✓		✓

### Value

*exitcode* is the USAP exit code for the SAP queue state [ ] (unprocessed).

#### Defaults

**[Internal default is 12.]**

**[Configuration default is 12.]**

## 5.33 EXTERNAL\_COMMAND

### Description

The EXTERNAL\_COMMAND option specifies the name of a command or a mask used to select SAP external commands that match the mask.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cmd <i>name</i>			√		√
Environment Variable	USAPCMD= <i>name</i>			√		
Configuration File Keyword	n/a					

### Value

*name* is the name of a command or a mask used to select SAP external commands that match the mask.

A mask contains an asterisk ( \* ) to represent 0 or more characters of a command name.

## 5.34 FILE\_NAME

### Description

The FILE\_NAME option specifies the file name (ddname for z/OS) of a plain text command file.

If FILE\_NAME does not specify a file name, the command file is read from stdin.

Note: If both the FILE\_NAME and ENCRYPT\_FILE options are used, ENCRYPT\_FILE is ignored.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-f <i>name</i>			✓		✓
Command Line, Long Form	-file <i>name</i>			✓		✓
Environment Variable	USAPFILE= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

*name* is the name (ddname for z/OS) of the plain text command file.

## 5.35 FROM\_DATE

### Description

---

The FROM\_DATE option specifies the earliest date to use for job selection or syslog request.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-fromdate <i>date</i>			✓		✓
Environment Variable	USAPFROMDATE= <i>date</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*date* is the earliest date to use for job selection or syslog request.

The format of *date* is:

YYYY/MM/DD

## 5.36 FROM\_TIME

### Description

---

The FROM\_TIME option specifies the earliest time to use for job selection or syslog request.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-fromtime <i>time</i>			✓		✓
Environment Variable	USAPFROMTIME= <i>time</i>			✓		✓
Configuration File Keyword	n/a					

### Value

---

*time* is the earliest time to use for job selection or syslog request.

The format of *time* is:

HH:MM:SS

## 5.37 HELP

### Description

---

The HELP option writes command line help.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-h			✓		✓
Command Line, Long Form	-help			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

---

(There are no values required for this option.)

## 5.38 IMMEDIATE\_JOB

### Description

---

The IMMEDIATE\_JOB option causes the job to be started immediately.

If the job cannot be started immediately, an error is returned and the job does not wait to start.

The default is to start a job “as soon as possible.” In the default case, if the SAP system is unable to start the job, it will keep the job in a waiting state and start it whenever possible.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-i			✓		✓
Command Line, Long Form	-immediate			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

---

(There are no values used with this option.)

## 5.39 INSTALLATION\_DIRECTORY

### Description

The `INSTALLATION_DIRECTORY` option specifies the location in which Universal Connector is installed.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	n/a					
Environment Variable	n/a					
Configuration File Keyword	<code>installation_directory directory</code>			✓		

### Values

*directory* is the path name for the Universal Connector installation file.

**[Default is `/opt/universal/usap.`]**



## 5.40 JOB\_ID

### Description

The JOB\_ID option specifies the job ID of an SAP job.

The type of job depends on the command being used, as shown in the following table.

Command	Type of Job
RUN_JOB SUBMIT_JOB	ID of an existing job to use as a model for the new job definition.
MODIFY_JOB	ID of an existing SAP job to be modified. The job ID can be specified on the command line or in the job definition file. The command line job ID will override the job definition file job ID when both are present.
START_JOB	ID of an existing SAP job to start.
WAIT_FOR_JOB	ID of a started SAP job.
BDCWAIT	ID of a started SAP job. It must be a single step job that executes ABAP program RSBDCSUB.
ABORT	ID of an existing SAP job to abort.
PURGE JOB	ID of an existing SAP job to purge.
DISPLAY JOB LOG DISPLAY SPOOLLIST DISPLAY STATUS DISPLAY JOBDEF	ID of an existing SAP job to select.
DISPLAY_SELECT	Either a complete job ID or a job ID mask used to select SAP jobs that match the mask. A mask contains an asterisk (*) to represent 0 or more characters of a job ID.
GENERATE Job Definition File	ID of an existing SAP job to select as the model job.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-b <i>jobid</i>			✓		✓
Command Line, Long Form	-jobid <i>jobid</i>			✓		✓
Environment Variable	USAPJOBID= <i>jobid</i>			✓		
Configuration File Keyword	n/a					

### Value

*jobid* is the ID of the SAP job.

## 5.41 JOB\_ID\_PATTERN

### Description

The JOB\_ID\_PATTERN option specifies the character pattern used to locate the header record and determine the offset of the job id in the RSBDCSUB batch input processing report.

The format of the RSBDCSUB report is somewhat dependant on the language parameter for the job step that executes it. Therefore, it may be necessary to adjust the character pattern specified by JOB\_ID\_PATTERN based on the value of the SAP job step language parameter being used.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-bdcjobidptrn <i>pattern</i>			✓		✓
Environment Variable	USAPBDCJOBIDPTRN= <i>pattern</i>			✓		
Configuration File Keyword	bdc_jobid_ptrn <i>pattern</i>			✓		✓

### Value

*pattern* is the character pattern that is used to locate the header record and determine the offset of the job ID.

**[Default is "Job no.".]**

## 5.42 JOB\_LOG\_CHILD

### Description

The JOB\_LOG\_CHILD option specifies whether or not job logs for child jobs are returned (that is, printed to standard error).

Note: JOB\_LOG\_CHILD is evaluated only when both the [RETURN\\_JOB\\_LOG](#) and [WAIT\\_FOR\\_CHILD\\_JOBS](#) options are set to yes.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-joblogchild <i>option</i>			✓		✓
Environment Variable	USAPJOBLOGCHILD= <i>option</i>			✓		
Configuration File Keyword	print_joblog_for_child_jobs <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not job logs for child jobs are returned.

Valid values for *option* are:

- **yes**  
Job logs will be returned for all child jobs.
- **error**  
Job logs will only be returned for child jobs that did not complete successfully.
- **no**  
Job logs will not be returned for child jobs.

**[Default is yes.]**

## 5.43 JOB\_NAME

### Description

The JOB\_NAME option specifies the name of an SAP job.

The type of job depends on the command being used, as shown in the following table.

Command	Type of Job
RUN_JOB SUBMIT_JOB	Name of an existing job to use as a model for the new job definition.
START_JOB	Name of an existing SAP job to start.
WAIT_FOR_JOB	Name of a started SAP job.
BDCWAIT	Name of a started SAP job. It must be a single step job that executes ABAP program RSBDCSUB.
ABORT	Name of an existing SAP job to abort.
PURGE	Name of an existing SAP job to purge.
DISPLAY JOBLOG DISPLAY SPOOLLIST DISPLAY STATUS DISPLAY JOBDEF	Name of an existing SAP job to select.
DISPLAY SELECT	Either a complete job name or a job name mask used to select SAP jobs that match the mask. A mask contains an asterisk (*) to represent 0 or more characters of a job name.
GENERATE Job Definition File	Name of an existing SAP job to select as the model job.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-j <i>jobname</i>			✓		✓
Command Line, Long Form	-jobname <i>jobname</i>			✓		✓
Environment Variable	USAPJOBNAME= <i>jobname</i>			✓		
Configuration File Keyword	n/a					

### Value

*jobname* is the name of the SAP job.

## 5.44 JOB\_NAME\_PATTERN

### Description

The JOB\_NAME\_PATTERN option specifies a character pattern that is used to locate the header record and determine the offset of the job name in the RSBDCSUB batch input processing report.

The format of the RSBDCSUB report is somewhat dependant on the language parameter for the job step that executes it. Therefore, it may be necessary to adjust the character pattern specified by JOB\_NAME\_PATTERN based on the value of the SAP job step language parameter being used.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-bdcjobnameptrn <i>pattern</i>			✓		✓
Environment Variable	USAPBDCJOBNAMEPTRN= <i>pattern</i>			✓		
Configuration File Keyword	bdc_jobname_ptrn <i>pattern</i>			✓		✓

### Value

*pattern* is the character pattern that is used to locate the header record and determine the offset of the job name.

**[Default is "|Session".]**

## 5.45 JOB\_NETWORK\_ID

### Description

The JOB\_NETWORK\_ID option specifies the network identifier for the pre-existing SAP FS job network being started.

Note: For the PURGE FS JOB NETWORK command, JOB\_NETWORK\_ID specifies the network identifier for the pre-existing SAP FS job network to purge.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-jnetid <i>jobnetid</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*jobnetid* is the network identifier for the pre-existing SAP job network.

## 5.46 JOB\_PROCESS\_ID

### Description

The JOB\_PROCESS\_ID option specifies the process ID of an existing SAP FS job network process to start.

Note: For the PURGE FS JOB NETWORK command, JOB\_PROCESS\_ID specifies the process ID of an existing SAP FS job network process to purge.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-jnetprcid <i>processid</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*processid* is the process ID of an existing SAP FS job network process.

## 5.47 LAYOUT\_NAME

### Description

The LAYOUT\_NAME option specifies either a complete layout name or a mask used to select printer layouts that match the mask.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-layout <i>name</i>			✓		✓
Environment Variable	USAPLAYOUT= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

*name* is either a complete layout name or a mask used to select printer layouts that match the mask.

A mask contains an asterisk ( \* ) to represent 0 or more characters of a layout name.



## 5.48 LISTEN\_INTERVAL

### Description

The LISTEN\_INTERVAL option specifies the number of seconds that will elapse between RFC listen calls.

Listen calls are polling calls that are performed repetitively to determine if an RFC event is available.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-rfc_listen_interval <i>interval</i>			✓		✓
Environment Variable	USAP_RFC_LISTEN_INTERVAL= <i>interval</i>			✓		
Configuration File Keyword	rfc_listen_interval <i>interval</i>			✓		✓

### Value

*interval* is the number of seconds that will elapse between RFC listen calls.

**[Default value is 1.]**

## 5.49 LOGON\_LANGUAGE

### Description

The LOGON\_LANGUAGE option specifies the SAP logon language used for the USAP session.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-saplang <i>language</i>			✓		✓
Environment Variable	USAPLANG= <i>language</i>			✓		
Configuration File Keyword	sap_language <i>language</i>			✓		✓

### Value

*language* is the SAP logon language used for the USAP session.

Valid values for *language* are:

- Any valid 1-character SAP language identifier
- Any valid 2-character ISO language identifier
- " " (no value)  
This prevents Universal Connector from explicitly setting the SAP language for the RFC communication session with the SAP system. The result is that the SAP system uses the default language set up for the user ID.

**[Default is *EN* (English).]**

## 5.50 LOGON\_RETRY\_COUNT

### Description

The LOGON\_RETRY\_COUNT option specifies the number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-rfc_logon_retry_count <i>count</i>			✓		✓
Environment Variable	USAP_RFC_LOGON_RETRY_COUNT= <i>count</i>			✓		
Configuration File Keyword	rfc_logon_retry_count <i>count</i>			✓		✓

### Value

*count* is the number of unsuccessful RFC logon retry attempts that can occur before USAP terminates the logon process and ends unsuccessfully.

**[Default value is 10.]**

## 5.51 LOGON\_RETRY\_INTERVAL

### Description

The LOGON\_RETRY\_INTERVAL option specifies the number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-rfc_logon_retry_interval <i>interval</i>			✓		✓
Environment Variable	USAP_RFC_LOGON_RETRY_INTERVAL= <i>interval</i>			✓		
Configuration File Keyword	rfc_logon_retry_interval <i>interval</i>			✓		✓

### Value

*interval* is the number of seconds that will elapse between a failed RFC logon attempt and the retry of that logon attempt.

**[Default value is 10.]**

## 5.52 LONG\_DEVICE\_NAME

### Description

The LONG\_DEVICE\_NAME option specifies either a complete device name or a mask used to select SAP output devices that match the mask.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-long_name <i>name</i>			✓		✓
Environment Variable	USAPLONGNAME= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

*name* is either a complete device name or a mask used to select SAP output devices that match the mask.

A mask contains an asterisk ( \* ) to represent 0 or more characters of a device name.

## 5.53 MASS\_ACTIVITY\_WAIT

### Description

The MASS\_ACTIVITY\_WAIT option causes USAP to wait for the SAP mass activity jobs to complete processing.

When MASS\_ACTIVITY\_WAIT is used, the exit code of USAP indicates the completion status of the mass activity. (See Sections [2.5 Exit Codes](#) (for z/OS) and [3.5 Exit Codes](#) (for UNIX) for a complete list of job status exit codes.)

The MASS\_ACTIVITY\_WAIT option also allows USAP to return the job log, application log, and spool lists for the job. [RETURN\\_JOB\\_LOG](#) controls the return of the job log, [RETURN\\_APPLICATION\\_LOG](#) controls the return of the application log, and [RETURN\\_SPOOL\\_LIST](#) controls the return of the spool list.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-mawait			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

(There are no values used with this option.)

## 5.54 MAX\_CHILD\_DEPTH

### Description

The MAX\_CHILD\_DEPTH option specifies the maximum relationship depth that will be monitored by USAP.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-max_child_depth <i>depth</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	max_child_depth <i>depth</i>			✓		✓

### Value

*depth* is the specification for the maximum relationship depth.

Valid values for *depth* are 1 to 999.

If *depth* is 1, USAP only will check for and monitor jobs created by the initial parent job. Jobs created by child jobs will not be detected or monitored.

**[Default is 999.]**

## 5.55 MAX\_HIT\_COUNT

### Description

---

The MAX\_HIT\_COUNT option specifies the maximum number of ABAP reports to be returned.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-count <i>number</i>			✓		✓
Environment Variable	USAPCOUNT= <i>number</i>			✓		
Configuration File Keyword	count <i>number</i>			✓		✓

### Value

---

*number* is the maximum number of ABAP reports to be returned.

**[Default is 999.]**



## 5.56 MAX\_JOB\_LOG\_SIZE

### Description

The MAX\_JOB\_LOG\_SIZE option specifies the maximum size for job logs. Job logs exceeding the maximum size will not be transferred.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-max_log_size <i>size</i>			✓		✓
Environment Variable	USAPMAXLOGSIZE= <i>size</i>			✓		
Configuration File Keyword	max_log_size <i>size</i>			✓		✓

### Value

*size* is the maximum size for job logs.

*size* can be suffixed with either:

- **M** (for megabytes)
- **K** (for kilobytes)

**[Default is 1536M.]**

## 5.57 MAX\_SPOOL\_LIST\_SIZE

### Description

The MAX\_SPOOL\_LIST\_SIZE option specifies the maximum size for job logs. Pool lists exceeding the maximum size will not be transferred.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-max_spool_size <i>size</i>			✓		✓
Environment Variable	USAPMAXSPOOLSIZE= <i>size</i>			✓		
Configuration File Keyword	max_spool_size <i>size</i>			✓		✓

### Value

*size* is the maximum size for spool lists.

*size* can be suffixed with either:

- **M** (for megabytes)
- **K** (for kilobytes)

**[Default is 1536M.]**

## 5.58 MAX\_XBP

### Description

The MAX\_XBP option specifies the maximum version of the SAP XBP interface that will be used during USAP execution.

If a version is not specified with this option, USAP will use the highest level supported by both USAP and the SAP system.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-maxxbp <i>version</i>			✓		✓
Environment Variable	USAPMAXXBP <i>version</i>			✓		
Configuration File Keyword	max_xbp <i>version</i>			✓		✓

### Value

*version* is the maximum version of the SAP XBP interface that will be used during USAP execution.

Valid values for *version* are:

- 1.0
- 2.0

## 5.59 MESSAGE\_LANGUAGE

### Description

---

The MESSAGE\_LANGUAGE option specifies the language in which messages are written.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-L <i>language</i>			✓		✓
Command Line, Long Form	-lang <i>language</i>			✓		✓
Environment Variable	USAPLANG= <i>language</i>			✓		
Configuration File Keyword	language <i>language</i>			✓		✓

### Value

---

*language* is the language in which messages are written.

The first three characters of the language are used as a three-character suffix to form the name of a Universal Message Catalog (UMC) file. UMC files are in the n1s product directory.

**[Default is *ENGLISH*.]**

## 5.60 MESSAGE\_LEVEL

### Description

The MESSAGE\_LEVEL option specifies level of messages to write.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-l <i>level</i>			✓		✓
Command Line, Long Form	-level <i>level</i>			✓		✓
Environment Variable	USAPLEVEL= <i>level</i>			✓		
Configuration File Keyword	message_level <i>level</i>			✓		✓

### Value

*level* is the level of messages to write.

Valid values for level are:

- **trace**  
Activates tracing and generates a trace file to which USAP writes trace messages used for debugging.  
Note: Use **trace** only as directed by Stonebranch, Inc. [Customer Support](#).
- **audit**  
Issues audit, informational, warning, and error messages.
- **info**  
Issues informational, warning, and error messages.
- **warn**  
Issues warning and error messages.
- **error**  
Issues error messages only.

**UNIX**

[Default is warn.]

**z/OS**

[Default is info.]

## 5.61 NO\_START\_DATE

### Description

The NO\_START\_DATE option specifies whether or not to include jobs with no start date in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-nodate <i>option</i>			√		√
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with no start date in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with no start date in selection criteria.
- **no**  
Do not include jobs with no start date in selection criteria.

**[Default is yes.]**

## 5.62 OPERATING\_SYSTEM

### Description

---

The OPERATING\_SYSTEM option specifies the name of the operating system for which external commands are searched.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-opsys <i>name</i>			✓		✓
Environment Variable	USAPOPSYS= <i>name</i>			✓		
Configuration File Keyword	opsys			✓		✓

### Value

---

*name* is the name of the operating system for which external commands are searched.

**[Default is \*.]**

## 5.63 OUTPUT\_FIELD\_LIST

### Description

The OUTPUT\_FIELD\_LIST option specifies additional fields to display for the `select` command.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-output <i>list</i>			✓		✓
Environment Variable	USAPOUTPUT= <i>list</i>			✓		
Configuration File Keyword	output			✓		✓

### Value

*list* is the additional fields to display.

*list* is a comma-separated list of fields, with no spaces between the field names and the commas.

The fields correspond with the field names in the BAPIXMJOB structure defined in the SAP system, as shown in [Table 5.2](#), below.



Field Name	Field Description
Field Name	Field Description
JOBNAME	Background job name
JOBCOUNT	Batch job number
STPCOUNT	Job step ID number
SDLSTRDT	Planned start date for batch job
SDLSTRTM	Planned start time for batch job
BTCSYSTEM	Target system to run background job
SDLDATE	Date of job/step scheduling
SDLTIME	Time of a scheduled job/step
SDLUNAME	Initiator of job step scheduling
LASTCHDATE	Date of last job change
LASTCHTIME	Time of last job change
LASTCHNAME	Last job change made by
RELDATE	Release date for batch schedule
RELTIME	Release time of scheduled batch job
RELUNAME	User that released scheduled batch job
STRTDATE	Job start date
STRTTIME	Batch job start time
ENDDATE	Job end date
ENDTIME	Batch job end time
PERIODIC	Periodic jobs indicator ('X')
STATUS	Status of batch job
AUTHCKNAM	Background user name for authorization check
AUTHCKMAN	Background client for authorization check
SUCCNUM	Number of subsequent jobs
PREDNUM	Number of previous jobs
LASTSTRDT	Latest run date for batch job
LASTSTRTM	Latest run time for batch job
WPNUMBER	Work process number
WPPROCID	Work process ID
EVENTID	Background event ID
EVENTPARM	Background event parameters (for example, Jobname/Jobcount)
JOBCLASS	Job classification
CALENDARID	Factory calendar ID for background processing
EXECSERVER	Server name
REAXSERVER	Server name

Table 5.2 BAPIXMJOB Structure Fields

## 5.64 PAGE\_LIMIT

### Description

The PAGE\_LIMIT option specifies the maximum number of pages that can be returned in the syslog report.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-pagelimit <i>limit</i>			✓		✓
Environment Variable	USAPPAGELIMIT= <i>limit</i>			✓		
Configuration File Keyword	n/a					

### Value

*limit* is the maximum number of pages that can be returned in the syslog report.

Valid values for list are 1 to 999.

**[Default is 999.]**

## 5.65 PASSWORD

### Description

---

The PASSWORD option specifies the password for the SAP user ID.

If the password is not specified and the command is executed from a console, USAP prompts for a password.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-w password</code>			✓		✓
Command Line, Long Form	<code>-pwd password</code>			✓		✓
Environment Variable	<code>USAPPWD=password</code>			✓		
Configuration File Keyword	<code>password password</code>			✓		✓

### Value

---

*password* is the password for the SAP user ID.

## 5.66 PLF\_DIRECTORY

### Description

The PLF\_DIRECTORY option specifies the Program Lock File (PLF) directory where the program lock files are located.

A program lock file is created and used by USAP process to store manager process termination information for the Universal Broker.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-plf_directory <i>directory</i>			✓		
Environment Variable	USAPPLFDIRECTORY= <i>directory</i>			✓		
Configuration File Keyword	n/a					

### Values

*directory* is the name of the PLF directory.

**[Default is /var/opt/universal/tmp.]**

## 5.67 PRINTER\_NAME

### Description

---

The PRINTER\_NAME option specifies the name of a printer for which the print formats will be retrieved.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printer <i>name</i>			✓		✓
Environment Variable	USAPPRINTER= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*name* is name of a printer for which the print formats will be retrieved.

## 5.68 PURGE\_BDC\_MAP

### Description

The PURGE\_BDC\_MAP option specifies whether or not USAP will delete the batch input session queues that have been processed successfully.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-purge_bdc_map <i>option</i>			✓		✓
Environment Variable	USAP_PURGE_BDC_MAP= <i>option</i>			✓		
Configuration File Keyword	purge_bdc_map <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not USAP will delete the batch input session queues.

Valid values for *option* are:

- **yes**  
Delete the batch input session queues
- **no**  
Do not delete the batch input session queues

## 5.69 PURGE\_CHILD\_JOBS

### Description

The PURGE\_CHILD option specifies whether or not all child jobs are purged from the SAP system.

Note: PURGE\_CHILD is evaluated only when the PURGE command is being used.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-purgechild <i>option</i>			✓		✓
Environment Variable	USAPPURGECHILD= <i>option</i>			✓		
Configuration File Keyword	purge_child_jobs <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not all child jobs are purged.

Valid values for options are:

- **yes**  
All child jobs are purged.
- **no**  
CHild jobs are not purged.

**[Default is yes.]**

## 5.70 PURGE\_JOB

### Description

The PURGE\_JOB option specifies that when the job completes processing, it is purged from the SAP system,

(When used with the BDCWAIT command, PURGE\_JOB specifies that when the job specified on the USAP command line (parent job) completes, and all child jobs created by RSBDCSUB have completed, the parent and child jobs are purged from the SAP system.)

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-P			✓		✓
Command Line, Long Form	-purge			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

(There are no values used with this option.)



## 5.71 QUEUE\_ID

### Description

---

The QUEUE\_ID option specifies the queue identifier associated with the batch input session.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-q <i>queueid</i>			✓		✓
Command Line, Long Form	-qid <i>queueidt</i>			✓		✓
Environment Variable	USAPQID= <i>queueid</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*queueid* is the queue identifier associated with the batch input session.

## 5.72 QUEUE\_ID\_PATTERN

### Description

The QUEUE\_ID\_PATTERN option specifies a character pattern used to locate the header record and determine the offset of the queue ID in the RSBDCSUB batch input processing report.

The format of the RSBDCSUB report is somewhat dependant on the language parameter for the job step that executes it. Therefore, it may be necessary to adjust the character pattern specified by QUEUE\_ID\_PATTERN based on the value of the SAP job step language parameter being used.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-bdcqidptrn <i>pattern</i>			✓		✓
Environment Variable	USAPBDCQIDPTRN= <i>pattern</i>			✓		
Configuration File Keyword	bdc_qid_ptrn <i>pattern</i>			✓		✓

### Value

*pattern* is the character pattern that is used to locate the header record and determine the offset of the queue ID.

**[Default is "|Queue ID".]**

## 5.73 RESTART

### Description

The RESTART option specifies whether or not this execution of USAP is a restart of a previous client fault tolerant USAP command.

See Section 2.3 Client Fault Tolerance for details on the client fault tolerant feature.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-restart <i>option</i>			✓		✓
Environment Variable	USAPRESTART= <i>option</i>			✓		
Configuration File Keyword	restart <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not this execution of USAP is a restart.

Valid values for *option* are:

- **yes**  
USAP is restarting an existing unit of work represented by a command ID.  
The `COMMAND_ID` and `CLIENT_FAULT_TOLERANT` options are required.
- **no**  
USAP is not restarting.
- **auto**  
USAP checks if the Broker is executing an existing unit of work, identified by the `COMMAND_ID` option.
  - If a matching command ID is found, the Manager attempts a restart.
  - If a matching command ID is not found, the Manager does not attempt a restart.

The `COMMAND_ID` and `MANAGER_FAULT_TOLERANT` options are required.

**[Default is no.]**

**Note:** When using the RESTART AUTO option, USAP will not start a new instance of a job on the SAP system if a job matching the job name/command ID exists in the SAP system. USAP will continue to reconnect to the existing SAP job. Without considering the behavior resulting from the use of RESTART AUTO, it may be possible for one to assume that a job has been run multiple times when, in fact, USAP has been reconnecting to the same job instance. Informational messages are printed by USAP to standard error to indicate the reconnected status but, if the message level is not set to `info`, the messages will not be seen.

Given the possibility for confusion surrounding the use of RESTART AUTO, a parameter has been introduced to control the use of RESTART AUTO. This parameter is described in the following section.

## 5.74 RETRY\_CALL\_COUNT

### Description

The RETRY\_CALL\_COUNT option specifies the number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-rfc_retry_count <i>interval</i>			✓		✓
Environment Variable	USAP_RFC_RETRY_COUNT= <i>interval</i>			✓		
Configuration File Keyword	rfc_retry_count <i>interval</i>			✓		✓

### Value

*interval* is the number of unsuccessful RFC call retry attempts that can occur before USAP terminates the RFC call retry process and ends unsuccessfully.

**[Default value is 10.]**

## 5.75 RETRY\_CALL\_INTERVAL

### Description

The `RETRY_CALL_INTERVAL` option specifies the number of seconds that will elapse between a failed RFC call and the retry of that call.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	<code>-rfc_retry_interval interval</code>			✓		✓
Environment Variable	<code>USAP_RFC_RETRY_INTERVAL= interval</code>			✓		
Configuration File Keyword	<code>rfc_retry_interval interval</code>			✓		✓

### Value

*interval* is the number of seconds that will elapse between a failed RFC call and the retry of that call.

**[Default value is 10.]**

## 5.76 RETURN\_APPLICATION\_LOG

### Description

The RETURN\_JOB\_LOG option specifies whether or not the job's application log is returned (provided that an application log was created for the job).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-applog <i>option</i>			✓		✓
Environment Variable	USAPAPPLOG= <i>option</i>			✓		
Configuration File Keyword	print_applog <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not the application log is returned.

Valid values for *option* are:

- **yes**  
Application log is returned to standard error.
- **no**  
Application log is not returned.

**[Default is yes.]**

## 5.77 RETURN\_APPLICATION\_RC

### Description

The RETURN\_JOB\_RC option specifies whether or not the job's application return codes are returned (provided that application return codes were set for the job).

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-printapprc <i>option</i>			✓		✓
Environment Variable	USAPPRINTAPPRC= <i>option</i>			✓		
Configuration File Keyword	print_app_rc <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not the application return codes are returned.

Valid values for *option* are:

- **yes**  
Application return codes are returned to standard error.
- **no**  
Application return codes are not returned.

**[Default is yes.]**



## 5.78 RETURN\_JOB\_LOG

### Description

---

The RETURN\_JOB\_LOG option specifies whether or not the job's job log is returned.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-g <i>option</i>			✓		✓
Command Line, Long Form	-joblog <i>option</i>			✓		✓
Environment Variable	USAPJOBLOG= <i>option</i>			✓		
Configuration File Keyword	print_joblog <i>option</i>			✓		✓

### Value

---

*option* is the specification for whether or not the job log is returned.

Valid values for *option* are:

- **yes**  
Job log is returned to standard out.
- **no**  
Job log is not returned.

**[Default is yes.]**

## 5.79 RETURN\_SPOOL\_LIST

### Description

The RETURN\_SPOOL\_LIST option specifies whether or not the spool lists of all job steps are returned.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-s <i>option</i>			✓		✓
Command Line, Long Form	-spoolist <i>option</i>			✓		✓
Environment Variable	USAPSPOLLIST= <i>option</i>			✓		
Configuration File Keyword	print_spoolist <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not the spool lists are returned.

Valid values for *option* are:

- **yes**  
Spool lists are returned to standard out.
- **no**  
Spool lists are not returned.

**[Default is yes.]**

## 5.80 SECURE\_CFT

### Description

The SECURE\_CFT option specifies the mode of client fault tolerance that will be used for the command invocation.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-cft_secure_cft <i>option</i>			✓		✓
Environment Variable	USAP_CFT_SECURE_CFT= <i>option</i>			✓		
Configuration File Keyword	cft_secure_cft <i>option</i>			✓		✓

### Value

*option* is the mode of client fault tolerance that will be used for the command invocation.

Valid values for *option* are:

- **yes**  
Secure CFT will be used for the command. See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for details on the secure CFT mode.
- **no**  
Original pre-XBP 2.0 CFT will be used for the command. See the Indesca User Guide, Section [15.5 Client Fault Tolerance - Universal Connector](#) for details on the pre-XBP 2.0 CFT mode.

**[Default is yes.]**

## 5.81 SERVER\_STOP\_CONDITIONS

### Description

The `SERVER_STOP_CONDITIONS` option specifies one or more exit codes of the executing Universal Connector process that should trigger the locally running Universal Broker to cancel the corresponding SAP job.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-server_stop_conditions <i>codes</i>					✓
Environment Variable	USAPSERVERSTOPCONDITIONS= <i>codes</i>					✓
Configuration File Keyword	server_stop_conditions <i>codes</i>					✓

### Values

*codes* is an exit code, or a comma-separated list of exit codes, that should cause the SAP job to be cancelled.

z/OS ABEND codes are specified in two different formats:

- System ABEND code      Starts with S followed by a 3-character hexadecimal value.
- User ABEND code        Starts with U followed by a 4-character decimal value.

For example, when a job is terminated with the CANCEL console command, the job ends with a system ABEND code of S222.

**[There is no default.]**

## 5.82 SPOOL\_CODEPAGE

### Description

The SPOOL\_CODEPAGE option specifies the codepage that will be used for transferring spool lists from the SAP system.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-spool_codepage <i>codepage</i>			✓		✓
Environment Variable	USAPSPoolCODEPAGE= <i>codepage</i>			✓		
Configuration File Keyword	spool_codepage <i>codepage</i>			✓		✓

### Value

*codepage* is the codepage that will be used for transferring spool lists from the SAP system.

Valid values for *codepage* are any valid SAP codepage.

In addition, two special values can be used to specify the UTF-8 codepage:

- **UTF-8**
- **UTF8**

These values are equivalent to specifying **4110** (the SAP codepage for UTF-8).

## 5.83 SPOOL\_LIST\_CHILD

### Description

The SPOOL\_LIST\_CHILD option specifies whether or not spool lists for child jobs are returned (that is, printed to standard out).

Note: SPOOL\_LIST\_CHILD is evaluated only when both the [WAIT\\_FOR\\_CHILD\\_JOBS](#) and [RETURN\\_SPOOL\\_LIST](#) options are set to **yes**.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-spoolistchild <i>option</i>			✓		✓
Environment Variable	USAPSPOLLISTCHILD= <i>option</i>			✓		
Configuration File Keyword	print_spoolist_for_child_jobs <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not job logs for child jobs are returned.

Valid values for *option* are:

- **yes**  
Spool list for each step of every child job is returned.
- **no**  
Spool lists for child jobs are not be returned.

**[Default is yes.]**

## 5.84 START\_JOB

### Description

---

The START\_JOB option starts the newly defined job.

(For the MODIFY JOB command, START\_JOB starts the modified job.)

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-S			✓		✓
Command Line, Long Form	-start			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

---

(There are no values used with this option.)

## 5.85 STATUS\_ABORTED

### Description

---

The STATUS\_ABORTED option specifies whether or not to include jobs with status **aborted** in selection criteria.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-aborted <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

---

*option* is the specification for whether or not to include jobs with status **aborted** in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status **aborted** in selection criteria.
- **no**  
Do not include jobs with status **aborted** in selection criteria.

**[Default is yes.]**



## 5.86 STATUS\_CHECK\_INTERVAL

### Description

The STATUS\_CHECK\_INTERVAL option specifies the number of seconds that can elapse, without a change in job status, before a call is made to synchronize the actual job status with the SAP stored status.

The job status synchronization is achieved by calling SAP function module BAPI\_XBP\_JOB\_STATUS\_CHECK. This addresses the unlikely scenario where an error condition in the SAP system prevents a completed job status from being written to the SAP database.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a			✓		✓
Command Line, Long Form	-job_stat_check_interval <i>seconds</i>			✓		✓
Environment Variable	USAPJOBSTATCHECKINTERVAL= <i>seconds</i>			✓		
Configuration File Keyword	job_stat_check_interval <i>seconds</i>			✓		✓

### Value

*seconds* is the number of seconds that can elapse before a call is made to synchronize the actual job status with the SAP stored status.

**[Default is 600.]**

## 5.87 STATUS\_FINISHED

### Description

The STATUS\_FINISHED option specifies whether or not to include jobs with status **finished** in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-finished <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with status **finished** in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status **finished** in selection criteria.
- **no**  
Do not include jobs with status **finished** in selection criteria.

**[Default is yes.]**

## 5.88 STATUS\_READY

### Description

The STATUS\_READY option specifies whether or not to include jobs with status **ready** in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-ready <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with status **ready** in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status **ready** in selection criteria.
- **no**  
Do not include jobs with status **ready** in selection criteria.

**[Default is yes.]**

## 5.89 STATUS\_RELEASED

### Description

The STATUS\_RELEASED option specifies whether or not to include jobs with status **re1eased** in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-released <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with status **re1eased** in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status **re1eased** in selection criteria.
- **no**  
Do not include jobs with status **re1eased** in selection criteria.

**[Default is yes.]**

## 5.90 STATUS\_RUNNING

### Description

The STATUS\_RUNNING option specifies whether or not to include jobs with status **running** in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-running <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with status **running** in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status **running** in selection criteria.
- **no**  
Do not include jobs with status **running** in selection criteria.

**[Default is yes.]**

## 5.91 STATUS\_SCHEDULED

### Description

The STATUS\_SCHEDULED option specifies whether or not to include jobs with status `scheduled` in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-scheduled <i>option</i>			√		√
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with status `scheduled` in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with status `scheduled` in selection criteria.
- **no**  
Do not include jobs with status `scheduled` in selection criteria.

**[Default is yes.]**

## 5.92 STEP\_NUMBER

### Description

---

The STEP\_NUMBER option specifies the step number of the SAP job step.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-n <i>stepnumber</i>			✓		✓
Command Line, Long Form	-stepnum <i>stepnumber</i>			✓		✓
Environment Variable	USAPSTEPNUM= <i>stepnum</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*stepnum* is the step number of the SAP job step.

## 5.93 SYSLOG

### Description

The SYSLOG option specifies whether or not to generate a syslog report. SYSLOG is used when USAP is directed to wait for job completion.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-y <i>option</i>			✓		✓
Command Line, Long Form	-syslog <i>option</i>			✓		✓
Environment Variable	USAPSYSLOG= <i>option</i>			✓		
Configuration File Keyword	print_syslog <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not to generate a syslog report.

Valid values for option are:

- **yes**  
Generate a syslog report on standard error.
- **no**  
Do not generate a syslog report.

**[Default is yes.]**



## 5.94 SYSLOG\_POST\_TIME

### Description

The SYSLOG\_POST\_TIME option specifies the number of seconds to add to the job end time when calculating the **to** time for the syslog report.

This will cause USAP to sleep for the specified number of seconds after a job ends and before retrieving the syslog. This is useful for allowing the SAP system time to log all relevant messages.

Note: SYSLOG\_POST\_TIME is used only when the [STATUS\\_READY](#) option is set to **yes**.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-syslogpost <i>seconds</i>			✓		✓
Environment Variable	USAPSYSLOGPOST <i>seconds</i>			✓		
Configuration File Keyword	syslog_post_time <i>seconds</i>			✓		✓

### Value

*seconds* is the number of seconds to add to the job end time.

**[Default is 15.]**

## 5.95 SYSLOG\_PRE\_TIME

### Description

The SYSLOG\_PRE\_TIME option specifies the number of seconds to subtract from the job release time when calculating the `from` time for the syslog report.

This can be used to obtain error messages that may have been generated prior to job release.

Note: SYSLOG\_PRE\_TIME is used only when the `STATUS_READY` option is set to `yes`.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-syslogpre <i>seconds</i>			✓		✓
Environment Variable	USAPSYSLOGPRE <i>seconds</i>			✓		
Configuration File Keyword	syslog_pre_time <i>seconds</i>			✓		✓

### Value

*seconds* is the number of seconds to subtract from the job release time.

**[Default is 0.]**

## 5.96 SYSTEM\_ID

### Description

The SYSTEM\_ID option identifies the local Universal Broker with which USAP must register before the Manager performs any request.

Each Universal Broker running on a system is configured with a system identifier that uniquely identifies the Broker.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-system_id <i>ID</i>					✓
Environment Variable	USAPSYSTEMID= <i>ID</i>					✓
Configuration File Keyword	n/a					

### Values

*ID* is the system identifier of the local Universal Broker.

(Refer to the local Universal Broker administrator for the appropriate system ID to use.)

## 5.97 SYSTEM\_NUMBER

### Description

The SYSTEM\_NUMBER option specifies the SAP system number of an SAP application server.

SYSTEM\_NUMBER, in conjunction with the AS\_HOST option, can be used instead of the DESTINATION option to define a connection to an SAP system.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-sysnr <i>number</i>			√		√
Environment Variable	USAPSYSNR <i>number</i>			√		
Configuration File Keyword	sysnr <i>number</i>			√		√

### Value

*number* is the SAP system number of an SAP application server.

## 5.98 TARGET\_JOB\_NAME

### Description

---

The TARGET\_JOB\_NAME option specifies the name to give the newly created job.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-target_jobname <i>jobname</i>			√		√
Environment Variable	USAPTARGETJOBNAME= <i>jobname</i>			√		
Configuration File Keyword	n/a					

### Value

---

*jobname* is the name for the newly created job.

**[Default is the original jobname.]**

## 5.99 TARGET\_SERVER

### Description

The TARGET\_SERVER option specifies the server on which the job will run.

(For the DISPLAY LOG command, TARGET\_SERVER specifies the name of the server whose SYSLOG will be read.)

Note: TARGET\_SERVER is not available on SAP 3.1 and 4.0 systems.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-r <i>server</i>			✓		✓
Command Line, Long Form	-targetserver <i>server</i>			✓		✓
Environment Variable	USAPTARGETSRV= <i>server</i>			✓		
Configuration File Keyword	n/a					

### Value

*server* is the server on which the job will run.

**[Default is current server when used with the DISPLAY\_LOG command.]**

## 5.100 TARGET\_VARIANT

### Description

The TARGET\_VARIANT option specifies one or more replacement variants for ABAP program job steps in an SAP job.

Each execution of an ABAP program (job step) in an SAP job can use a single variant that contains parameters specific to that program. TARGET\_VARIANT specifies variants that can be used as replacement variants for one or more of these job steps in single SAP job execution.

When a user RUNs or SUBMITs a predefined SAP job that specifies TARGET\_VARIANT, USAP first performs a copy of the template job, then performs the variant substitution.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					✓
Command Line, Long Form	-target_variant <i>job step, variant name;</i> <i>[job step, variant name]...</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

Each target variant contains a pair of values:

- *job step* is the number of the job step (ABAP program) in the SAP job.
- *variant name* is the name of the replacement variable for that job step.

Each *job step / variant name* in a target variant is separated by a comma ( , ). Each target variant is separated by a semicolon ( ; ).

For example:

- -target\_variant **1,var1**
- -target\_variant **1,var1;3,var2;7,var3**

## 5.101 TECHNICAL\_DEVICE\_NAME

### Description

The TECHNICAL\_DEVICE\_NAME option specifies either a complete device name or a mask used to select SAP output devices that match the mask.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-short_name <i>name</i>			✓		✓
Environment Variable	USAPSHORTNAME= <i>name</i>			✓		
Configuration File Keyword	n/a					

### Value

*name* is either a complete device name or a mask used to select SAP output devices that match the mask.

A mask contains an asterisk ( \* ) to represent 0 or more characters of a device name.



## 5.102 TIMEOUT\_INTERVAL

### Description

The `TIMEOUT_INTERVAL` option specifies the number of seconds that can elapse before USAP considers an RFC call to have timed out.

This sets a time constraint on all RFC functions, with the exception of a blocking RFC connect call.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	<code>-rfc_timeout interval</code>			✓		✓
Environment Variable	<code>USAP_RFC_TIMEOUT=interval</code>			✓		
Configuration File Keyword	<code>rfc_timeout interval</code>			✓		✓

### Value

*interval* is the number of seconds that can elapse before USAP considers an RFC call to have timed out.

**[Default value is 120.]**

## 5.103 TO\_DATE

### Description

---

The TO\_DATE option specifies the latest date to use for job selection or syslog request.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-todate <i>date</i>			✓		✓
Environment Variable	USAPTODATE= <i>date</i>			✓		
Configuration File Keyword	n/a					

### Value

---

*date* is the latest date to use for job selection or syslog request.

The format of *date* is:

YYYY/MM/DD

## 5.104 TO\_TIME

### Description

The TO\_TIME option specifies the latest time to use for job selection or syslog request.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-totime <i>time</i>			✓		✓
Environment Variable	USAPTOTIME= <i>time</i>			✓		✓
Configuration File Keyword	n/a					

### Value

*time* is the latest time to use for job selection or syslog request.

The format of *time* is:

HH:MM:SS

## 5.105 TRACE\_DIRECTORY

### Description

The TRACE\_DIRECTORY option specifies the directory where RFC trace files will be written.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-rfc_trace_dir <i>path</i>					√
Environment Variable	n/a					
Configuration File Keyword	rfc_trace_dir <i>path</i>					√

### Value

*path* is the directory where RFC trace files will be written.

A value of . will cause the trace files to be created or appended in the home directory of the user under which USAP is running.

**[Default value is /tmp.]**

## 5.106 TRACE\_FILE\_LINES

### Description

The TRACE\_FILE\_LINES option specifies the maximum number of lines to write to the trace file.

A trace file is generated when the MESSAGE\_LEVEL option is set to **trace**. The trace file will wrap around when the maximum number of lines has been reached and start writing trace entries after the trace header lines.

#### z/OS

In order for the trace file to wrap, the data set must support repositioning. Only sequential, fixed record format data sets support repositioning.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-tracefilelines <i>lines</i>			✓		✓
Environment Variable	USAPTRACEFILELINES <i>lines</i>			✓		
Configuration File Keyword	trace_file_lines <i>lines</i>			✓		✓

### Value

*lines* is the maximum number of lines to write to the trace file.

**[Default is 500,000,000.]**

## 5.107 TRACE\_TABLE

### Description

The TRACE\_TABLE option specifies the size of a wrap-around trace table, and under what conditions the table is written to a file when the process ends.

Trace data can be written to a file / data set as it is produced, or it can be written to a table maintained in memory.

The trace table is written to a file / data set when the program ends under the conditions specified in this option. Tracing is activated, and a trace file is generated, when the MESSAGE\_LEVEL option is set to **trace**.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-trace_table size, condition			✓		✓
Environment Variable	n/a					
Configuration File Keyword	trace_table size, condition			✓		✓

### Values

*size* is the size (in bytes) of the table.

The size can be suffixed with either of the following characters:

- M Indicates that the size is specified in megabytes.
- K Indicates that the size is specified in kilobytes.

For example, 50M indicates that 50 X 1,048,576 bytes of memory is allocated for the trace table.

**[Default is 0 (trace table is not used).]**

*condition* is the condition under which the trace table is written.

Valid values for *condition* are:

- **error**  
Write the trace table if the program ends with a non-zero exit code.
- **always**  
Write the trace table when the program ends regardless of the exit code.
- **never**  
Never write the trace table.

**[Default is never.]**

## 5.108 TRANSLATION\_TABLE

### Description

The TRANSLATION\_TABLE option specifies the spool list translation table file to use for formatting returned spool lists.

The Spoolist Translate Table (STT) files are used to format raw (SAP internal format) spoollists. The STT files are located in the NLS subdirectory of the installation directory.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-t <i>translation_table</i>			✓		✓
Command Line, Long Form	-transtab <i>translation_table</i>			✓		✓
Environment Variable	USAPTRANSTAB= <i>translation_table</i>			✓		
Configuration File Keyword	<i>translation_table translation_table</i>			✓		✓

### Value

*translation\_table* is the base file name of the translation table (STT) file to use for formatting returned spool lists.

All STT files end with an extension of `.stt`.

**[Default is *default*.]**

(The *default* translation table contains translations for the standard SAP formatting codes to appropriate ASCII character representations.)



## 5.109 USAP\_POLL

### Description

The USAP\_POLL option specifies the number of seconds to wait between job status calls to the SAP system.

These status calls are used to monitor the SAP job and, therefore, are made repeatedly until the job completes.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-p <i>seconds</i>			✓		✓
Command Line, Long Form	-poll <i>seconds</i>			✓		✓
Environment Variable	USAPPOLL= <i>seconds</i>			✓		
Configuration File Keyword	poll_time <i>seconds</i>			✓		✓

### Value

*seconds* is the number of seconds to wait between job status calls.

**[Default is 10.]**

## 5.110 USE\_APPLICATION\_RC

### Description

The USE\_APPLICATION\_RC option specifies whether or not the job's application return codes are used to determine the exit code of the Universal Connector job.

If USE\_APPLICATION\_RC is turned on, Universal Connector will merge the SAP job's application return codes with other factors that can affect the exit code of the Universal Connector job. In the merge process, the highest value recorded is used as the exit code.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-useapprc <i>option</i>			✓		✓
Environment Variable	USAPUSEAPPRC= <i>option</i>			✓		
Configuration File Keyword	use_app_rc <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not the application return codes will be merged with the Universal Connector exit code.

Valid values for *option* are:

- **yes**  
Application return codes are merged with the Universal Connector exit code.
- **no**  
Application return codes are not merged with the Universal Connector exit code.

**[Default is no.]**

## 5.111 USER\_ID

### Description

---

The USER\_ID option specifies the SAP user ID with which to logon to the SAP system.

If the user ID is not specified and the command is executed from a console, USAP prompts for a user ID.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-u <i>userid</i>			✓		✓
Command Line, Long Form	-userid <i>userid</i>			✓		✓
Environment Variable	USAPUSERID= <i>userid</i>			✓		
Configuration File Keyword	userid <i>userid</i>			✓		✓

### Value

---

*userid* is the SAP user ID with which to logon to the SAP system.

## 5.112 USER\_NAME

### Description

The USER\_NAME option specifies the user ID associated with a job.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-selusername <i>userid</i>			✓		✓
Environment Variable	USAPSELUSERNAME= <i>userid</i>			✓		
Configuration File Keyword	n/a					

### Value

*userid* is the user ID.

*userid* is either:

- Complete user ID
- User ID mask

Note: A mask contains an asterisk ( \* ) to represent 0 or more characters of a user ID.

**[Default is the user ID with which USAP currently is running.]**

## 5.113 VARIANT

### Description

The VARIANT option specifies the pre-existing SAP variant whose contents will be displayed.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	<code>-V <i>variant</i></code>			✓		✓
Command Line, Long Form	<code>-variant <i>variant</i></code>			✓		✓
Environment Variable	<code>USAPVARIANT=<i>variant</i></code>			✓		
Configuration File Keyword	n/a					

### Value

*variant* is the pre-existing SAP variant.

## 5.114 VARIANT\_LANGUAGE

### Description

The VARIANT\_LANGUAGE option specifies the preferred language in which to return the variant description.

The option is only effective if a variant description exists on the SAP system in the language specified.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-varlang <i>language</i>			✓		✓
Environment Variable	USAPVARLANG <i>language</i>			✓		
Configuration File Keyword	variant_language <i>language</i>			✓		✓

### Value

*language* is the language in which to return the variant description.

**[Default is EN.]**

## 5.115 VARIANT\_SELECTION

### Description

The VARIANT\_SELECTION option specifies the display of available variants.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-varselopt <i>option</i>			✓		✓
Environment Variable	USAPVARSELOPT= <i>option</i>			✓		
Configuration File Keyword	n/a					

### Value

*option* is the variant selection option.

Valid values for *option* are:

- **A**  
Display variants that are available for batch and dialog modes.
- **B**  
Displays variants that are available for batch mode only.

## 5.116 VERSION

### Description

---

The VERSION option writes USAP version and copyright information.

### Usage

---

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-v			✓		✓
Command Line, Long Form	-version			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

---

(There are no values required for this option.)



## 5.117 WAIT

### Description

The WAIT option causes USAP to wait for the SAP job to complete processing.

(When used with the FS JOB NETWORK command, WAIT causes USAP to wait for the SAP job network to complete processing.)

When WAIT is used, the exit code of USAP indicates the completion status of the SAP job / network. (See Sections [2.5 Exit Codes](#) (for z/OS) and [3.5 Exit Codes](#) (for UNIX) for a complete list of job status exit codes.)

It also allows USAP to return the joblog and spoolists for the job. [RETURN\\_JOB\\_LOG](#) controls the return of the joblog. [RETURN\\_SPOOL\\_LIST](#) controls the return of the spoolist.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	-W			✓		✓
Command Line, Long Form	-wait			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

(There are no values used with this option.)

## 5.118 WAIT\_FOR\_CHILD\_JOBS

### Description

The WAIT\_FOR\_CHILD\_JOBS option specifies whether or not to monitor child jobs.

WAIT\_FOR\_CHILD\_JOBS is dependant on the USAP WAIT or RUN command. It is evaluated only when the WAIT command is being used.

When WAIT\_FOR\_CHILD\_JOBS is used, USAP will exit with most significant completion status received from all monitored jobs.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-waitchild <i>option</i>			✓		✓
Environment Variable	USAPWAITCHILD= <i>option</i>					
Configuration File Keyword	wait_for_child_jobs <i>option</i>			✓		✓

### Value

*option* is the specification for whether or not to monitor child jobs.

Valid values for *option* are:

- **yes**  
USAP will monitor all child jobs to completion.
- **no**  
USAP will not monitor child jobs.

**[Default is yes.]**

## 5.119 WITH\_PREDECESSOR

### Description

The WITH\_PREDECESSOR option specifies whether or not to include jobs with start after predecessor in selection criteria.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-withpred <i>option</i>			✓		✓
Environment Variable	n/a					
Configuration File Keyword	n/a					

### Value

*option* is the specification for whether or not to include jobs with start after predecessor in selection criteria.

Valid values for option are:

- **yes**  
Include jobs with start after predecessor in selection criteria.
- **no**  
Do not include jobs with start after predecessor in selection criteria.

**[Default is yes.]**

## 5.120 XMI\_AUDIT\_LEVEL

### Description

The XMI\_AUDIT\_LEVEL option sets the XMI audit level to be used for the execution of the command.

### Usage

Method	Syntax	IBM i	NonStop	UNIX	Windows	z/OS
Command Line, Short Form	n/a					
Command Line, Long Form	-xmiaudit <i>level</i>			✓		✓
Environment Variable	USAPXMIAUDIT= <i>level</i>			✓		
Configuration File Keyword	xmi_audit_level <i>level</i>			✓		✓

### Value

*level* is the XMI audit level to be used for the execution of the command.

Valid values for *level* are 0, 1, 2, and 3. The amount of information logged in the XMI log increases with higher audit level values.

**[Default is 0.]**

# Customer Support

---

Stonebranch, Inc. provides technical support, via telephone and e-mail, for Universal Connector and all Stonebranch Solutions components.

## E-MAIL

---

### All Locations

[support@stonebranch.com](mailto:support@stonebranch.com)

Customer support contact via e-mail also can be made via the Stonebranch website:

[www.stonebranch.com](http://www.stonebranch.com)

## TELEPHONE

---

Customer support via telephone is available 24 hours per day, 7 days per week.

### North America

**(+1) 678 366-7887, extension 6**

**(+1) 877 366-7887, extension 6 [toll-free]**

### Europe

**+49 (0) 700 5566 7887**





**950 North Point Parkway, Suite 200  
Alpharetta, Georgia 30005  
U.S.A.**

