



## **UEMLoad 5.1.0 Quick Reference Guide**

© 2012 by Stonebranch, Inc. All Rights Reserved.

# UEMLoad 5.1.0 Quick Reference Guide

## Usage

```
uemload [ACTION] [OPTIONS] [ {DEFFILE | [EVENTDEF] [HANDLER] } ]
```

```
uemload { -help | -version }
```

## Format

There is a long form and, for most options, a short form available for specifying each option on the command line. The long form is not case-sensitive; the short form is case-sensitive.

Options must be prefixed with a dash ( - ) character. If an option value is specified, the option and its value must be separated by at least one space.

### ACTION { -add | -update | -delete | -list | -export }

Long Form	Short Form	Description
-add	n/a	Add records to the event definition and/or event handler databases.
-update	n/a	Update records in the event definition and/or event handler databases.
-delete	n/a	Remove records from the event definition and/or event handler databases.
-list	n/a	Displays selected records from the event definition and/or event handler databases.
-export	n/a	Create a definition load file containing selected records from the event definition and/or event handler databases.

### OPTIONS [-port] [-cmdid] [ { -help | -version } ]

Long Form	Short Form	Description
-cmdid <i>id</i>	-C <i>id</i>	Command identifier. Associates a Universal Event Monitor Server with the UEMLoad utility that started it.
-help	-h	Write this message.
-level	-l	Level of messages that will be issued.
-port <i>port</i>	-p <i>port</i>	Port number on which the local Universal Broker is listening. If this parameter is omitted, the Universal Broker-installed default is used.

-version	-v	Writes program version information.
----------	----	-------------------------------------

**DEFFILE [-deffile]**

Long Form	Short Form	Description
-deffile <i>filename</i>	n/a	Complete path to the definition file. This file can be used to specify any number of event definitions and event handlers. When used with the <b>-export</b> option, this is the name of the output file.

**EVENTDEF [-event\_id] [-comp\_name] [-event\_type] [-state] [-act\_date\_time] [-inact\_date\_time] [-tracking\_int] [-triggered\_id] [-rejected\_id] [-expired\_id] [-handler\_opts][[-filespec] [-min\_file\_size] [-rename\_file] [-rename\_file\_spec]**

Long Form	Short Form	Description
-act_date_time <i>date and time</i>	n/a	Date and time at which a UEM Server will begin testing for the occurrence of the specified event.  Format for <i>date and time</i> is <i>yyyy.mm.dd,hh:mm</i> . (The time must be expressed in 24-hour format.)  <i>date</i> can be omitted, but the comma must be used as a placeholder. If <i>time</i> is omitted, no comma is required.
-comp_name <i>compname</i>	n/a	Name of the UEM Server component to which this event should be assigned.
-event_id <i>id</i>	n/a	Unique identifier of an event definition.
-event_type <i>type</i>	n/a	Type of event. This parameter is required when adding records and updating type-specific values.
-expired_id <i>handlerid</i>	n/a	Event handler to execute when an event expires.
-handler_opts <i>string</i>	n/a	Literal string to pass to an event handler process.
-inact_date_time <i>date and time</i>	n/a	Date and time at which a UEM Server will stop testing for the occurrence of the specified event.  Format for <i>date and time</i> is <i>yyyy.mm.dd,hh:mm</i> . (The time must be expressed in 24-hour format.)  <i>date</i> can be omitted, but the comma must be used as a placeholder. If <i>time</i> is omitted, no comma is required.
-rejected_id <i>id</i>	n/a	Event handler to execute when an event occurrence is rejected.
-state <i>option</i>	n/a	Used to control whether or not the event is monitored by Universal Event Monitor.  Valid values for <i>option</i> are enable and disable.
-tracking_int <i>seconds</i>	n/a	Frequency with which a tracked event is tested for completeness.

-triggered_id <i>handlerid</i>	n/a	Event handler to execute when an event occurrence is triggered.
--------------------------------	-----	---

The following parameters are used when adding or updating event definitions with an event type of **FILE**.

Long Form	Short Form	Description
-filespec <i>filename</i>	n/a	Name of the file whose creation (and completion) Universal Event Monitor should detect. Wildcards can be specified.
-min_file_size <i>size[units]</i>	n/a	Smallest size a file can be in order for UEM to consider it complete. Valid values for <i>unit</i> are (b)ytes, (k)ilobytes, (m)egabytes, and (g)igabytes. If no units are specified, it will default to bytes. If this parameter is omitted, it will default to 0b (zero bytes).
-rename_file <i>option</i>	n/a	Specifies whether or not the file should be renamed before executing the event handler.
-rename_filespec <i>renamefile</i>	n/a	Format to use for the renamed file.

**HANDLER [-handler\_id] [-handler\_type] [-options] [-maxrc] [-file | -encryptedfile [-key] ] [-uerid [-pwd] ] [-cmd | -script [-script\_type] ]**

Long Form	Short Form	Description
-cmd <i>command</i>	n/a	Complete path to an application or script that should be executed by the handler.
-encryptedfile <i>filename</i>	-x <i>filename</i>	Universal Encrypted file that contains user account information that will be used for handler execution.
-file <i>filename</i>	-f <i>filename</i>	Complete path to a file that contains user account information that will be used for handler execution.
-handler_id <i>id</i>	n/a	Unique identifier of an event handler.
-handler_type <i>type</i>	n/a	Information that UEM needs when building a command string in order to execute a process for the event handler.
-key <i>key</i>	-k <i>key</i>	Encryption key used to encrypt the file specified by <b>-encryptedfile</b> .
-maxrc <i>returncode</i>	n/a	Highest return code that may be returned by the handler process to still be considered as having executed successfully.
-options	n/a	String value added to the command line that the UEM Server builds in order to execute an event handler process.
-pwd <i>password</i>	-w <i>password</i>	Password for the user account specified by <b>-userid</b> .

<code>-script <i>filename</i></code>	n/a	File that contains a set of script statements that will be executed by the handler.
<code>-script_type <i>type</i></code>	n/a	Type of script provided when the <b>-script</b> option is used. Windows servers treat <i>type</i> as a file extension, which results in the script being executed by the program associated with the extension.
<code>-userid <i>userid</i></code>	<code>-u <i>userid</i></code>	User account in whose security context the event handler process will execute.